

# Core 11.2.0.0 Device Management Guide

for Android and Android Enterprise Devices

April 19, 2021

For complete product documentation see: Ivanti [Product Documentation](#) page

# Contents

---

<b>Core 11.2.0.0 Device Management Guide</b>	<b>1</b>
<b>Contents</b>	<b>2</b>
<b>New features and enhancements</b>	<b>9</b>
<b>Android Deployment Models</b>	<b>10</b>
Android Enterprise devices	10
Android devices using the device administrator	10
Android MAM-only devices	10
AppConnect for Android devices	11
Samsung Knox Workspace devices	11
Wear OS by Google	11
<b>Setting up Core for Android Enterprise</b>	<b>14</b>
Android Enterprise Overview	14
Enabling Android Enterprise	16
Configuring the security policy for Android Enterprise devices	25
Configuring the lockdown policy for Android Enterprise devices	25
Removing Android Enterprise	25
<b>Setting up Core with a closed network / AOSP deployment</b>	<b>28</b>
Use cases	28
Enabling a closed network / AOSP deployment in Core	29
Creating a new Android Enterprise configuration	31
Provisioning the Android device	32
Managing the closed network / AOSP devices	33
<b>Registering Devices</b>	<b>36</b>
Registration methods	36
Terms of service	45
Visual privacy	49
Invite users to register	50
In-app registration for iOS and Android	51
Web-based registration for Android devices	54
ActiveSync device registration	56
Managing the Android Enterprise device life cycle	56
Provisioning an Android Enterprise device	62
Managing operators and countries	68
Specifying eligible platforms for registration	69
Setting the registration PIN code length for device user registration	70
Customizing registration messages	70
Configuring the default ownership for newly registered devices	76
Disabling analytics data collection	77
Disabling the QR code and registration URL	77
<b>Searching for Devices</b>	<b>78</b>
Basic searching	78
Advanced searching	79
Using the query builder	97

---

Using a manually edited search expression .....	98
Using both the query builder and manual editing .....	98
Negative operators with advanced search .....	100
Clearing an advanced search .....	102
Searching for retired devices .....	102
Searching for blocked devices .....	103
Saving a search criterion to a label .....	103
<b>Securing Devices .....</b>	<b>104</b>
Registration-related features and tasks .....	105
Reprovisioning a device .....	105
Using self service security features .....	105
Retiring a device .....	106
Retiring and deleting unused and retired devices .....	107
Security-related features and tasks .....	111
Lock .....	113
Unlock .....	113
Unlock AppConnect container .....	115
Encryption .....	115
Android Security Patch level .....	115
Wipe .....	116
Cancel Wipe .....	117
Selective Wipe .....	118
Block AppTunnels .....	118
Lost .....	118
Found .....	119
Locate .....	119
Reset device PIN .....	120
Force Device Check-In .....	120
Setting up background check-ins with APNs .....	121
Managed iBooks .....	121
Personal hotspot on/off switch .....	121
Using custom APN with Android devices .....	121
Custom Configuration support for Zebra devices .....	126
Reporting on managed devices .....	127
Setting the time zone of a device .....	130
<b>Managing Custom Attributes .....</b>	<b>131</b>
Assigning a custom attributes role .....	131
Adding custom attributes to users and/or devices .....	131
Viewing custom attributes available for users and/or devices .....	132
Viewing custom attributes assigned to users .....	133
Viewing custom attributes assigned to devices .....	133
Editing custom attributes for users and/or devices .....	133
Searching for custom attributes for users and/or devices .....	133
Exporting a log of the custom attributes for users and/or devices .....	134
Deleting custom attributes from users and/or devices .....	134

---

Setting custom attribute values for device or users .....	134
Pushing label attribute changes to devices and users .....	135
<b>Managing Policies .....</b>	<b>137</b>
Working with default policies .....	138
Importing and exporting policies .....	140
Viewing policy status and platform support .....	141
Security Policy .....	143
Device log encryption on Android devices .....	143
Sync policies and battery use .....	144
Work Schedule policy .....	144
Country changes and alerts .....	147
Android devices and the Client Is Always Connected option .....	147
Enabling SafetyNet attestation on Android devices .....	147
Working with Windows Update policies .....	150
Working with Samsung Android kiosk policies .....	150
Working with Android Quick Setup policies .....	150
Working with Samsung general policies .....	154
Working with Wear OS device policies .....	160
Notifications of changes to the privacy policy .....	163
Exporting the devices in the WatchList .....	163
<b>Managing Compliance .....</b>	<b>165</b>
Managing device compliance checks .....	165
Tiered compliance .....	172
Compliance actions policy violations .....	173
Viewing quarantine information .....	179
Viewing configurations removed due to quarantine .....	179
Custom compliance policies .....	180
<b>Managing Device Settings with Configurations .....</b>	<b>194</b>
Management of device settings with configurations .....	194
Configurations page .....	195
Default configurations .....	195
Displaying configurations status .....	196
Adding new configurations .....	196
Editing configurations .....	197
Deleting configurations .....	197
Exporting configurations .....	197
Importing configurations .....	198
Applying configurations to labels .....	198
Exporting the devices in the WatchList .....	198
Impact of changing LDAP server variables .....	199
<b>Configuring Email .....</b>	<b>200</b>
Exchange settings .....	200
Configuring POP and IMAP email settings (for iOS and macOS) .....	207
Synchronizing Google account data .....	207
Setting up Gmail with Android Enterprise .....	214

---

<b>Managing Wi-Fi Settings</b>	<b>216</b>
Wi-Fi settings	216
Wi-Fi profiles and password caching	218
Wi-Fi network priority for Android devices	218
Using Wi-Fi priority values	222
How an Android device chooses its Wi-Fi network	222
Wi-Fi network manual override behavior	223
Wi-Fi authentication types	223
<b>Managing VPN Settings</b>	<b>239</b>
VPN settings overview	240
Configuring new VPN settings	240
Check Point Capsule	240
Cisco AnyConnect (iOS only)	240
Cisco Legacy AnyConnect	241
F5 SSL	249
IKEv2 (iOS Only)	255
IKEv2 (Windows)	256
IPSec (Blue Coat)	256
IPSec (Cisco)	256
Juniper SSL	256
L2TP	264
Tunnel (iOS and macOS)	264
Tunnel (Android)	264
Tunnel (Samsung Knox Workspace)	265
Tunnel (Windows)	265
NetMotion Mobility VPN (iOS)	265
OpenVPN	265
Palo Alto Networks GlobalProtect	267
PPTP	279
Pulse Secure SSL	284
KNOX VPN Support	291
SonicWall Mobile Connect	308
Custom SSL	308
<b>Managing Certificates and Configuring Certificate Authorities</b>	<b>309</b>
Certificates overview	309
Managing certificates issued by certificate enrollment configurations	311
Supported certificate scenarios	312
Core as a certificate authority	314
Configuring Core as an independent root CA (Self-Signed)	314
Configuring Core as an intermediate CA	318
Mutual authentication between devices and Core	319
Certificates settings	332
Certificate Enrollment settings	333
Configuring a client-provided certificate enrollment setting	336
Configuring an Entrust CA	339

---

Configuring a GlobalSign CA .....	341
Configuring Core as the CA .....	344
Configuring OpenTrust CA .....	346
Configuring a single file identity certificate enrollment setting .....	348
Configuring SCEP .....	349
Configuring Symantec Managed PKI .....	354
Configuring Symantec Web Services Managed PKI .....	356
Configuring a user-provided certificate enrollment setting .....	359
<b>Android shared-kiosk mode overview .....</b>	<b>363</b>
Setting up the Android shared-kiosk mode .....	363
Configuring the Android shared-kiosk mode .....	365
User experience for staging and shared kiosk users .....	370
Suggestions for configuring shared-kiosk mode .....	372
<b>Working with Events .....</b>	<b>374</b>
About events .....	374
Managing events .....	374
Event settings .....	379
Customizing Event Center messages .....	399
Viewing and Exporting Events .....	407
<b>Troubleshooting Core and devices .....</b>	<b>410</b>
About Core logs .....	410
Audit log information .....	418
Best practices: label management .....	419
Device events .....	420
ActiveSync Device information .....	423
MDM events .....	423
Certificate events .....	424
App Tunnel events .....	425
Audit Logs use cases .....	430
MDM Activity .....	434
Certificate Management .....	434
Service Diagnostic tests .....	438
Device log encryption on Android devices .....	440
Encrypting device logs with your own certificate .....	441
Pull client logs for client devices .....	442
<b>Office 365 .....</b>	<b>444</b>
Office 365 App Protection overview .....	444
Office 365 App Protection policies .....	445
Office 365 App Protection configurations .....	454
Office 365 App Protection user groups .....	456
Office 365 App Protection reports .....	456
Office 365 App Protection settings .....	462
Zebra Support .....	462
<b>Azure Tenant .....</b>	<b>474</b>
Overview .....	474

---

From the Core administrator's point of view .....	475
From the device user's point of view .....	476
Apply the Intune license to device users .....	476
Adding Core as a compliance partner .....	477
Creating a conditional access policy in Microsoft Endpoint Manager .....	480
Connecting Microsoft Azure to Core .....	486
Creating a partner device compliance policy .....	492
De-provisioning of the Azure tenant .....	494
Installing Mobile@Work for iOS and Android .....	496
Required client device user action and use cases .....	496
<b>Samsung Knox Settings .....</b>	<b>498</b>
Android Samsung browser settings .....	498
Android Samsung Knox Container Settings .....	499
Activating the Samsung firmware E-FOTA license .....	506
Setting the system update policy for Android devices .....	506
Setting the firmware policy for Samsung devices .....	508
AppConnect for Samsung Knox devices .....	509
Samsung Knox support .....	509
<b>Help@Work for Android .....</b>	<b>512</b>
About Help@Work for Android .....	512
How Help@Work for Android works .....	513
Help@Work for Android setup overview .....	514
Installing TeamViewer on your desktop .....	514
Requesting a TeamViewer account .....	516
Creating a TeamViewer app .....	517
Enabling Help@Work in Core .....	520
Deploying the TeamViewer QuickSupport app .....	521
Starting a remote control session .....	522
<b>Language Support .....</b>	<b>529</b>
Translated versions of client apps .....	529
Selecting languages for Core messages .....	529
Setting the system default language .....	530
Changing language selection from the Admin Portal .....	531
<b>Samsung Android Kiosk Support .....</b>	<b>532</b>
About Samsung Android kiosk .....	532
Setting up Samsung Android kiosk mode .....	533
Samsung Android kiosk policy .....	534
Creating a Samsung Android kiosk configuration for multiple-app mode .....	538
Enabling and Disabling Samsung Android kiosk mode .....	539
An example of Samsung Android kiosk mode .....	540
Information about Samsung Android kiosk mode in device details .....	541
Samsung Android kiosk mode deployment notes .....	541
Setting kiosk policy for Android Managed devices .....	542
<b>The SMS Archive Feature .....</b>	<b>547</b>
About the SMS & Call Log Archive feature .....	547

---

Supported devices .....	547
Setting Up the SMS & Call Log Archive feature .....	547
Setting up encrypted SMS and call log archive encryption .....	549
Monitoring the SMS & Call Log archive .....	550
<b>Self-service User Portal .....</b>	<b>552</b>
User portal overview .....	552
Device management with the user portal .....	559
Assigning user portal device management roles .....	559
Customizing the self-service user portal .....	560
Configuring an end user Terms of Service agreement .....	566
Requiring user portal password change .....	567
Limiting devices per user by LDAP group membership .....	568
Configuring help desk contact information .....	571
User portal information for your users .....	572
Viewing device history logs from the self-service user portal .....	585
Disabling device history logs in the self-service user portal .....	586
<b>Setting up Android Enterprise with the alternative method .....</b>	<b>587</b>
Using the alternative method to set up Android Enterprise .....	587
Managing users for Android Enterprise .....	592



# New features and enhancements

This release includes the following new features and enhancements.

- **Content changes for rebranding and distribution:** Product documentation has been rebranded to align with Ivanti standards and is now available on the [Ivanti Product Documentation page](#).

This release does not include new Android-specific features or enhancements.

# Android Deployment Models

Core supports these deployment models for Android devices that are registered to Core:

- ["Android Enterprise devices" below](#)
- ["Android devices using the device administrator" below](#)
- ["Android MAM-only devices" below](#)
- ["AppConnect for Android devices" on the next page](#)
- ["Samsung Knox Workspace devices" on the next page](#)



Different devices can have each of these deployment models.

---

## Android Enterprise devices

*Android Enterprise* is Google's program for supporting Android devices for enterprise. Android Enterprise enables devices to have separate private and work profiles in BYOD deployments, and enables administrators to have broader control over enterprise owned and provisioned devices. Core supports Android Enterprise.

### Related topics

- ["Setting up Core for Android Enterprise" on page 14](#)
- "Managing Mobile Apps for Android Enterprise" in the *Core Apps@Work Guide*.

## Android devices using the device administrator

In this deployment model, Mobile@Work has Android device administrator privileges. With these privileges, Core is the Mobile Device Management (MDM) server for a registered device. As the MDM server, Core, with help from Mobile@Work, can enforce many MDM features, such as device password requirements, device encryption requirements, lockdown requirements, Samsung-specific features, and more. Core can also perform Mobile App Management (MAM) on the devices.

## Android MAM-only devices

In this deployment model, Core provides only Mobile App Management (MAM) features for a registered device. Core supports app installations using Apps@Work and most policies and configurations. However, because Mobile@Work does not have device administrator privileges, Core provides no MDM features to the device.

### Related topics

"Managing apps on MAM-only devices" in the *Core Apps@Work Guide*.

## AppConnect for Android devices

AppConnect for Android is Ivanti's solution that containerizes apps to protect data on registered Android devices. Each AppConnect-enabled app becomes a secure container whose data is encrypted, protected from unauthorized access, and removable. Because each user has multiple business apps, each app container is also connected to other secure app containers. This connection allows the AppConnect-enabled apps to share data, like documents.

Core supports AppConnect for Android only on:

- devices using the device administrator
- MAM-only devices

Core does not support AppConnect for Android on:

- Android Enterprise devices
- Samsung Knox devices

### Related topics

*AppConnect Guide for Core*

## Samsung Knox Workspace devices

Core supports Samsung Knox Workspace devices. Samsung Knox Workspace provides a secure container for corporate apps within a device.

Note The Following:

- You cannot deploy Samsung Knox Workspace and Android Enterprise containers on a device at the same time.
- Core does not support using both Samsung Knox Workspace and AppConnect apps on the same device.

### Related topics

["Samsung Knox Settings" on page 498](#)

## Wear OS by Google

Mobile@Work for Android utilizes the Google Wear OS app as a companion app for Android phones and tablets. The Wear OS app works with Mobile@Work in Android Enterprise deployments for Work managed device (DO) mode. The Wear OS app can be used by administrators to track the presence and inventory of apps on Wear OS devices in a corporate environment.

In Core, the Devices & Users page displays the information gathered from the watch, in addition to displaying all watches paired with the local device. If the connection to the Wear OS device is not established up to 1 week, Core will purge the data from the Device Details page > Wear OS tab. Mobile@Work will not display watches paired with remote devices.



Mobile@Work for Android (phone) receives Wear OS data from the Wear OS device (watch) and the Android system tends to cache this data for an unknown time frame. There is a possibility that the true value of the "Wear OS Client Installed" field in Device Details > Wear OS tab is delayed for several hours.

### Procedure

1. Create a Wear OS policy (see ["Working with Wear OS device policies" on page 160.](#))
2. View the paired watch in the Device Details page > Wear OS tab. (see ["Viewing paired watch information " below.](#))
3. Search for watch information in ["Advanced searching" on page 79.](#)
4. ["Removing paired watch information" on the next page.](#)

## Viewing paired watch information

Once you have a Wear OS policy in place, the Device Details page displays information about the Wear OS device that is connected to a mobile phone. This feature is applicable to Work managed device (DO) mode.

### Procedure

1. Select **Devices & Users > Devices**.
2. Select the device. The device details display below.
3. Select the **Wear OS** tab. The Wear OS device details and application inventory display.

TABLE 1. WEAR OS TAB

Item	Description
Last Check-in Time	Lists the time stamp of the last time the Wear OS app checked in. The value field is updated when the device checks in.
Android Wear Make	Displays the make of the Wear OS device.
OS version	Displays the OS of the Wear OS device.

TABLE 1. WEAR OS TAB (CONT.)

Item	Description
Model	Displays the model of the Wear OS device.
Brand	Displays the brand of the Wear OS device.
Serial Number	The serial number of the watch. The value of this item is blank if the device user has not granted permission on the watch app.

Below the initial Wear OS information, a table displays the name of the app, its version number and the app's identifier.

## Removing paired watch information

When the Mobile@Work client is erased (wiped) from the phone, the Wear OS data (including policies) stored in Core is purged after a specific time frame, only if the device is retired and the purge data setting is active. For example, if the device is retired and the "Delete Retired Device" field is set for 1 day, the data is purged from the Wear OS tab after 1 day the device is retired. Administrators can change the purge time frame (1-365 days) in Settings >Users & Devices > Delete Retired Devices.

### Related topics

["Working with Wear OS device policies" on page 160](#)

# Setting up Core for Android Enterprise

Core supports Android Enterprise devices.

- ["Android Enterprise Overview " below](#)
- ["Enabling Android Enterprise" on page 16](#)
- ["Configuring the security policy for Android Enterprise devices" on page 25](#)
- ["Configuring the lockdown policy for Android Enterprise devices" on page 25](#)
- ["Managing users for Android Enterprise" on page 592](#)
- ["Removing Android Enterprise" on page 25](#)

## Android Enterprise Overview

*Android Enterprise* is Google's program for supporting Android devices for enterprise. Android Enterprise enables devices to have separate private and work profiles in BYOD deployments, and enables administrators to have broader control over enterprise owned and provisioned devices. Core supports Android Enterprise. This support requires you to perform setup tasks with Google, Ivanti ([help.mobileiron.com](http://help.mobileiron.com)), and the Core Admin Portal.

## Modes for Android Enterprise devices

Android Enterprise devices that are registered with Core are in one of the following Android Enterprise modes:

- **Work Profile mode:** An Android Enterprise device is in Work Profile mode when it has a *work profile*. The device is typically privately owned (BYOD). Corporate data and apps are secured in the *work profile*, while the user's private data and apps are in the separate *personal profile*. Core has administrative control over the work profile. For more information see <https://developers.google.com/android/work/requirements/work-profile>.
- **Work Managed Device mode:** An Android Enterprise device that is in Work Managed Device mode is typically corporate-owned. The device has a single profile with corporate data and apps. This mode is only available on factory installed devices. If a device with this mode on it is wiped it will no longer be in Work Managed Device mode. Core has administrative control over the device, with more lockdown features available than for device using a work profile. For more information see: <https://developers.google.com/android/work/requirements/work-managed-device>.
- **Managed Device with Work Profile (COPE) mode:** An Android Enterprise device in this mode is an enterprise-owned device with personal data separate from the rest of the phone. It has a small client installed on it to separate personal data from the rest of the phone. This mode is only available on factory installed or factory reset devices. If a device in this mode is wiped it will no longer be in Work Managed Device mode. This mode requires:

- Mobile@Work 9.7 or supported newer versions.
- Only works on Android versions 8-10.
- A managed Google Play account
- If the account is enrolled with Google Domain, the device will be registered in the Work Managed Device mode.
- **Work Profile on Company Owned Devices mode:** This is similar to the Work Profile mode with a few additional device level configurations controlled from Work profile. Applies to Android versions 11 or supported newer versions.



In Android developer documentation, "work profile" is referred to as "profile owner" and "work managed device" is referred to as "device owner".

---

## Requirements for using Android Enterprise

To enable Android Enterprise for your enterprise and use it with Core, you need:

- A Google account that is not tied to Managed Google Accounts. That is, any Google account that is not managed by an enterprise can be used for enrolling with Android Enterprise.
- access to Google Play on Android devices and Core
- access to these URLs through outbound HTTP proxy:
- <https://accounts.google.com/o/oauth2/token>
- <https://www.googleapis.com>

See Outbound HTTP Proxy Set Up in the On-Premise Installation Guide.

## Requirements for using an Android Enterprise device in work profile mode

To enable an Android Enterprise device in work profile mode, the following is required:

- an Android Enterprise-capable device, running Android 5.0 or supported newer versions, with the Mobile@Work for Android app installed



The Mobile@Work app on Android devices shows whether the device is Android Enterprise-capable in the Settings > About > Product Details tab. Google provides a list of Android Enterprise-capable devices here: <https://enterprise.google.com/android/>.

---

- if using managed Google Play Accounts, Core automatically generates a Google User based on the UUID of the user.
- an Android Enterprise setting on Core (**Policies & Configs > Configurations**) applied by label to the device

## Requirements for using an Android Enterprise device in work managed mode

To enable an Android Enterprise device in work managed mode, all the ["Requirements for using an Android Enterprise device in work profile mode" on the previous page](#) are necessary. In addition, for work managed mode devices, you must enroll devices with either NFC, QR code, "afw#" tokens, Knox Mobile Enrollment (KME), or Google's Zero-Touch. For more information, see ["Provisioning an Android Enterprise device" on page 62](#).

## Requirements for using an Android Enterprise device in Managed Device with Work Profile mode and Work Profile on Company Owned Device mode

To enable an Android Enterprise device in Managed Device with Work Profile mode and Work Profile on Company Owned Device mode, all the ["Requirements for using an Android Enterprise device in work profile mode" on the previous page](#) and ["Requirements for using an Android Enterprise device in work managed mode" above](#) are necessary. In addition, for devices in this mode, you must select **Enable Managed Device with Work Profile on the devices** on the Android Enterprise setting. This setting applies to Android 8, 9, and 10 devices. For Work Profile on Company Owned Device mode, this setting applies to Android 11.0 devices.

## Enabling Android Enterprise

To enable Core to provide Android Enterprise features, you must perform setup steps with Google, Ivanti Support, and Core. You will associate a managed Google Play Account with Core. Note that this procedure does not share your enterprise's user names or email addresses with Google.

Depending on if you are a new or upgrading customer, the app distribution settings are different. If you are a new customer, the app distribution is set to per device by default. You cannot change this setting. For upgrading customers, you have a choice between apps distribution per user or per device. Also for upgrading customers, app distribution per user is selected by default. Many users have multiple devices. If a user has multiple devices, when app distribution is set per device then you can make a different set of apps available on each device.

### Procedure

1. Log into [help.mobileiron.com](http://help.mobileiron.com).
2. Click **Android enterprise Enrollments**.
3. Click **Create New Android enterprise Enrollment**.

The screen **Android enterprise Setup - Step 1** displays.

4. Click **Begin**.

Do not click **Alternate Setup Method**. If you used the alternate setup method in the past, see ["Using the alternative method to set up Android Enterprise" on page 587](#).

After clicking **Begin**, the screen **Android enterprise Setup - Step 2** displays.



5. Use the radio buttons to select a brand that matches the Core you are using.
6. Click **Submit**.
7. The Bring Android to Work page displays. Click **Sign In**.
8. Sign in with a Google account.
9. Click **Get Started**.
10. Enter your Organization details: name and agree to the **managed Google Play agreement**.
11. Click **CONFIRM**.
12. Click **COMPLETE REGISTRATION**.
13. The **Android enterprise Enrollment** page displayed in [help.mobileiron.com](https://help.mobileiron.com).

Click **Download Google JSON Enrollment file**.

The downloadService JSON file is downloaded.

Store it in an accessible file location for later use, such as if you need to enable Android Enterprise on another Core.

14. Log into the Core Admin Portal and go to **Services > Google**.
15. Upload the JSON file. Use the browse button to navigate to the JSON file you downloaded earlier in this procedure and click **Connect**.

The Google Play App Catalog dialog box opens with this warning message: If more than one Core instance is publishing the Google Play layout, you will be sending redundant (possibly conflicting) layouts to Google. This does NOT affect the distribution of apps, only the layout visible in Google Play. To use a Custom Layout in the Google Play store see "Distributing your enterprise apps in the Google Play App catalog or in Apps@Work" in the *Core Apps@Work Guide*. This step is optional.

16. Go to **Policies & Configs > Configurations > Add New > Android > Android enterprise** to go to the New Android enterprise (all modes) Setting dialog box.
17. Enter a Name and Description.
18. To make devices that this setting applies to be in a work profile, select **Enable Managed Device with Work Profile (on Android 10 and below.)** This setting applies to Android 8, 9, and 10 devices.

19. If you are in a European country that has GDPR requirements, Ivanti recommends selecting the **Prompt user for enabling location setting (Fully Managed, Managed Device with Work Profile and Work Profile on Company Owned Device)** check box. This is located in the Android 10 and higher only section of the New Android enterprise (all modes) Setting dialog box.



---

Administrators also need to select the **Prompt User to Enable Location Services if Wi-Fi/MTD configuration is pushed (Android enterprise)** check box in the Privacy Policy. If this is not selected, then Wi-Fi / MTD configurations will fail if the device user does not enable the device's location setting. For more information, see "Privacy policies" in *Getting Started with Core*.

---

20. Ignore **Auto update Mobile@Work app on the devices**. This option is no longer applicable. Using Google Play on the device, a user can specify that apps should be updated automatically. Click **Save**.
21. Apply the Android Enterprise setting to a label that is also applied to Android Enterprise-capable devices.  
For example, apply this setting to the built-in **Android** Label, or a custom label that is defined using the filter "android.afw\_capable = true". For more details about labels, refer to *Getting Started with MobileIron Core*.

For information on the other fields on the Android Enterprise setting, see:

- ["Enabling run-time permissions for Android Enterprise apps" on the next page](#)
- ["Adding a Google account to an Android Enterprise managed device" on page 20](#)
- ["Enabling an Android Enterprise VPN client to be always on" on page 21](#)
- ["Samsung Knox Dual Encryption \(DualDAR\) support" on page 504](#)
- ["For more information, see "VPN clients deployed either inside or outside Knox Workspace" on page 292." on page 22](#)
- Refer to the *Core Apps@Work Guide*.

#### Related topics

- ["Impact of removing the Android Enterprise setting from a device" on page 24](#)
- ["Removing Android Enterprise" on page 25](#)

## Impact of Android Enterprise setting to devices that are not Android Enterprise-capable

There is no impact to devices that are not Android Enterprise-capable to have the Android Enterprise setting applied. Some devices might become Android Enterprise-capable in the future, if the carrier upgrades the device's firmware.

To view the status of the Android Enterprise setting for a device:

- Go to **Devices & Users > Devices**.
- Open the device details for the device.
- Click the **Configurations** tab.
- Look for the Android Enterprise setting. The **Status** column displays:
  - **Pending:** The device has not yet confirmed that it has received the setting.
  - **Applied:** The setting is applied.
  - **Sent:** The device is not Android Enterprise-capable; the setting is ignored by Mobile@Work.

## Determining if a device is Android Enterprise-capable

You can check if a device is Android Enterprise capable by doing the following:

- On the device, open Mobile@Work. Tap the menu, and tap **Settings > About > Product Details**. Look for Android Enterprise (AFW) Support and see if its value is **Yes**.
- Once the device is registered, on Core go to **Devices & Users > Devices** page. Find the device and click the caret next to the display name to view the **Device Details**. Look for the “Android enterprise Capable” row. The value is true if the device is capable.

## Enabling run-time permissions for Android Enterprise apps

You can specify whether run-time permissions are automatically accepted or denied for Android Enterprise apps, or whether the device user is prompted to accept run-time permissions when each app requests them. You make this choice in the Android Enterprise setting. The choice you make applies to all Android Enterprise apps on devices that receive the Android Enterprise setting, based on the labels on the devices and the setting.

However, you can also specify run-time permissions for each permission for each app in the app’s settings in the Core App Catalog. The run-time permissions setting for the app in the App Catalog overrides the run-time permissions setting in the Android Enterprise setting.



The run-time permission settings are supported only on Android 6.0 or supported newer versions.

---

### Procedure

1. In the Core Admin Portal, go to **Policies & Configs > Configurations**.
2. Select an Android Enterprise setting.
3. Click **Edit**.
4. Select **Enable Runtime Permissions**.

The choices for run-time permissions display.

5. Select a run-time permission setting.
  - **User Prompt:** The device user is prompted to accept or deny each run-time permission that each app requests when it launches. This behavior also applies if you do not select **Enable Runtime Permissions**.
  - **Always Accept:** The run-time permissions are automatically accepted for each app when it launches. The device user is not prompted.
  - **Always Deny:** The run-time permissions are automatically denied for each app when it launches. The device user is not prompted.
6. Click **Save**.

### Related topics

"Features specific to Android Enterprise devices" in the *Core Apps@Work Guide*.

## Adding a Google account to an Android Enterprise managed device

As an administrator, you can add an additional Google account to an Android Enterprise managed device. This action enables you to control which Google account can be added to the Android Enterprise account. This account can only be administered or modified by you, the device administrator. The device user cannot modify or remove the added account or add another account to the managed profile.

### Procedure

1. In the Core Admin Portal, go to **Policies & Configs > Configurations**.
2. Select an Android Enterprise setting.
3. Click **Edit**.
4. Select **Add Google Account** check box in the **For Android 6.0 and higher only** section.

A Google Account field displays.

5. Enter the name of a Google Account you want to add.

The added account must be an account with a Google domain. The name can include any of the following Core substitution variables listed in the information popup next to the field. For example, you can enter:

- \$USER\_CUSTOM1\$
- \$LAST\_NAME\$. \$FIRST\_NAME\$@mycompany.com
- \$DISPLAY\_NAME\$@mycompany.com

6. Go to **Policies & Configs > Policies** and select the lockdown policy for this device.
7. Uncheck the **Allow the user to create and modify accounts** option if it is checked.

## Searching for devices that are registered as Android Enterprise devices

The Device Details pane for a device indicates the registration status of Android Enterprise devices. These values are:

- **Work Profile**
- **Work Managed Device**
- **Managed Device with Work Profile**
- **Work Profile for Company Owned Device**

You can use advanced search to find devices with the registration statuses of interest to you, and create dynamic labels for those sets of devices, if desired.

### Related topics

["Searching for Devices" on page 78](#)

## Enabling an Android Enterprise VPN client to be always on

You can specify an Android Enterprise VPN client as an Always-On client.

### Procedure

1. Go to **Policies & Configs > Configurations**.
2. Select an Android Enterprise setting.
3. Click **Edit**.
4. Select the **Always-On VPN** check box to display the **App Identifier** drop-down menu.  
The drop-down menu lists only apps that are configured to be installed as Android Enterprise apps.
5. Select a VPN app to apply the Always-On setting.
6. Click **Save**.

Note The Following:

The Android Enterprise setting displays in Device Details as Partially Applied with an error message in the following cases:

- The selected app is not installed on the device.
- The selected app is installed on the device, but it is not a VPN app, or it is a VPN app that does not support Always-On.

For Samsung Knox VPN settings, see ["KNOX VPN Support" on page 291](#).

## Moving in-house apps to a Knox v3 Workspace

You can move your in-house apps to a Knox v3 Workspace.

## Procedure

1. Go to **Policies & Configs > Configurations**.
2. Select **Add New > Android > Android enterprise**. The New Android enterprise (all modes) Setting dialog box is displayed.
3. Select the check box next to the **Move In-house app into workspace** field. Then the **Package Names** field is displayed.
4. Use the drop-down menu next to the **Package Names** field to select an app name.
5. Click **Save**.

For more information, see ["VPN clients deployed either inside or outside Knox Workspace" on page 292](#).

## Requiring a password for accessing the work profile

Typically, a password for an enterprise work profile should not be the same as the device password; however, some devices allow the two passwords to be the same.

Within the Work Challenge section, having the "Block unified password" option selected will force the device user to enter a password twice – first to unlock the device, second to unlock the work profile. (Using the "Block unified password" field helps disable the use one lock option on the device to force device users to specify a security challenge for apps running in the work profile.) This feature is supported on devices using Android 7 or supported newer versions.

- For devices using Mobile@Work 10.1.0.0 for Android and Android 9.0 or supported newer versions, select **Block unified password (device and work profiles)** in the Android Enterprise setting. This option appears when you select the **Work Challenge** option.
- For other devices, distribute an Android Enterprise setting with a work challenge configuration that has stricter requirements than the device passcode settings on the security policy for the devices. For example, stricter requirements include increasing the minimum password length in the **Minimum Password Length** field or increasing the number of complex characters in the **Minimum Number of Complex Characters** field.

For more information, see step 15 in the procedure below.

## Procedure

1. In the Core Admin Portal, go to **Policies & Configs > Configurations**.
2. Select an Android Enterprise setting.
3. Click **Edit**.

4. In the For Android 7.0 and higher only section, select the **Work Challenge** check box. When a work challenge is set, the administrator can block device passcode matching the work profile. This is to enforce separate work and device passwords so that device users do not unlock the work profile at the same time as unlocking the device.

The Password fields display for configuring your work challenge requirements.

5. Select the Password Type:
  - **Simple PIN:** Includes repeated characters, or ascending/descending characters, for example, 123 or CBA.
  - **Complex PIN:** Select **On** to include numbers that are not repeated and should not be in a sequence, for example, 1234, 2468, 9876. An example of repeating digits is 4444.
  - **Alphanumeric:** At least one letter and one number is required.
6. Set **Minimum Password Length** to the minimum password length ranging from 1 to 16 numbers or characters.
7. Set **Maximum Inactivity Timeout** to the maximum time allowed for the device to be inactive before the user must reenter the work challenge to access the work profile. This may be set to **Never** to prevent timeout.
8. Use **Minimum Number of Complex Characters** to set the minimum number of complex characters required in the password. Complex characters are special characters that are not numbers or letters, such as !, \*, and #.
9. Set the **Maximum Password Age** to the number of days until the user must change the work challenge.
10. Set **Maximum Number of Failed Attempts** to the maximum number of attempts to enter the correct password in one login. The default value for failed attempts is 10. When the maximum number of attempts is reached, the work profile is retired.
11. Set **Password History** to how many old work challenge passwords are stored so that the device user cannot repeat them.
12. Select **Block Fingerprint** to prevent a device user from using a fingerprint to replace the work challenge password.



Both the **Block Iris Scan** and **Block Face unlock** fields require either a Samsung device running Samsung OS 7.0 or supported newer versions or a non-Samsung device running Android 9.0 or supported newer versions.

---

13. Select **Block Iris Scan (Android 9 or Samsung only)** to prevent a device user from using an iris scan to replace the work challenge password.

14. Select **Block Face unlock (Android 9 or Samsung only)** to prevent a device user from using a face scan to replace the work challenge password.
15. Select **Block unified password (device and work profiles)** - by selecting this option, the administrator forces the device user to set a secondary password for the work profile. The system shows the security challenge when the user attempts to open any work apps. This feature is supported on devices using Android 7 or supported newer versions. If this field is de-selected (default), then the device user can use the same password for unlocking the device and the work profile.

## Impact of removing the Android Enterprise setting from a device

Removing the Android Enterprise setting from a device causes the device to become retired.

The Android Enterprise setting can be inadvertently removed from a device if:

- the setting is applied to a dynamic label instead of a built-in label, and
- the device is dynamically removed from the label for any reason, or
- the Android Enterprise setting is manually removed from a label shared with a device.

Removing the setting from the device causes the following to happen:

TABLE 1. REMOVING ANDROID ENTERPRISE SETTING

Android Enterprise status	If Android Enterprise setting is removed:
Work Profile mode	<ul style="list-style-type: none"><li>• Starting in Core 10.7, Core will not display the device as registered. Instead, the Mobile@Work app will notify Core that the device is retired before deleting the work profile.</li><li>• User can re-register the device. The user must re-enable Mobile@Work through the Google Play store.</li></ul>
Work Managed Device (DO) mode	<ul style="list-style-type: none"><li>• The device becomes unregistered and performs a factory reset.</li><li>• The device can be re-registered at a later time.</li></ul>
Work Profile on Company Owned Device mode	<ul style="list-style-type: none"><li>• Same as for Work Managed Device (DO) mode.</li></ul>

### Related topics

["Removing an Android Enterprise configuration causes device to retire" on page 26](#)



## Configuring the security policy for Android Enterprise devices

Most security policy settings for Android Enterprise devices are the same as the settings for other Android devices. However, note that a few settings in the security policy are specific to Android Enterprise devices. These settings are:

- **Block notifications on lock screen** (Android Enterprise Work Managed Devices only)
- **Allow only redacted notifications on lock screen** (for Android Enterprise Work Profile modes only)
- **Bypass Factory Reset Protection** (Applicable to Android Enterprise Work Managed Devices and Work Profile on Company Owned Devices.)

Also in the security policy, you specify compliance actions for various security violations. When a compliance action includes quarantine, on Android Enterprise devices, all Android Enterprise apps and functionality are hidden except for Downloads, Google Play Store, and the Mobile@Work app.

When configuring Zebra OTA (Over-the-Air) service, only for Work Managed Zebra devices is supported.

### Related topics

- "Security policies" in *Getting Started with MobileIron Core*
- "Add Compliance Action table" in *Core Device Management Guide for Android and Android Enterprise Devices*

## Configuring the lockdown policy for Android Enterprise devices

You can configure the lockdown policy to apply lockdown settings to Android Enterprise devices. Whether a lockdown policy field applies to an Android Enterprise device depends on the Android Enterprise mode that the device is registered in. The modes - Work Profile Mode, Work Managed Device Mode, Managed Device with Work Profile (COPE) mode and Work Profile on Company Owned device - are described in the "[Android Enterprise Overview](#)" on page 14



For Android Enterprise Work Profile and Work Managed Device modes, only the camera and phone are included in the package identifier. Enable all system apps by logging into the Admin Portal and going to **Policies & Configs > Policies > Add New > Lockdown**.

---

### Related topics

"Lockdown policies" in *Getting Started with MobileIron Core*

## Removing Android Enterprise

This section addresses the removal of Android Enterprise-related items.

## Removing an Android Enterprise configuration causes device to retire

When you enroll an Android device on a dynamic label using Android for Work with Work Profile mode, Work Managed Device mode, and Managed Device with Work Profile (COPE) mode and later modify the label criteria to exclude the device, the following occurs:

- the device's client configuration is removed
- the device becomes retired and displays in the Retired Device's Dashboard.

This is applicable to Android Enterprise devices in all modes:

- Work Managed Device (Device Owner) mode - a device retire causes a factory reset
- Work Profile mode - a device retire causes deletion of the work profile
- Managed Device with Work Profile (COPE) mode - a device retire causes a factory reset. Applicable to Android devices versions 8-10.
- Work Profile on Company Owned device - a device retire causes a factory reset. Applicable to Android versions 11 or supported newer versions.

## Removing the Android Enterprise account in Core

You can remove the Android Enterprise account from Core, severing Core's connection with Google. This removal causes devices to retire when they check in.

### Procedure

1. In the Core Admin Portal, go to **Services > Google**.
2. Under **Android enterprise**, click **Remove** to open the **Remove Account** dialog.
3. If you wish to remove the Android Enterprise account with Core, click the check box for "I understand" and then click **Remove**.

Core will retire Android Enterprise devices when they next check in.

## Removing your managed Google Play account

You can remove your managed Google Play account if you no longer need it.

### Procedure

1. Login to [help.mobileiron.com](https://help.mobileiron.com).
2. Select **Android enterprise Enrollments**.
3. Click on your managed Google Play Account.

4. The **Android enterprise Enrollment Detail** screen displays.
5. Click **Delete**.

# Setting up Core with a closed network / AOSP deployment

There are situations where the onboarding, registration and management of devices is limited and requires a different approach. Examples of these kinds of situations are:

- In an environment that does not have connectivity to Google mobile services (GMS) due to restrictions in the organization or due to a closed network.
- In countries where Google mobile services are not available.
- Where devices that do not have Google mobile services but vendors have enabled Android Enterprise AOSP (Android Open Source Project.)

With Core version 11.0.0.0, Core supports a new mode of deployment:

- **Integrated deployment (GMS/Non-GMS)** - the entire Core instance serves devices in full Android Enterprise mode (for example, Samsung devices) and also devices that do not have GMS (for example, AR/VR devices.)

This feature applies to Android 6 or supported newer versions.

## Use cases

AOSP deployment can work side-by-side with Android Enterprise deployment.

Supported modes of registration supported:

- Device Admin mode
- Device Owner mode

Below are the possible use cases for this feature.

TABLE 1. USE CASES FOR CLOSED NETWORK / AOSP DEPLOYMENT

Use Case	Expected Result
Only the AOSP configuration is pushed	AOSP in Device Admin or Device Owner mode.
Both AOSP and Android Enterprise configurations are pushed	Android Enterprise configuration takes priority over AOSP.
Device is registered in AOSP and the Android Enterprise configuration is pushed to the registered device	The registered device retains AOSP mode. Android Enterprise configuration applies only to fresh registrations.

**Process of setting up:**

1. ["Enabling a closed network / AOSP deployment in Core" below.](#)
2. ["Creating a new Android Enterprise configuration" on page 31.](#)
3. ["Provisioning the Android device" on page 32.](#)
4. ["Managing the closed network / AOSP devices" on page 33.](#)

Once you have AOSP deployment in place, you can [disable AOSP / closed network deployment](#).

## Enabling a closed network / AOSP deployment in Core

With the Core version 11.0.0.0 release, Administrators have the ability to enable a closed network / AOSP deployment in Core whether Android Enterprise is already enabled or not. Once the closed network / AOSP is deployed, Administrators can optionally switch off Android Enterprise on the instance.

Note The Following:

- Core does not impose any "special" restrictions for Google calls, both on the client and on the server. It is completely the device user's own decision as to how to handle public apps pushed from Core when the device is registered in Work Managed Device - Non GMS mode.

## Procedure

1. In Core, go to **Services > Google**.
2. Scroll down and find the **AOSP/Closed Network Devices** tile.




3. Select the **Enable registration of fully managed device in Non-GMS mode** check box and then click **Save**.

## Disabling AOSP / closed network deployment

You can disable the AOSP / closed network deployment. Disabling AOSP in the Google Services page will cause the registered devices in Device Owner (DO) mode to retire. Devices in Device Admin (DA) mode will stay intact.

1. In the **AOSP/Closed Network Devices** tile, de-select the check box and then click **Save**.

The Disable AOSP/Closed Network Devices Registration dialog box opens.



2. Select the **I understand the implications and want to remove the configuration** check box and then click **Confirm**.

## Creating a new Android Enterprise configuration

Administrators will need to create a new Android Enterprise configuration for the closed network or for an AOSP deployment, and then add the new configuration to a label.

1. Go to **Policies & Configs > Configs**.
2. Click **Add New > Android enterprise Setting**.  
The New Android enterprise (all modes) Setting dialog box opens.
3. Enter a **Name** and **Description**.
4. Select the **Enable Closed Network/AOSP deployment** check box. All other options in the dialog box become hidden except Enable Runtime Permissions.
5. Click **Save**.
6. Apply a label to the configuration.

Note The Following:

- If two Android Enterprise configurations (one with Android for Work and one with AOSP) are pushed to the same device, the Android for Work configuration takes priority.

- As FCM services will not be available, Ivanti recommends administrators to modify the **Sync Policy > Sync Interval** field to 30 minutes or to the lowest value as needed by the administrator.
- Once the **Enable Closed Network/AOSP deployment** check box in the Android Enterprise Setting (configuration) dialog box is enabled, after saving, the option will be greyed out. There is no option for the administrator to disable it. As a workaround, the administrator should either remove the label or delete the configuration.

## Provisioning the Android device

For a closed network / AOSP deployment, only Android Enterprise devices in Work Managed Device mode can be provisioned. In order to provision the device, the administrator needs to download the Device Policy Controller (DPC.)

### What the Administrator does:

- The Administrator adds the URL for the IIS server (where the Device Policy Controller (DPC) is hosted) into the Provisioner app and generates a QR code.
- The Android device is rebooted to factory setting.

For more information, see "[Provisioning Android Enterprise devices using a QR code or NFC bump](#)" on [page 62](#).

### What the device user does:

#### Provisioning Non-GMS devices

1. Sideload and install the Mobile@Work app onto the device.
2. Run the below command to provision the device into Device Owner (DO) mode. Be sure that the Mobile@Work app is installed before running the command.  

```
adb shell dpm set-device-owner com.mobileiron/.receiver.MIDeviceAdmin
```
3. Register the device by entering the server URL, username, and password.

#### Provisioning GMS devices

1. Device user scans the QR code. The DPC is downloaded onto the device.
2. Mobile@Work client opens and requests the device user to enter the server URL.
3. The device user enters the server URL, username and password.
4. The device registration is completed.



# Managing the closed network / AOSP devices

## Registration status values

Upon registration to Core, the device sends all device details to Core. The **Device Details page** > **Registration Status** field lists the following values:

TABLE 1. REGISTRATION STATUS VALUES

Action	Registration Status value
Android Enterprise configuration sent to device	Work Managed Device
Closed network / AOSP configuration sent to device	Work Managed Device - Non GMS
Device does not receive the AOSP configuration	The device is retired (factory reset.)

## Closed network / AOSP device capabilities

After successful registration, devices will be able to receive and provision the following:

TABLE 2. CLOSED NETWORK / AOSP DEVICE CAPABILITIES

Type	Description
Configurations	<ul style="list-style-type: none"> <li>• Android Enterprise</li> <li>• Android XML</li> <li>• Android APN</li> <li>• Exchange</li> <li>• MTD</li> <li>• Certificates</li> <li>• VPN</li> <li>• Wi-Fi</li> </ul>
Policies	<ul style="list-style-type: none"> <li>• Android Quick Setup</li> <li>• Android Kiosk</li> <li>• Firmware policy</li> <li>• Security</li> <li>• Privacy</li> <li>• Lockdown</li> <li>• MTD local actions</li> <li>• MTD anti-phishing</li> <li>• Compliance policy</li> <li>• Sync policy</li> </ul>
App Management	<ul style="list-style-type: none"> <li>• Support for in-house apps with configurations/restrictions</li> <li>• Apps@Work</li> </ul>
Standard device management capabilities	All the supported device management commands of Android Enterprise work for closed network / AOSP deployment, except "Shared Kiosk- Signout."

## App Management

- With a closed network / AOSP deployment, devices registered as a non-GMS device will have access to all in-house applications through Apps@Work.

- In non-closed networks / AOSP deployments, all apps need to be uploaded as in-house apps using their .apks since there is no access to Google's application bundles.
- When applying app restrictions, make sure to have the **Install this app for Android enterprise** and **Enable AOSP app restrictions** check boxes selected.

For more information about app management, see "Adding in-house apps for Android" in the *Core Apps@Work Guide*.

# Registering Devices

A device is available for management by Core after it has been registered by a device user or administrator.

The topics in this section include the following advanced topics:

- ["Registration methods" below](#)
- ["Terms of service" on page 45](#)
- ["Visual privacy" on page 49](#)
- ["Invite users to register" on page 50](#)
- ["In-app registration for iOS and Android" on page 51](#)
- ["Registering Android devices" on page 38](#)
- ["Web-based registration for Android devices" on page 54](#)
- ["ActiveSync device registration" on page 56](#)
- ["Managing the Android Enterprise device life cycle" on page 56](#)
- ["Provisioning an Android Enterprise device" on page 62](#)
- ["Managing operators and countries" on page 68](#)
- ["Specifying eligible platforms for registration" on page 69](#)
- ["Setting the registration PIN code length for device user registration" on page 70](#)
- ["Customizing registration messages" on page 70](#)
- ["Configuring the default ownership for newly registered devices" on page 76](#)
- ["Disabling analytics data collection" on page 77](#)

Refer to the *Getting Started with MobileIron Core* for the most commonly used registration topics, such as:

- Single device registration
- Bulk device registration
- Tracking registration status
- Restricting the number of devices a user registers
- Registration considerations

## Registration methods

Registering a device designates it for management by Core.

## Before you begin

["Setting the registration PIN code length for device user registration" on page 70](#)

The following registration methods are available:

- ["Admin invites users to register" below](#)
- ["In-app registration" on the next page](#)
- ["Registering Android devices" on the next page](#)
- ["Registration methods" on the previous page](#)
- ["Registration methods" on the previous page](#)
- ["Users register additional devices" on page 42](#)
- ["Admin registers ActiveSync devices" on page 42](#)
- ["Registration methods" on the previous page](#)
- ["Registering Android devices via web portal \(MIRP\)" on page 43](#)
- ["Registering Samsung devices using Samsung Knox Mobile Enrollment" on page 44](#)

You can also register Android devices using the Provisioning app. See ["Provisioning an Android Enterprise device" on page 62](#)

The process resulting from these methods may vary by device OS.

## Admin invites users to register

For users who are mobility savvy and do not require significant assistance, you can send an invitation and enable them to register their own phones. You can send an invitation to multiple users from the Users Management screen. The invitation includes instructions on how to log into the user portal to register phones.

The administrator needs to know the following information for the device:

- phone number (if any)
- country
- platform

## Related topics

["Invite users to register" on page 50](#)

## In-app registration

One way to reduce the load on IT personnel is to instruct iOS and Android users to download the Core app directly from the App Store on iTunes or from Google Play and initiate registration from within the Mobile@Work app.

### For iOS devices

1. Go to **Settings > System Settings > iOS > MDM** and select the Send email to user and notification to client if MDM profile is not installed check box.
2. Device users of iOS 12.2 and later will need to download Mobile@Work, manually navigate to Settings view and download the MDM profile.
3. Device users then complete the registration process by responding to registration prompts. If Core detects that the MDM profile has not yet been installed, upon the next device check-in, Mobile@Work will display a notification asking the device user to re-enroll.



---

In iOS 13, the option to "Allow Always" was removed from the iOS Settings app. Instead, a dialog box displays requesting device users to enable tracking when the Mobile@Work app is running. Mobile@Work opens iOS Settings where device users can choose "Ask Next Time" or "Never". Ivanti recommends device users to enable tracking. This change applies to all versions of iOS 13 or supported newer versions. Mobile@Work for iOS does not track device users' location without consent.

---

### Administrator tasks

- This feature depends on access to the Core Gateway; therefore, the corresponding port must be properly configured. See the Pre-Deployment Checklist in the *On-Premise Installation Guide* for details. The User Portal role must be assigned to the user.
- To auto-populate the Core server name during registration, the following setup is required:
  - The user associated with the device must be known as an LDAP user or defined as a local user.
  - To auto-populate based on the device phone number, see ["Auto-populating the Core server name based on email address" on page 52](#) for details.
  - To auto-populate based on the email address, you must register your VSP with Core.
- Schedule email reminders, see ["Customizing registration messages" on page 70](#)

## Registering Android devices

As with other types of devices, you can configure whether you want Android device users to enter a password, PIN, or both during registration. This can be done with managed and un-managed Android devices.



If upgrading to Core 10.6.0.0, and you have your Device Registration set to a specific authentication setting (Password, Registration PIN or Password and Registration PIN), the setting will be retained as a default. If you are registering devices for the first time using Core 10.6.0.0 or supported newer version, the default setting is Password.

## Before you begin

["Setting the registration PIN code length for device user registration" on page 70](#)

## Procedure

1. Upload the APK file for Mobile@Work for Android to a secure server. This server must be accessible to device users.
2. For unmanaged Android devices:
  - a. Go to **Settings > System Settings > Users & Devices > Device Registration**.
  - b. In the In-App Registration Requirement field, select one of the following:
    - **Password** - device user will be required to enter username and password.
    - **Registration PIN** - device user will be required to enter a registration PIN.
    - **Password and Registration PIN** - device user will be required to enter a username, password, and registration PIN.
  - c. Click **Save**.
3. For Zero Touch and Samsung Knox Android managed devices:
  - a. Go to **Settings > System Settings > Users & Devices > Device Registration**.
  - b. In the Zero Touch and Samsung Knox Mobile Enrollment field, select one of the following:
    - **Password** - device user will be required to enter username and password.
    - **Registration PIN** - device user will be required to enter a registration PIN.
    - **Password and Registration PIN** - device user will be required to enter a username, password, and registration PIN.
  - c. Click **Save**.

For more information, see ["Provisioning Android Enterprise devices using Zero Touch" on page 66](#) and ["Registering Samsung devices using Samsung Knox Mobile Enrollment" on page 44](#)

4. For all other managed Android device types, in the Managed Devices/Device Owner (afw#, QR code, NFC) field, select one of the following:
  - **Password** - device user will be required to enter username and password.
  - **Registration PIN** - device user will be required to enter a registration PIN.
  - **Password and Registration PIN** - device user will be required to enter a username, password, and registration PIN.

Click **Save**.

For more information on registering using afw# token, QR code or NFC bump, see ["Provisioning an Android Enterprise device" on page 62](#).

5. In **Devices & Users > Add Single Device**, make sure the "Include Registration PIN only for Android Company-Owned Device Enrollment" field is selected.
6. Click **Register**.

The Registration Instructions dialog box opens.
7. Copy the Registration PIN for sending to the device user. If you are intending to send an email invitation to device users, you can skip this step.
8. Set up the email invitation template. See ["Customizing registration messages" on page 70](#)
9. Send the email invitation to device users. Core will automatically add the Registration PIN within the invitation.
10. Once the device user has registered, monitor devices for status in **Devices & Users > Devices**. The Android Automated Enrollment field lists the values as appropriate for the type of Android setup:
  - Google Zero Touch
  - Knox Mobile Enrollment
  - Non Zero Touch AE Enrollment



The Android Automated Enrollment field is valid for Core 10.6.0.0 or supported newer versions. If an "Unknown" value displays, it indicates a previous version of Core was used and the "In-App Registration Requirement" field in **Settings > System Settings > Users & Devices > Device Registration** was used. It can also mean that an old client was used with Core version 10.6.0.0 or later.

---

## Registration restrictions for Android devices

From the **Device Registration** page, you can specify conditions that Android devices must meet to qualify for registration. You can limit Android devices by operating system (OS) version, security patch level, or by manufacturer and model.



## Before you begin

- Complete ["Registering Android devices"](#) on page 38.

## Procedure

1. From the **Settings > System Settings > Users & Devices > Device Registration** page, scroll down to the **Restrictions for Android** section. Choose from these optional filter settings:

FIGURE 1 . REGISTRATION RESTRICTIONS FOR ANDROID DEVICES

**Restrictions for Android**

Minimum OS Version:

Minimum Security Patch Level: Within  days

Allowed/Blocked devices list: ☒ None ?

- ☒ Create a list of Allowed devices  
Only allow devices from these manufacturers to be registered
- ☐ Create a list of Blocked devices  
Prevent devices from these manufacturers to be registered

MANUFACTURER NAME	MODEL	
Google	Pixel	✕
Samsung	<input type="text" value=""/>	✕

Minimum SafetyNet Certification: ☒ None ☐ Basic ☐ Certified

2. **Minimum OS version:** Select a minimum OS version from the drop-down menu from Android 5.0 through 11.0 or supported newer versions. The default is **None**.
3. **Minimum Security Patch Level:** Enter an integer specifying within how many days a device can be non-compliant for the minimum security patch level before rejecting the device. The default is **None**.

4. **Allowed/Blocked devices list:** The options are:

- **None:** The default. Do not create an Allowed or Blocked devices list.
- **Create a list of Allowed devices:** Only allow devices of these makes and models to be registered.
- **Create a list of Blocked devices:** Prevent devices of these makes and models to be registered.

To enter specific manufacturers and models, click **Add+** to open text fields in the **Manufacturer Name** and **Model** columns. Enter allowed or restricted device information.

5. Click **Save**.

#### Related topics

["Disabling the QR code and registration URL" on page 77](#)

## Users register additional devices

Once a device has been registered, an authorized user can use the user portal to register additional devices without administrative help. This is often used with adding devices for users who do not require assistance.

#### Prerequisites

- Users must have the **User Portal** role assigned, with the **Device Registration** option enabled.
- The user needs to know the following information for the device:
  - phone number (if any)
  - country
  - platform

#### Related topics

["Self-service User Portal" on page 552](#)

## Admin registers ActiveSync devices

If you have a Sentry configured, then you can see the devices that are connecting to your ActiveSync server. To incorporate these devices into your Core inventory, you can use the Register button in the ActiveSync Associations screen. This is often used with devices accessing email via ActiveSync.

#### Prerequisites

- Sentry must be installed and configured.
- The user (local or LDAP) associated with the device must be available for selection at the time of registration.
- For iOS, Android, and Windows devices, the User Portal role must be assigned to the user.

- You need to know the following information for the device:
  - phone number (if any)
  - country code
  - platform

### Related topics

["ActiveSync device registration" on page 56](#)

## Registration via user portal

The user portal can be used to streamline the registration process. See ["Self-service User Portal" on page 552](#) for more information.

## Registering Android devices via web portal (MIRP)

Administrators who use web portals (such as the BYOD Portal) to initiate registrations can provide a URL in the web portal to help device users register Android devices with little or no typing. Users just download Mobile@Work from Google Play and then tap the URL in the web portal from the device. Tapping the URL launches the Mobile@Work app and populates the registration screen with the available information, such as the username. The information that is available depends on the web portal being used.

The URL is based on the Registration Protocol (MIRP). The link you provide on the web portal must have the following format:

`mirp://<Core URL> <parameters>`

The following parameters are available:

- user: The username for the device user.
- pin: The PIN generated for this user for PIN-based registration.

Examples:

- `mirp://mycore.mycompany.com&user=android&pin=1234`

If you have configured Core for PIN-only registration, device users will be automatically registered without having to enter any credentials.

- `mirp://mycore.mycompany.com&user=android`

Device users will be prompted to enter credentials to complete registration. The credentials include either a PIN or password, depending on how you configured Core.

Note The Following:

- The ampersand character is reserved. If you require an ampersand in a field value, it must be URL-escaped to a character code (i.e.,%26).
- Unsupported parameters will be ignored.

## Registering Samsung devices using Samsung Knox Mobile Enrollment

Core supports using the Samsung Knox Mobile Enrollment process to register qualified Samsung devices with Core.

Using Samsung's Knox Mobile Enrollment process, once the process is set up, qualified devices are automatically enrolled and registered to Core when the end user activates the device for the first time.

### Requirements

- A CSV file that provides a list of device IMEI numbers or serial numbers, and optionally:
  - a username
  - a registration PIN and/or password

If you configured registration to use a PIN, include a PIN in the registration file. If you configured registration to use a password, include a password. If you configured registration to use both a password and a PIN, include only one of them in the CSV file. You configure the registration requirements on the Admin Portal at:

**Settings > System Settings > User & Devices > Device Registration > Zero Touch and Samsung Knox Mobile Enrollment.**

NOTE: If username or PIN or password is not in the CSV file, the user must provide them.

- A Samsung Knox account and use of the Samsung Knox Mobile Enrollment portal
- Samsung Knox devices (see Samsung portal for a list of qualified devices)



Mobile@Work for Android is automatically installed during the enrollment process.

---

### Benefits

- Bulk enrollment of devices: No user interaction is required to download the Mobile@Work app. The app is installed automatically as part of the enrollment process. No access to Google Play is required.
- No need for users to enter credentials (unless desired); credentials are populated in the background.
- Auto-Enrollment: Once a device is enrolled into an UEM/MDM via Samsung's mobile enrollment process, the MDM software is always be imposed even if the device is erased, inadvertently or maliciously, until you remove the device from the Samsung Knox Mobile Enrollment portal or retire
- Choice of enrollment options: you can choose to enroll the device using NFC bump, a URL, or

automatic activation when a device is first powered on.

- Multiple Core (or Cloud) servers can participate in the program.

## Instructions

Complete instructions for setting up and using the Samsung Knox Mobile Enrollment portal with Core are available in the Ivanti knowledge base article, here:

[Samsung Knox Mobile Enrollment with Core Quick Start Guide](#)

## Related topics

You can also register Android devices using the Provisioning app. See "[Provisioning an Android Enterprise device](#)" on page 62

## Terms of service

You can optionally define terms of service text to be displayed to users during:

- device registration on iOS, macOS, Android, and Windows devices
- logging into AppConnect apps on iOS and Android devices

Device users must accept the terms of service before they can continue with registration or with accessing AppConnect apps.

You can search for users by terms of service acceptance and date of acceptance. You can create one terms of service agreement for each supported language. The same terms of service text is used for both registration and AppConnect app access.

Regarding terms of service during registration:

- Presenting the terms of service is part of the registration process when using Mobile@Work. Users must accept the terms of service agreement in order to complete registration.
- Configuring a terms of service agreement or updating it applies only to users who register after you complete the configuration. Previously registered users do not accept the terms of service agreement. However, you can require existing users to accept the terms of service agreement by retiring their devices and requesting them to re-register.
- If both custom terms of service and the privacy policy are enabled, users will have to accept the privacy policy first.

Regarding terms of service for accessing AppConnect apps:

- In addition to providing the terms of service text, you must enable terms of service on the AppConnect global policy.

- Also on the AppConnect global policy, you indicate whether:
  - users must accept the terms of service each time they are prompted for their AppConnect passcode or biometric authentication. If you update the terms of service text for a user's language, the user sees the updated text on all subsequent AppConnect logins.
  - the user must accept the terms of service only once. However, if you update the terms of service text for a user's language, on the next AppConnect login, the user is prompted once more to accept the terms of service.
- If you delete the terms of service, but do not disable it on the AppConnect global policy, users continue to be prompted to accept the terms of service with whatever the last terms of service text was.
- For information about enabling terms of service when logging into AppConnect apps, see "Configuring the AppConnect global policy" in the *AppConnect Guide for Core*.

## Creating a terms of service agreement

### Before you begin

Set up the system default language as described in ["Setting the system default language " on page 530](#).

If there is no terms of service available in the primary language of a given device, or if more than one agreement is defined for more than one device language on a device, the terms of service agreement defaults to the system default language.

### Procedure

1. In the Admin Portal, go to **Settings > System Settings > Users & Devices > Registration**.
2. Scroll down to the **End User Terms of Service** section.
3. Click **Add+**.
4. Select the language for the terms of service.
5. For **Type**, select **System** for iOS, macOS and Android devices. Select **AAD enrollment** for Windows devices.
6. Enter the text for the terms of service.  
You can adjust the editor to use rich or plain text by clicking the Source Edit icon.
7. Click **Save**.
8. Optionally, repeat steps 3 through 6 to add a terms of service agreement for each supported language, and for Windows devices versus iOS, macOS, and Android devices.

Note The Following:

- To edit a terms of service agreement, click the **Edit** link next to the relevant language.
- To delete a terms of service agreement, click the **Delete** button next to the relevant language.

## Searching for devices by terms of service agreement criteria

You can search for devices based on whether users have agreed to the terms of service, and the date on which terms of service were accepted.

The following table describes the searchable criteria related to terms of service. Corresponding fields are displayed on each device's Device Details tab.

TABLE 1. SEARCHABLE CRITERIA FOR TERMS OF SERVICE

Criterion	Description
<b>Terms of Service Accepted</b>	<p>A false value means the user did not accept the terms of service at registration, which means the device was registered before a terms of service agreement was required, or a terms of service agreement was never configured.</p> <p>A true value indicates the device user accepted the terms of service agreement at registration.</p>
<b>Terms of Service Accepted Date</b>	Filters for the exact time users accepted the terms of service agreement at registration. This search is useful if you want to locate the version of the terms of service agreement accepted by a specific user for a particular device.
<b>AppConnect Terms of Service</b>	<p>The value <b>DECLINED</b> means the user did not accept the terms of service for using AppConnect, which means the device user logged into AppConnect before a terms of service agreement was required, or a terms of service agreement was never configured.</p> <p>The value <b>ACCEPTED</b> indicates the device user accepted the terms of service agreement when logging into AppConnect.</p>
<b>AppConnect Terms of Service Date</b>	Filters for the exact time users accepted the terms of service agreement when logging into AppConnect. This search is useful if you want to locate the version of the terms of service agreement accepted by a specific user for a particular device.

### Procedure

1. In the Admin Portal, go to **Devices & Users > Devices**.
2. Click **Advanced Search**.

3. Add one or more of the search rules regarding terms of service.
  - a. From the **Field** drop-down list, select the field of interest:
    - **Common Fields > Terms of Service Accepted.**
    - **Common Fields > Terms of Service Accepted Date.**
    - **Common Fields > AppConnect Terms of Service.**
    - **Common Fields > AppConnect Terms of Service Date.**
  - b. Provide the appropriate value:
    - **Terms of Service Accepted:** Select **true** or **false** in the **Select Value** field.
    - **Terms of Service Accepted Date:** Enter the number of units in the **Value** field and select the units (such as days, weeks, or months) in the **Date** field.
    - **AppConnect Terms of Service.** Enter **ACCEPTED** or **DECLINED** in the **Value** field
    - **AppConnect Terms of Service Date.** Enter the number of units in the **Value** field and select the units (such as days, weeks, or months) in the **Date** field.
- The search criteria you selected are displayed in the search field.
4. Click **Search**.
5. The results are displayed.
6. Optionally, save your search to a label by clicking **Save to Label**.
7. If Notes for Audit Logs is enabled, a text dialog box opens. Enter the reason for the change and then click **Confirm**. For more information, see ["Best practices: label management" on page 419](#).

## Terms of Service for users

Device users can easily scroll through and accept an administrator-defined terms of service agreement in their web browser or Mobile@Work client, as in the following example.



FIGURE 1. TERMS OF SERVICE FOR USERS

Before you continue you must read and accept the Terms of Service.

Section 1 - Definitions And Interpretation

1.01 In this Agreement, unless the context otherwise requires:

(a) "Acceptance" means the acceptance of the Deliverables in accordance with Section 10 (Inspection of the Deliverables) of this Agreement;

(b) "CUSTOMER Group" means CUSTOMER and its Affiliates and Associates, as such terms are defined in the Business Corporations Act ([\_\_\_\_\_]);

(c) "Confidential Information" means all confidential, scientific, technical, financial, business and other information, all manufacturing, marketing, sales and distribution data, all scientific and test data, documents, methods, techniques, formulations, operations, know-how, experience, skills, trade secrets, computer programs and systems, processes, practices, ideas, inventions, designs, samples, plans and drawings;

(d) "Contract Price" means the amounts referred to or expressed in this Agreement, and specifically in the payment schedule attached as Schedule "A" to this Agreement, to be payable by CUSTOMER to the Vendor for the Deliverables;

(e) "IT System" means the computer

## Visual privacy

Core allows you to display privacy information to device users.

Visual privacy describes to users what device information is collected and why, and what actions administrators can take on the device, based on Core settings. Additionally, Core notifies users when changes are made to the privacy policy or MDM profile settings.

Users view the visual privacy information during registration, when they must accept the privacy policy.

## Enabling visual privacy for devices

When enabled, end-users will be able to learn more about the privacy of their data. Mobile@Work will show what content stays private on the device, what information is collected and why, and what actions the IT administrator can take on the device, according to the settings on the server. This can help reduce end-user questions and concerns.

### Procedure

1. Go to **Settings > System Settings > Users & Devices > Registration**.
2. Select **Enable privacy settings in Mobile@Work**.
3. Click **Save**.

## Invite users to register

This feature is supported on macOS devices.

Administrators can invite users to perform self-service registration through the user portal. See "[Self-service User Portal](#)" on page 552 for information on this self-service user portal. The administrator sends invitations that provide the instructions necessary to complete the registration process.



Language-specific templates are not currently available for invitations.


---

See "[Registration methods](#)" on page 36 for points to consider before using this registration method.

### Procedure

1. Go to **Devices & Users > Users**.
2. Select the type of user accounts you want to work with:
  - a. Select **Authorized Users** from the To drop-down list to select from local user accounts.
  - b. Select **LDAP Entities** from the To drop-down list to select users from the configured LDAP server.
3. Click the check box next to each user you want to invite.

4. Click **Actions** and then click **Send Invitation**.



The image shows a 'Send Invitation' dialog box with a title bar, a close button (X), and two input fields. The 'Subject' field contains the text '\$BRAND\_COMPANY\_NAME\$ registration for \$USER\$'. The 'Message' field contains HTML-formatted text: '<html><body><p style="font-family: Arial,Helvetica,sans-serif, font-weight:bold;">Please register your phone for \$SENT\_NAME\$ mobile access.</p><p style="font-family: Arial,Helvetica,sans-serif;">\$SENT\_NAME\$ is using \$BRAND\_COMPANY\_NAME\$ software to enable your phone to access the company network.</p><p style="font-family: Arial,Helvetica,sans-serif;">Click on \$DEV\_REG\_URL\$ for instructions on how to register your phone.</p><p style="font-family: Arial,Helvetica,sans-serif;">Thank you.</p></body></html>'. At the bottom right, there are 'Cancel' and 'Send' buttons.

5. Review the default text for the invitation and make any changes.

The text is displayed here with HTML markup. The user will receive the formatted version.

6. Click **Send**.

### What the user sees

This registration method results in user notification via email. The email contains instructions for registering devices via the user portal. See ["Self-service User Portal" on page 552](#) for information on what the user is expected to do to complete the registration process.

## In-app registration for iOS and Android

You can ask Android device users to download Mobile@Work from Google Play and register by themselves.

### Procedure

1. Make sure that the device user has a user record (local or LDAP) available in Core. See "Managing Users" in *Getting Started with Core*.

2. Instruct the device user on downloading the app and registering. The device user will need the following information:
  - user name
  - password and/or Registration PIN
  - server (and the port number, if you did not use the default port number for TLS)

See "[Registration methods](#)" on [page 36](#) for points to consider before using this registration method.

### What the device user sees



For iOS 12.2 or supported newer versions, when doing the iReg and in-app registration of the MDM profile, the device user experiences a different registration process.

After downloading and installing Mobile@Work, the device user must register with Core by entering their user name, password, and server details.



In iOS 13, the option to "Allow Always" was removed from the iOS Settings app. Instead, a dialog box displays requesting device users to enable tracking when the Mobile@Work app is running. Mobile@Work opens iOS Settings where device users can choose "Ask Next Time" or "Never". Ivanti recommends device users to enable tracking. This change applies to all versions of iOS 13 or supported newer versions. Mobile@Work for iOS does not track device users' location without consent.

If a customized terms of service agreement has been defined on Core, device users will need to accept the agreement before registering with Core.

## Auto-populating the Core server name during registration

Auto-populating the Core server name streamlines the registration process and eliminates the need for the device user to type it. You can auto-populate the Core server address based on the device phone number or the email address.



This feature is not supported for devices with Android v6.0 and above.

### Auto-populating the Core server name based on email address

To auto-populate the server name based on the device user's email address, you only need to register your Core with Ivanti. Additional configuration on Core is not required.

Device users must enter their full email address when prompted to enter their user name in the registration screen. Ivanti matches the email domain to the appropriate Core and populates the registration screen with the correct server name.

## Registering your Core with Ivanti

To register your Core, open a ticket on the Ivanti Support portal and provide the following information:

- your company name (e.g. Ivanti)
- your email domain (e.g. ivanti.com)
- your Core hostname for on-premise Core, or m.mobileiron.net:<appropriate port number> for Connected Cloud.

## Auto-populating the Core server name based on the phone number

You can also auto-populate the Core server name based on the device's phone number. The following setup is required:

- Core access to the Ivanti Gateway. Configure the required ports. See the "Changing Firewall Rules" section in the *On-Premise Installation Guide for Core and Enterprise Connector* for details.
- Enable server name look up in the Admin Portal on the **Settings > System Settings > Users & Devices > Device Registration** page.

To enable server name lookup:

1. In the Admin Portal, go to **Settings > System Settings > Users & Devices > Device Registration**.
2. Select **Enable Server Name Lookup**.
3. Click **Save**.

Note The Following:

- Because this feature relies on a mobile number, it does not apply to iOS devices.
- The mobile number must also be present on the SIM in order for the **Enable Server Name Lookup** option to work.
- Registering Core with Ivanti is not required.

## Registering an Android device with Mobile@Work

This registration method applies to registering Android devices using the following methods:

- web-based registration - see "[Web-based registration for Android devices](#)" on the next page
- using a QR code - see "[Provisioning Android Enterprise devices using a QR code or NFC bump](#)" on [page 62](#)
- using email - see "[Invite users to register](#)" on [page 50](#)

### Procedure

After the Mobile@Work app is installed on your device, complete registration as a corporate device user.

1. Tap the Mobile@Work app icon. The "Get Ready for Work with Mobile@Work" page opens.
2. Enter your company's URL. You can also use the Scan QR code and Register with Email option.
3. Tap **Next**.
4. The Username page displays. Enter it and tap **Sign In**.
5. The Password field displays. Enter it and tap Sign In.
6. After your credentials are verified, the Home page opens.
7. Mobile@Work checks for updates.
8. Once registration is complete, the Privacy statement displays for the device user to read.
9. Mobile@Work guides the device user through the rest of the provisioning. The type of provisioning depends upon the policies and configurations set by the administrator.

## Requiring device identifiers for enrollment

You have the option to make the collection of a device's hardware identifiers such as the IMEI number and the phone number optional before the device is enrolled. If you disable **Require device identifiers for enrollment**, the enrollment will still proceed, but the client will not collect the device identifier data. The device would be a "PDA" device such as a tablet.

### Procedure

1. In Admin Portal, go to **Settings > System Settings > Users & Devices > Registration**.
2. Select **Require device identifiers for enrollment**.  
This is supported on devices using Android 6.0 or supported newer versions.
3. Click **Save**.



Phone number lookup is supported on devices in Device Owner mode and using Android prior to Android 6.0.

---

## Web-based registration for Android devices

You can instruct users to register with Core through the web. Users enter the URL of the server with forward slash "go" appended to the end of the URL, which takes them through a guided web-based registration process. Device users must still install Mobile@Work to complete the registration process.

### Procedure

1. Make sure the user has a user record (local or LDAP) available in Core. See "Managing Users" in *Getting Started with MobileIron Core*.

2. Instruct the user on downloading the app and registering. The user will need the following information:
  - user name
  - password and/or Registration PIN
  - server (and the port number, if you did not use the default port number for TLS)
3. Instruct the user to register with the Core server at the following URL:

<https://<fully-qualified domain name for Core>/go>

The following pages are displayed, instructing the device user to download Mobile@Work for Android from Google Play:



4. Instruct the user to tap the **Google play** button so as to download Mobile@Work.
5. Instruct the user to follow the on-screen instructions in Mobile@Work, entering the user credentials and server name in the space provided.

## Registering a device with Mobile@Work using your company's URL

After the Mobile@Work app is installed on your device, complete registration as a corporate user.

### Procedure

After the Mobile@Work app is installed on your device, complete registration as a corporate user.

1. Tap the Mobile@Work app icon. The "Get Ready for Work with Mobile@Work" page opens.
2. Enter your company's URL. You can also use the Scan QR code and Register with Email option.
3. Tap **Next**.
4. The Username page displays. Enter it and tap **Sign In**.
5. The Password field displays. Enter it and tap Sign In.
6. After your credentials are verified, the Home page opens.
7. Mobile@Work checks for updates.
8. Once registration is complete, the Privacy statement displays for the device user to read.
9. Mobile@Work guides the device user through the rest of the provisioning. The type of provisioning depends upon the policies and configurations set by the administrator.

## ActiveSync device registration

The **ActiveSync** view displays the devices that are accessing ActiveSync. This view is populated only if you have a Sentry configured. From this view, you can decide to register selected devices.

See ["Registration methods" on page 36](#) for points to consider before using this registration method.

### Procedure

1. Go to **Devices & Users > ActiveSync**.
2. Select a device to be registered.
3. Click **Actions > Register**.
4. See "Single device registration" in the *Getting Started with MobileIron Core* for instructions on completing the registration process.

## Managing the Android Enterprise device life cycle

Managing the life cycle of an Android Enterprise device includes the following steps:

- ["Provisioning a Work managed device for Android Enterprise" on the next page](#)
- ["Registering a Work managed device for Android Enterprise" on the next page](#)
- ["Migrating devices to Android Enterprise" on page 58](#)
- ["Preventing automatic migration" on page 58](#)
- ["Migration effects on a device" on page 58](#)
- ["Quarantine on Android Enterprise devices" on page 59](#)
- ["Retiring an Android Enterprise device" on page 59](#)



- ["Wiping an Android Enterprise device" on page 60](#)
- ["Locking an Android Enterprise device" on page 61](#)
- ["Unlocking an Android Enterprise device" on page 61](#)

#### Related topics

["Removing Android Enterprise" on page 25](#)

## Provisioning a Work managed device for Android Enterprise

Provisioning is necessary only for work managed devices. You can provision factory reset Android devices using one of these methods:

- the Provisioner app, which uses the NFC bump and QR code method.
- an afw# token
- Android Zero Touch
- Knox Mobile Enrollment (KME)

Provisioner (QR code) and Zero Touch can be used to provision Work Profile on Company Owned Devices. Once provisioned, a work-managed devices or Work Profile on Company Owned Devices can register with Core.

#### Related topics

["Provisioning an Android Enterprise device" on page 62](#)

## Registering a Work managed device for Android Enterprise

To register an Android Enterprise-capable device, the user follows the same registration process as for any Android device. The registration process detects if Core and the device are Android Enterprise-capable, and performs the correct registration steps automatically.

To register an Android Enterprise-capable device to have an Android Enterprise work profile (as opposed to being registered as a regular Android device), the following must be in place:

- Core has been set up for Android Enterprise as described in ["Enabling Android Enterprise" on page 16](#). To confirm the setup, go to **Services > Google**. In the **Android enterprise** section you should see **Account Settings:** information with **Status: Connected**.
- The **Android enterprise setting** is applied to an appropriate label.

The user follows the registration process in the Mobile@Work app.

Once registered, to verify that the device is using Android Enterprise:

- on a device with a work profile, check that the Mobile@Work app appears with the Android Enterprise badge
- on a work managed device that was provisioned, look for the Google Play store icon, which will show the Work version of the store.

### Related topics

["In-app registration for iOS and Android" on page 51](#)

## Migrating devices to Android Enterprise

"Migrating" refers to the actions devices take when they are already registered and running Mobile@Work and an update to Core or Mobile@Work takes effect. This section describes migration and what to expect.

Migration does not apply to work managed devices, because such devices are enabled for Android Enterprise after factory reset. Migration applies only to device that are not in work profile mode, yet.

A registered device may migrate to an Android Enterprise profile (assuming Core has Android Enterprise enabled, and the device has the Android Enterprise setting applied to it) when the following occurs:

- the device becomes Android Enterprise-capable after it receives a firmware update from the carrier
- Core is newly enabled for Android Enterprise.

In these migration scenarios, the Android devices begin their migration to use work profile automatically.

## Preventing automatic migration

When all the conditions required to enable Android Enterprise are met, a device will automatically migrate to use the work profile. If you want to prevent a device from automatically migrating, ensure the device does not have the **Android enterprise setting** applied.



If you applied the **Android** label to the **Android enterprise setting**, then all Android devices potentially have the setting, and all Android Enterprise-capable devices be will be automatically migrated. If this is not desired, do not use the **Android** label for this configuration.

---

## Migration effects on a device

The following changes occur on a registered device when it is migrated to work profile:

1. User is prompted to uninstall all secure apps, in-house apps, and public apps.



The migration will not continue until the user completes this step or there are no secure or in-house apps installed.

---

2. All managed configurations are removed, except for Wi-Fi configurations.  
As when a device is retired, no personal certificates are removed.
3. The Android Enterprise work profile is created.
4. The Mobile@Work app icon appears with the Android Enterprise badge.
5. Configuration steps appear as needed.

## Quarantine on Android Enterprise devices

When an Android Enterprise device is quarantined (with all configurations removed) due to a compliance violation, the following changes are made on the device:

TABLE 1. ANDROID ENTERPRISE QUARANTINE BEHAVIOR

Android Enterprise mode	"Quarantine app when device is quarantined" field is selected (checked)	"Quarantine app when device is quarantined" field is de-selected (not checked)
<ul style="list-style-type: none"> <li>Work Profile mode</li> <li>Work Managed Device</li> <li>Managed Device with Work Profile (COPE) (Android versions 8-10 only)</li> <li>Work Profile on Company Owned Devices (Android 11 or supported newer versions)</li> </ul>	<ul style="list-style-type: none"> <li>All the apps in the work profile are hidden, except:               <ul style="list-style-type: none"> <li>- Google Play</li> <li>- Mobile@Work</li> <li>- Downloads</li> </ul> </li> <li>Contacts are hidden.</li> <li>The Wi-Fi configurations are kept or removed, based on the quarantine settings.</li> </ul>	Users will still see the app on the device.



The quarantine behavior of individual Android Enterprise apps is controlled by setting the configuration of each Android Enterprise app in the App Catalog.

For more information, see "Adding in-house apps for Android" section or the "Adding an Android Enterprise public app using the app wizard in the Core Admin Portal" section in the *Core Apps@Work Guide*.

## Retiring an Android Enterprise device

When an Android Enterprise device gets the **Retire** command, the following behavior occurs:

TABLE 2. ANDROID ENTERPRISE RETIRE BEHAVIOR

Android Enterprise status	Retire behavior
Work Profile	<ul style="list-style-type: none"> <li>The work profile is removed.</li> <li>All apps, data, and contacts in the work profile are removed.</li> <li>A user can re-register a retired device by re-enabling Mobile@Work through Google Play.</li> </ul>
<ul style="list-style-type: none"> <li>Work Managed Device</li> <li>Managed Device with Work Profile (COPE)</li> <li>Work Profile on Company Owned Devices</li> </ul>	<p>The device is reset to factory settings.</p> <p>(Note: Retire and Wipe have the same effect.)</p> <p>The device can be re-provisioned by an administrator.</p>

### Related topics

["Removing an Android Enterprise configuration causes device to retire" on page 26](#)

## Wiping an Android Enterprise device

When an Android Enterprise device gets the **Wipe** command, the following behavior occurs:

TABLE 3. ANDROID ENTERPRISE WIPE BEHAVIOR

Android Enterprise status	Wipe behavior
Work Profile	<ul style="list-style-type: none"> <li>The work profile is removed. (No changes are made to any apps or data on the personal profile.)</li> <li>All apps, data, and contacts in the work profile are removed.</li> <li>A user can re-register a wiped device by re-enabling Mobile@Work in Google Play.</li> </ul>
<ul style="list-style-type: none"> <li>Work Managed Device</li> <li>Managed Device with Work Profile (COPE)</li> <li>Work Profile on Company Owned Devices</li> </ul>	<p>The device is reset to factory settings.</p> <p>(Note: <b>Retire</b> and <b>Wipe</b> have the same effect.)</p> <p>The device can be re-provisioned by an administrator.</p>

## Locking an Android Enterprise device

The **Lock** command locks the screen of an Android Enterprise device. To lock the device:

1. Go to **Devices & Users > Devices**.
2. Select the device.
3. Click **Actions > Lock**.

For work managed devices, the Lock command locks the entire device. The user must enter the device password to unlock the device.

For work profile devices, the Lock command locks the work profile if a Work Challenge was set (Android 7.0 through etc).

## Unlocking an Android Enterprise device

The **Unlock** command unlocks the screen of an Android Enterprise device. Before unlocking Samsung devices running in Device Administrator mode, the password must be reset in the DevicePolicyManager resetpassword() API. For unlocking devices with Knox licenses, administrators will need to make sure the Knox license is activated (Samsung General Policy in Policies & Configs) and then reset the password. This is applicable to Android 7 or supported newer versions.

To unlock the device:

1. Go to **Devices & Users > Devices**.
2. Select the device.
3. Click **Actions > Unlock Device**.

The following table shows unlock support on Android Enterprise devices:

TABLE 4. SUPPORT FOR UNLOCKING THE DEVICE ON ANDROID ENTERPRISE DEVICES

Android Enterprise device	Prior to Android 7.0	Android 7.0 or supported newer versions
<ul style="list-style-type: none"><li>• Work Managed Devices</li><li>• Managed Device with Work Profile (COPE)</li></ul>	Supported	Supported
<ul style="list-style-type: none"><li>• Work Profile Devices</li><li>• Work Profile on Company Owned Devices</li></ul>	Supported	Not supported

## Provisioning an Android Enterprise device

Administrators register Android Enterprise devices, by registering a “work profile” and by provisioning “work managed” devices on a master device.

- Register a “work profile” device by following the regular registration process to install Mobile@Work.
- Provision Work Managed Devices and Work Profile on Company Owned Devices using a master device that is running the Provisioner app. For details, see the following sections.
  - ["Provisioning Android Enterprise devices using a QR code or NFC bump" below](#)
  - ["Provisioning Android Enterprise devices using an afw# token" on page 65](#)
  - ["Provisioning Android Enterprise devices using Zero Touch" on page 66](#)

Before registering using a QR code for devices in a closed network or using AOSP deployment, see ["Setting up Core with a closed network / AOSP deployment" on page 28](#).

### Related topics

["In-app registration for iOS and Android" on page 51](#)

## Provisioning Android Enterprise devices using a QR code or NFC bump

To provision Android Enterprise devices using QR code or near field communication (NFC) bump, you will need to download and install the Provisioner app from Google Play on the master device.

Using this method, you can provision Android devices in a closed network or with a AOSP (Android Open Source Project) deployment. For more information, see ["Setting up Core with a closed network / AOSP deployment" on page 28](#).

### Requirements to provision an Android Enterprise device

To provision an Android Enterprise device to be a work managed device, you need to:

- Ensure the required **Android Enterprise Configuration** is defined and applied to a recommended label.
- Enable Android Enterprise on the server.
- In **Devices & Users > Add Single Device**, make sure the "Include Registration PIN only for Android Company-Owned Device Enrollment" field is selected.
- In **Settings > Device Registration**, have the "Managed Devices / Device Owner (afw#, QR code, NFC)" field set to Password, Registration PIN or Password and Registration PIN.
- In **Settings > Device Registration**, verify that the option **Display QR Code and Registration URL** is enabled. To disable sending users a QR code and registration URL, see ["Disabling the QR code and registration URL" on page 77](#).

- Have an NFC-capable Android device (only if NFC is used) to serve as the master, with the Provisioner app installed.
- Have Android Enterprise-capable devices to provision.

## Enabling the Android beam for use with NFC bump

### Procedure

1. Go to **Settings** on the device.
2. Go to **Networks > Wireless Networks**.
3. In the **Connectivity** section select **Share & connect**.
4. Slide the **NFC** switch to **On**.
5. Slide the **Android Beam** switch to **On**.



The steps to enable the Android beam and NFC may vary on different devices.

## Provisioning Android Enterprise devices to become work managed devices

This section applies to Work Managed Devices and Work Profile on Company Owned Devices.

### Procedure

1. Using the Android master device, download the **Provisioner** app from Google Play and install the app.
2. Launch Provisioner on the master device.
3. Select **NFC** or **QR code** for the Provisioning method.
4. Tap **App for Provisioning**, and choose the client app to be installed on the provisioned device:

Select this client app:	To register with this EMM server:
Mobile@Work	Core
MDM	Deutsche Telekom Core
Vodafone Mobile@Work	Vodafone Core

5. Fill out the remaining fields in the Provisioner app. Some fields may auto-populate if a supported Wi-Fi type is present. The Wi-Fi fields are not shown if QR code is selected. Use these guidelines:

Field	Value
Select app for provisioning	Mobile@Work
Time Zone	Enter the time zone to be configured on the device
Locale	Enter the locale to be configured on the device
Enable All System Apps	Click the check box to enable all system apps
Wi-Fi Network SSID	Enter the Wi-Fi SSID the target device is to use
Wi-Fi Security Type	Enter the Wi-Fi security type
Wi-Fi Password	Enter the password for the Wi-Fi
Bulk Enrollment	Bulk enrollment is optional along with the hostname and username. Optionally click the Quick Start check box to use Quick Start feature.  If a username is entered or Quick Start is checked, then a hostname is required.

6. Tap **Continue**.
7. If you selected **NFC**, tap **Continue**. The screen **Bump the devices!** appears on the master device. Continue with the NFC Bump section below.
8. If you selected QR code, the screen Scan this QR code! appears on the master device. Continue with the QR Code section below.
9. Configure NFC Bump.
  - a. Confirm that the target device is displaying the Android Welcome screen.
  - b. Press the master device back-to-back with the target device to initiate an NFC transfer. If the NFC transfer succeeds, the target device may make a sound, and then proceed to downloading the client app. If a Wi-Fi connection cannot be established, or if the device is unable to download the client app, the device will automatically do a factory reset.
  - c. If you hear the sound or see a screen other than the Welcome screen, you can decouple the devices. This typically takes a few seconds. If the device is not encrypted, it will start the encryption process before continuing.
  - d. You can continue to provision additional devices by "bumping" the devices to the master device. The target device must be showing the Welcome screen, and the master device must be showing the "Bump the devices!" screen.



10. Configure QR Code provisioning.
  - a. Confirm that the target device is displaying the Android Welcome screen.
  - b. Tap the Android Welcome screen on the target device 6 times on the same place on the screen.
  - c. You will be prompted to configure a WiFi network so the setup wizard can download a QR code reader to the target device.
  - d. After the QR code reader is downloaded, the camera is launched.
  - e. Hold the target device a few inches above the master device until the QR code is scanned successfully. The setup wizard will then proceed to download the client app. If it is unable to download the client app, it will automatically do a factory reset.
  - f. You can continue to provision additional devices by scanning the QR code on the master device. The target device must have a camera ready to scan, and the master device must show the "Scan this QR code!" screen.
  - g. The QR code can also be exported by tapping the Share icon. The options offered for exporting will vary by device.

#### Related topics

"Disabling the QR code and registration URL" on page 77.

## Provisioning Android Enterprise devices using an afw# token

You can provision an Android Enterprise device in Device Owner mode using an afw# token instead of using the NFC bump or QR code methods. This method enables you to sign on a device with a token in the form afw#mobileiron.core which facilitates an automatic installation of the Mobile@Work client and provisioning in Device Owner mode.



Device Owner mode is supported on devices provisioned with Managed Google Play Accounts, using Android 6 or supported newer versions. For details see the Android EMM Developers guide: [https://developers.google.com/android/work/prov-devices#Key\\_provisioning\\_differences\\_across\\_android\\_releases](https://developers.google.com/android/work/prov-devices#Key_provisioning_differences_across_android_releases).

---

#### Before you begin

- You must be enrolled with an Android Enterprise account.
- The device must be Android Enterprise-capable.
- The device must use Android 6 or supported newer versions.
- In **Devices & Users > Add Single Device**, make sure the "Include Registration PIN only for Android Company-Owned Device Enrollment" field is selected.

- In **Settings > Device Registration**, have the "Managed Devices / Device Owner (afw#, QR code, NFC)" field set to Password, Registration PIN or Password and Registration PIN.
- You must have an Android Enterprise token for Core or a client branded token such as:
  - Core: **afw#mobileiron.core**
  - Deutsche Telekom: **afw#telekom.mi**
  - Vodafone: **afw#vodafone.mi**
- You must have a new or factory reset device.

### Procedure

1. Power on the device and enter your WI-FI password.  
Your device may prompt you for a different password.
2. In the **Verify your account** screen enter your Android Enterprise token. Click **Next**.
3. On the **Google Services** screen click **Install**.
4. Accept the Terms and Conditions.
5. On the Setup work device screen click **Next**.  
The Mobile@Work client downloads and installs on the device. The device now enters Device Owner mode.

## Provisioning Android Enterprise devices using Zero Touch

For information on Android Zero Touch provisioning, see the [Android Zero Touch Provisioning Guide](#).

Note The Following:

- In **Devices & Users > Add Single Device**, make sure the "Include Registration PIN only for Android Company-Owned Device Enrollment" field is selected.
- In **Settings > Device Registration**, have the "Zero Touch and Samsung Knox Mobile Enrollment" field set to Password, Registration PIN or Password and Registration PIN.

### Zero Touch enrollment with custom attributes

Administrators can specify certain custom device attributes at the time of initial provisioning. This works with the Provisioner app, QR code, KNOX Mobile Enrollment (KME) and Zero Touch (ZT) for devices in Work managed device mode (DO) or corporate-owned personal-enabled (COPE) mode. It also works with all modes of registration, including PIN based and password based registration.

At initial registration and during any check-in, these custom attributes are passed on to Core to categorize the device and place it in the correct group and assign the correct labels. The client sends property (customAttributes) consisting of the device custom attribute keys (variable name) and values that client wants Core to set for that device. The client also sends to Core updated values with the existing keys for the (customAttributes) key. If the client does not send a (customAttributes) key, the existing custom attributes values will not change.

Zero Touch enrollment with custom attributes is supported for custom attributes of type: String, Boolean, and Integer. The Provisioner App only supports String type.



It is the responsibility of the administrator to make sure that the custom attributes are setup correctly in Core beforehand and match what is being sent by the Provisioner app or Zero Touch portal.

---

### **Use Case examples**

#### **Example - BOOLEAN**

- Attribute Name – COPE
- Attribute Description – Enabled COPE Mode
- Value Type – Boolean
- Variable Name – True

#### **Example - INTEGER**

- Attribute Name – OrgID
- Attribute Description – Organization ID
- Value Type – Integer
- Variable Name – 3456

#### **Example - STRING**

- Attribute Name – AEmode
- Attribute Description – Android Enterprise Mode
- Value Type – String
- Variable Name – DO

For information on how to set custom attributes, see ["Adding custom attributes to users and/or devices" on page 131](#).

## Managing operators and countries

Core provides a default list of operators for users to select from during registration. You can enable or disable operators to determine whether they appear in the list of operators displayed during registration of US devices and other devices having a country code of 1.

For non-US devices, country selection is an important part of the registration process. Core also provides a default list of countries enabled for registration purposes. You may need to adjust this list to enable additional countries.

This section explains how to customize displayed operators and countries.

### Enabling operators

Enabling an operator displays it in the list of operators presented to users during registration.

#### Procedure

1. In the Admin Portal, go to **Services > Operators**. By default, the Operators screen shows only Enabled operators.
2. Select **Disabled** or **All** from the **Status** drop-down.
3. Click the check box next to each operator you want to enable.
4. Click **Actions > Enable**.

### Enabling additional countries for registration

A subset of countries are enabled for device registration by default. You should check this list and determine if any of your users have home countries not represented in the default list.

#### Procedure

1. In Admin Portal, go to **Settings > System Settings > Users & Devices > Registration**.
2. Scroll to the **Countries for Registration** section.
3. Select countries from the **Disabled Countries** list.
4. Click the arrow button to move them to the **Enabled Countries** list.
5. Click **Save**.

### Disabling operators

Disabling an operator removes it from the list of operators presented to users during registration.

## Procedure

1. In the Admin Portal, go to **Services > Operators**.
2. By default, the **Operators** screen shows only Enabled operators.
3. Click the check box next to each operator you want to disable.
4. Click **Actions > Disable**.

## Filtering operators

You can use filters to display only those operators you want to work with in the Operators screen. You can:

- Search for a specific operator
- Display operators by country
- Display operators by status

## Searching for an operator

### Procedure

1. Enter a portion of the operator's name in the **Search by Name** field.
2. Click the search icon to display the matching operators.
3. Click the x that appears in the search field to return to the default display.

## Displaying operators by country

To narrow the list of operators by country, select a country from the **Country** drop-down list.

## Displaying operators by status

To display operators by status, select from the **Status** drop-down list. The following options are available:

- Enabled
- Disabled
- All

## Specifying eligible platforms for registration

In some cases, you may want to exclude from registration all devices of a particular platform. For example, if corporate policy dictates that a particular device platform will not be supported, you may want to prevent users from selecting the platform during self registration. Likewise, you may want to prevent help desk personnel from mistakenly registering the unsupported platform in the Admin Portal.

## Procedure

1. In Admin Portal, go to **Settings > System Settings > Users & Devices > Registration**.
2. Scroll to the **Platforms for Registration** section.
3. In the **Enabled Platforms** list, select the platform you want to exclude.  
Shift-click platforms to select more than one.
4. Click the left arrow button to move the selected platforms to the **Disabled Platforms** list.
5. Click **Save**.

All methods of registration now exclude the selected platforms.

## Setting the registration PIN code length for device user registration

This feature is supported on Android, iOS and macOS devices.

By default, device users must enter a password to register a device. You have the option to require a Core-generated Registration PIN in place of or in addition to the password.

## Procedure

1. In Admin Portal, go to **Settings > System Settings > Users & Devices > Registration**.
2. Select a **Registration PIN code Length**, which is the minimum length for the PIN (6-12 characters).
3. Click **Save**.

For setting Android registration authentication, see ["Registering Android devices" on page 38](#).

For iOS and macOS registration authentication, see [Registering iOS and macOS devices through the web](#)

## Limit for failed attempts to enter a registration password

After the sixth failed attempt to enter a registration password, Core locks the device user's account for 30 seconds. The device user sees a message stating that the account is locked and will be released after the specified interval.

## Customizing registration messages

This feature is supported on iOS, macOS, Windows, and Android devices.

The registration process is a critical part of deployment. You can customize the registration messages involved in this process by editing the registration templates. Registration templates enable you to specify content and basic formatting using HTML markup.

Core sends multiple messages related to registration:

- registration SMS
- registration email and reminder email
- post registration email

These messages may vary by:

- platform
- language

In addition, messages may vary by device type:

- phones
- PDAs

To accommodate this range of messages:

- Separate registration templates are provided for each language/platform combination.
- Each registration template contains separate text for each registration message type.
- Each registration template contains separate text for phones and PDAs.
- For when Core discovers device users that have not downloaded the MDM profile, reminder email scheduling capabilities are provided

## Viewing registration templates














To view Core message templates:

1. In Admin Portal, click **Settings > Templates**.
2. Select **Registration Templates**.
3. Click the **View** link for the template you want to view.

## Editing registration messages

To edit registration messages:

1. In Admin Portal, select **Settings > Templates > Registration Templates**.
2. Select the template you want to edit and click the **Edit** pencil icon.

REGISTRATION TEMPLATES				
Language: All		Platform: All		<a href="#">Restore to Factory Default</a>
<input type="checkbox"/>	Edit	Language	Platform	Templates
<input type="checkbox"/>		Chinese	Windows	<a href="#">View</a>
<input type="checkbox"/>		Chinese	Android	<a href="#">View</a>
<input type="checkbox"/>		Chinese	OS X	<a href="#">View</a>
<input type="checkbox"/>		Chinese	iOS	<a href="#">View</a>
<input type="checkbox"/>		Dutch	Android	<a href="#">View</a>
<input type="checkbox"/>		Dutch	Windows	<a href="#">View</a>
<input type="checkbox"/>		Dutch	OS X	<a href="#">View</a>
<input type="checkbox"/>		Dutch	iOS	<a href="#">View</a>
<input type="checkbox"/>		English	Android	<a href="#">View</a>
<input checked="" type="checkbox"/>		English	iOS	<a href="#">View</a>
<input type="checkbox"/>		English	OS X	<a href="#">View</a>
<input type="checkbox"/>		English	Windows	<a href="#">View</a>
<input type="checkbox"/>		French	Windows	<a href="#">View</a>

Registration messages are displayed with the HTML markup that provides the basic formatting for the content.



3. Make changes to the displayed registration messages.



Do not add the <head> html tag in the registration template fields.

**Edit Registration Template: iOS (English)**

Language: English  
Platform: iOS

[Variables Supported](#)

**Registration SMS**

Phones	PDAs
Go to \$REG_LINK\$. For full instructions, please check your email.	N/A

Only the first 160 characters will be sent with the text message.

**Push Notification Reminder to Complete Registration**

Phones/Devices	PDAs
Your MDM profile is ready to be installed from Settings. For more details please check your email.	N/A

**Registration Email**

	Phones	PDAs
Subject	\$ENT_NAME\$ device registration instructions for \$USER\$ (	\$ENT_NAME\$ device registration instructions for \$USER\$ (
Body	<html><body><p style="font-family: Arial,Helvetica,sans-serif;">\$ENT_NAME\$ is using \$BRAND_COMPANY_NAME\$&#39;s Platform to enable access to corporate resources.</p><p style="font-family: Arial,Helvetica,sans-serif;">To allow you to easily register your device with this system. If you selected	<html><body><p style="font-family: Arial,Helvetica,sans-serif;">\$ENT_NAME\$ is using \$BRAND_COMPANY_NAME\$&#39;s Platform to enable access to corporate resources.</p><p></p><p style="font-family: Arial,Helvetica,sans-serif;">From your device.</p></body></html>
Reminder Subject	Reminder: \$ENT_NAME\$ device registration instructions fo	Reminder: \$ENT_NAME\$ device registration instructions fo
Reminder Body	<html><body><p style="font-family: Arial,Helvetica,sans-serif;">\$ENT_NAME\$ is using \$BRAND_COMPANY_NAME\$&#39;s Platform to enable access to corporate resources.</p><p style="font-family: Arial,Helvetica,sans-serif;">To allow you to easily register your device with this system. If you selected	<html><body><p style="font-family: Arial,Helvetica,sans-serif;">\$ENT_NAME\$ is using \$BRAND_COMPANY_NAME\$&#39;s Platform to enable access to corporate resources.</p><p></p><p style="font-family: Arial,Helvetica,sans-serif;">From your device.</p></body></html>

Values for \$INAPP\_REG\_STEPS\$ ⓘ

[Save](#) | [Cancel](#)

4. Click the **Variables Supported** link in the right corner of the dialog box to display a guide to the supported variables. See ["Using variables in registration messages" on the next page](#) for additional details.
5. Click **Save**.

## Next steps

["Customizing registration messages" on page 70](#)

## Using variables in registration messages

Each field in a registration template has a set of supported variables, most of which are required. Supported and required variables also differ by OS. Use the following variables to guide your customization. You can also click the Variables Supported link to display this information. **All variables except \$BRANDING\_COMPANY\_NAME\$ are also required in the specified field.**

### Registration message variables

The following table gives the of variables used in types of registration messages.

TABLE 1. VARIABLES USED IN DIFFERENT TYPES OF REGISTRATION MESSAGES

Type	Supported Variables
Registration SMS, Phone	\$REG_LINK\$
<b>Registration Email</b>	
Registration Email, Subject (Phone)	\$ENT_NAME\$, \$USER\$, \$PHONE\$
Registration Email, Subject (PDA)	\$ENT_NAME\$, \$USER\$, \$PHONE\$
Registration Email, Body(Phone)	\$ENT_NAME\$, \$BRAND_COMPANY_NAME\$, \$PHONE\$, \$INAPP_REG_STEPS\$, \$REG_LINK\$
Registration Email, Body(PDA)	\$ENT_NAME\$, \$BRAND_COMPANY_NAME\$, \$REG_LINK\$, \$INAPP_REG_STEPS\$
Registration Email, Reminder Subject (Phone)	\$ENT_NAME\$, \$USER\$, \$PHONE\$
Registration Email, Reminder Subject (PDA)	\$ENT_NAME\$, \$USER\$, \$PHONE\$
Registration Email, Reminder Body (Phone)	\$ENT_NAME\$, \$BRAND_COMPANY_NAME\$, \$PHONE\$, \$INAPP_REG_STEPS\$, \$REG_LINK\$
Registration Email, Reminder Body (PDA)	\$ENT_NAME\$, \$BRAND_COMPANY_NAME\$, \$REG_LINK\$, \$INAPP_REG_STEPS\$
<b>Values for \$INAPP_REG_STEPS\$</b>	
Server	\$SERVER_URL\$
Username	\$USER_ID\$
PIN	\$PASSCODE\$, \$PASSCODE_TTL\$

TABLE 1. VARIABLES USED IN DIFFERENT TYPES OF REGISTRATION MESSAGES (CONT.)

Type	Supported Variables
<b>Post-Registration Email</b>	
Post Registration Email, Subject (Phone)	\$BRAND_COMPANY_NAME\$, \$USER\$, \$PHONE\$
Post Registration Email, Subject (PDA)	\$BRAND_COMPANY_NAME\$, \$USER\$, \$PHONE\$
Post Registration Email, Body (Phones)	\$PHONES\$, \$BRAND_COMPANY_NAME\$

### Variables used inside registration messages

The following table gives the description of variables used inside registration messages.

TABLE 2. DESCRIPTION OF VARIABLES USED INSIDE REGISTRATION MESSAGES

Variable	Description
\$BRAND_COMPANY_NAME\$	An internal variable.
\$ENT_NAME\$	The name of the organization using Core to secure the device. See the field <b>EnterpriseName</b> in <b>Settings &gt; System Settings &gt; General &gt; Enterprise</b> .
\$INAPP_REG_STEPS\$	Combines \$SERVER_URL\$, the user's LDAP password, \$PASSCODE\$, and \$USER_ID\$.
\$PASSCODE\$	The registration PIN generated for the device by Core.
\$PASSCODE_TTL\$	The number of hours that the registration PIN remains valid. See the field <b>Passcode Expiry</b> in <b>Settings &gt; System Settings &gt; Users &amp; Devices &gt; Registration</b> .
\$PHONE\$	The phone number associated with the device.
\$REG_LINK\$	The URL that users access to complete the registration process (i.e., https://server name:port/a/ for Androidhttps://server name:port/v/passcode for Windows and other platforms).

TABLE 2. DESCRIPTION OF VARIABLES USED INSIDE REGISTRATION MESSAGES (CONT.)

Variable	Description
\$SERVER_URL\$	The Core server address used for registration.
\$USER\$	The name of the user associated with the device, as displayed in Core.
\$USER_ID\$	The user ID for the user associated with the device, as defined in the user account on Core.

## Filtering registration messages

In the Registration Templates page, you can filter registration messages by:

- language
- platform

### Procedure

1. If you want to restrict the templates displayed based on language, select the preferred language from the **Language** list.
2. If you want to restrict the templates displayed based on device platform, select the preferred platform from the **Platform** list.

## Restoring registration messages to default content

To restore a registration message to the default content provided by Ivanti:

1. In the **Settings > Registration Templates** page, select the template you want to restore.
2. Click **Restore to Factory Default**.

## Configuring the default ownership for newly registered devices

By default, all newly registered devices are configured as company-owned. You can change this default setting to employee-owned (and back) on the Registration page.

Alternatively, you can change the ownership of a device after registration by:

- selecting **More > Change Ownership** in the User Portal. For more information, see ["About changing device ownership in the user portal" on page 556](#).
- selecting **Devices & Users > Devices > Actions > Change Ownership** in Core.

## Procedure

1. In Core, go to **Settings > System Settings > Users & Devices > Registration**.
2. For the **Default ownership for a newly registered device** setting, select the relevant radio button:

**Company owned**

OR

**Employee owned**

3. Click **Save**.

## Disabling analytics data collection

Ivanti collects data to analyze the use of Core to help us provide customer support, perform bug fixes, improve product functionality and reliability and fulfill obligations to our customers. You can view details about data collected in our product privacy notice: <https://www.ivanti.com/company/legal/privacy-policy>.

The data is collected from:

- Mobile@Work
- Apps@Work

## Procedure

1. In Core, go to **Settings > System Settings > General > Analytics**.
2. Select the **Disable data collection from Mobile@Work and Apps@Work** check box.
3. Click **Save**. A confirmation dialog opens.
4. Click **Yes** to confirm or **No** to cancel and allow analytics data collection.

## Disabling the QR code and registration URL

When new users are invited to register with Core, a QR code and registration URL display by default. If your organization prefers not to show users a QR code and registration URL, an administrator can disable the feature from the **Device Registration** page of the Core admin portal.

## Procedure

1. Go to **Settings > System Settings > Users & Devices > Device Registration** page.
2. Deselect **Display QR Code and Registration URL** by clicking it.
3. Click **Save**.

## Related topics

To disable the user Activity page in the self-service portal (SSP), see ["Disabling device history logs in the self-service user portal" on page 586](#).

# Searching for Devices

The **Devices** page in the Admin Portal, offers both basic and advanced searching features. The basic search features provide a way to find devices or users using a limited set of criteria. The Advanced search features allow you to create complex search queries using the full set of available criteria. You can also apply advanced search criteria to a new or existing/unassigned or existing/unused label.

The topics in this chapter include the following advanced topics:

- ["Basic searching" below](#)
- ["Advanced searching" on the next page](#)
- ["Using the query builder" on page 97](#)
- ["Using a manually edited search expression" on page 98](#)
- ["Using both the query builder and manual editing" on page 98](#)
- ["Negative operators with advanced search" on page 100](#)
- ["Clearing an advanced search" on page 102](#)
- ["Searching for retired devices" on page 102](#)
- ["Searching for blocked devices" on page 103](#)
- ["Saving a search criterion to a label" on page 103](#)

Refer to the *Getting Started with Core* for the most commonly used topics for managing devices, such as:

- Using the Dashboard
- Creating custom attributes
- Deleting retired devices

## Basic searching

You can quickly search for devices based on the following criteria:

- Label
- User Principal/ID
- User Email Address
- User First/Last Name

To search by label, you can:

- select the appropriate label name from the **Labels** list.
- enter the initial letters of the label name in the **Labels** list.

The list changes to show only label names containing the letters you entered.

FIGURE 1. SEARCH BY LABEL

<div> <div>Actions ▾</div> <div>Add ▾</div> <div>Export to CSV</div> </div>						
	DISPLAY NAME	CURRENT PHONE ...	MODEL	MANUFAC...	PLATFOR...	HOME COUNT...
No records to display						

To search by the other criteria, select any label in the **Labels** list then use the following syntax in the **Search by User or Device** field:

- uid:<User Principal/ID>
- mail:<User Email Address>
- name:<User First/Last Name>



The prefixes mail: and name: are optional. All others are required. For example, to find the devices registered with the email address jdoe@ivanti.com, you can enter the following:

```
mail:jdoe@ivanti.com
or just
jdoe@ivanti.com
```

## Advanced searching

As data sets get larger, it is increasingly important to have a powerful search. You can use advanced search to build complex queries using the full set of available criteria (see ["Using the query builder" on page 97](#) and ["Using both the query builder and manual editing" on page 98](#).) You can also create a new label using the advanced search criteria.

To access advanced search:

1. Log into the Admin Portal.
2. Go to **Device & Users > Devices**.
3. Click the **Advanced Search** button located at the top right, above the table to display the query builder.

4. Enter search criteria using the query builder, or type the search expression directly. See "[Device field definitions](#)" below.
5. Click **Search**. Verify your results.
6. (Optional) Click **Save to Label** button. This will save your new search query as a new label and in **Devices & Users > Labels**, you can utilize this new label as a filtered label.
7. If Notes for Audit Logs is enabled, a text dialog box opens. Enter the reason for the change and then click **Confirm**. For more information, see "[Best practices: label management](#)" on page 419.

## Searchable fields

To see the complete list of searchable fields in the query builder:

1. Click **Field** to see the categories
2. Click **Expand All**.

The fields are organized alphabetically into the following categories for convenience:

- Device fields: apply to device type based on their operating system.
- OS-specific fields: apply to devices of the selected platform.
- User fields: apply to the device's user, including LDAP fields for groups and custom attributes.

## Device field definitions

This section covers the device field definitions found in the **Devices & Users > Devices** page. They also display in the Advanced Search field on the same page.



TABLE 1. DEVICE FIELD DEFINITIONS

Device Type	Field	Description
Android Fields	Admin Activated	True / false if device activated by admin.
	Android Automated Enrollment (This field is valid for Core 10.6.0.0 or supported newer versions.)	Once automated Android registration is completed, the following values display: <ul style="list-style-type: none"> <li>• Google Zero Touch</li> <li>• Knox Mobile Enrollment</li> <li>• Non Zero Touch AE Enrollment - this is for Managed Devices / Device Owner types (afw#, QR code, NFC)</li> <li>• Unknown - this value displays if versions before Core 10.6.0.0 were used. This means the "In-App Registration Requirement field in Settings &gt; System Settings &gt; Users &amp; Devices &gt; Device Registration was used. It can also mean that an old client was used with Core version 10.6.0.0 or later.</li> </ul>
	Android Client Version Code	Version code of the client.
	Android for Work Capable	True if the device is Android Enterprise capable, otherwise false.
	Attestation	Result of Samsung Attestation.
	Brand	Brand of the device.
	C2DM Token	C2DM token of the device if present, otherwise blank.
	Code Name	Code name of the Mobile@Work client
	Developer Mode	True if the Android device has Developer mode enabled, otherwise false. This is reported on all Android device configurations and also on KNOX.
	Device	Brand name of device, for example, Mako.
	Device Encryption Status	Device encryption status.
	Device Roaming Flag	True if the device is roaming, otherwise false.

TABLE 1. DEVICE FIELD DEFINITIONS (CONT.)

Device Type	Field	Description
	File encryption	True if the Android device has enabled file encryption, otherwise false. This is reported on all Android device configurations and also on KNOX.
	GCM/FCM Token Present	GCM token of the device if present, otherwise blank.
	Google Device Account Present	True if the device has a Google Device Account (eg: Android Enterprise), false otherwise.
	ICCID	Integrated Circuit Card Identifier number.
	Kiosk Enabled	True if the device is kiosk enabled, otherwise false.
	Manufacturer OS Version	Manufacturer OS version.
	MDM Enabled	True if MDM is enabled, otherwise false.
	Media Card Capacity	Amount of memory capacity of the media / SD card.
	Media Card Free	Amount of free memory on the media / SD card.
	Multi MDM	Indicates true/false.
	OS API Level	The Android OS API level. See <a href="https://developer.android.com/studio/releases/platforms">https://developer.android.com/studio/releases/platforms</a> for more details.  This number is used so administrators can use a numerical comparison of OS versions.
	OS Build Number	OS build number.
	OS Update Path	OS Update Path.
	OS Update Status	OS Update Status.
	OS Version	Lists the OS version of the device.

TABLE 1. DEVICE FIELD DEFINITIONS (CONT.)

Device Type	Field	Description
	Password/PIN Days Before Expiring	Represents the number of days before the password / PIN will expire. This numerical value is controlled by the Security policy's Maximum Password Age field value. This field is a dynamic field, its value decreases every day by 1 until the password / PIN is renewed. At renewal, the value returns to the original number stated in the Maximum Password Age field and starts a new daily count-down. See <a href="#">"Working with default policies" on page 138</a> .
	Platform Flags	Internal string representing the capabilities of the Mobile@Work application.
	Registration Status	<p>Registration status of the device. Registration Status can be used as part of a dynamic label evaluation and criteria for tier compliance.</p> <p>In the <b>Select Type</b> drop-down, select one of these options:</p> <ul style="list-style-type: none"> <li>• Device Admin</li> <li>• Device Admin Not Required</li> <li>• Work Managed Device</li> <li>• Managed Device with Work Profile</li> <li>• Work Profile</li> <li>• Work Profile for Company Owned Device</li> <li>• Unknown</li> </ul>
	Samsung DualDAR Version	Represents the Samsung Knox v3 license key for DualDAR. Lists the Samsung DualDAR version if client is enabled. If not client enabled or device is in Device Owner mode, lists as "Unsupported."
	SafetyNet Enabled	True if SafetyNet is enabled, false otherwise.
	SafetyNet Exception	SafetyNet exception during error.
	SafetyNet Status	SafetyNet status if enabled and no error.
	SafetyNet Timestamp	Timestamp of when last SafetyNet check was run.

TABLE 1. DEVICE FIELD DEFINITIONS (CONT.)

Device Type	Field	Description
	Samsung Carrier Code	Samsung Carrier code.
	Samsung E-FOTA Capable	True if the device supports Samsung E-FOTA, false otherwise.
	Samsung KNOX Version	Knox version, if present.
	Samsung Model Number	Samsung Model Number.
	Samsung SAFE Version	Samsung Safe Version.
	Screenlock PIN Change Prompt – Showing	<p>Indicates if device user was prompted to change the device's screen lock password / PIN and the device user skipped the prompt. Values are:</p> <ul style="list-style-type: none"> <li>Unknown - If coming from an older client device, value is unknown.</li> <li>True - Indicates the PIN is to expire in 7 days or less.</li> <li>False - (default) Indicates the device user is not being prompted to change the password / PIN (it has not reached its 7-day expiration window.)</li> </ul> <p>The value listed stays until the device user successfully changes the password / PIN on the device. See <a href="#">"Working with default policies" on page 138</a>.</p>
	Secure Apps Enabled	True if Secured Apps / AppConnect is enabled, otherwise false.
	Secure Apps Encryption Enabled	True if Secured Apps Encryption is enabled, otherwise false.
	Secure Apps Encryption Mode	Type of Secured Apps / AppConnect Encryption.
	Security Detail	Reason for security failure if it occurs.
	Security Patch Level	Security Patch Level string or timestamp.
	Security Patch Level Date	Date of the Security Patch Level of the OS.

TABLE 1. DEVICE FIELD DEFINITIONS (CONT.)

Device Type	Field	Description
	Security Reason	Reason device is considered jailbroken.
	USB Debugging	True if USB debugging is enabled, otherwise false.
	Wear OS Client installed	True only if one or more paired-watches have Mobile@Work installed on the Wear OS device.
	Wear OS Device is Paired	True if one or more Wear OS device is paired to device via Bluetooth.
	Zebra Build Fingerprint	Fingerprint of the firmware build currently present on the Zebra device.
	Zebra Device Build Id	Current Build ID of the Zebra device.
	Zebra Device System Update	<ul style="list-style-type: none"> <li>• <b>Unknown</b> - Not supported by client or OS version</li> <li>• <b>Current</b> - The most current update is installed. Applicable to Android 8.0 or supported newer versions. Applicable to Zebra 6 or supported newer versions.</li> <li>• <b>Pending</b> - The client has accepted a system update configuration, but the update is not yet downloaded or installed. Applicable for Zebra 6 or supported newer versions.</li> <li>• <b>Downloading</b> - An update is being downloaded. Applicable for Zebra 6 or supported newer versions.</li> <li>• <b>Available</b> - An update is available (Android 8 or supported newer versions) or downloaded (Zebra 6 or supported newer versions) but is not yet installed.</li> </ul>
	Zebra OTA Capable	True if the device supports Zebra OTA (Over The Air), otherwise false.
	Zebra Patch Version	The version of firmware for the Zebra device to be upgraded to. This is the target firmware version of the firmware applied to the Zebra device through firmware policy.
<b>Common Fields</b>	APNS Capable	Only true if there is an APNS token for the Mobile@Work client, otherwise false.

TABLE 1. DEVICE FIELD DEFINITIONS (CONT.)

Device Type	Field	Description
	AppConnect Terms of Service	True/false for if the AppConnect Terms of Service was accepted.
	AppConnect Terms of Service Date	Represents the date/time the AppConnect Terms of Service was accepted.
	Authenticator Only	True/false if the device is registered in Authenticator Only mode.
	Azure Client Status Code	<p>Indicates whether device is connected to Azure. The possible values are:</p> <ul style="list-style-type: none"> <li>• Success - Able to retrieve device ID.</li> <li>• Internal_Error - An unrecoverable error occurred either within the client or on server side.</li> <li>• Workplace_Join_Required - Registration of device required. Device user can mitigate this status.</li> <li>• Interaction_Required - An interactive log-in is required. Device user can mitigate this status.</li> <li>• Server_Declined_Scopes - Some scopes were not granted access to.</li> <li>• Server_Protection_Policies_Required - The requested resource is protected by an Intune Conditional Access policy.</li> <li>• User_Canceled - The device user cancelled the web Auth session by tapping the "Done" or "Cancel" button in the web browser.</li> <li>• Account_logged_out - Account logged out.</li> </ul>
	Azure Device Compliance Report Status	<p>Lists the device's compliance status in Azure. Possible values are:</p> <ul style="list-style-type: none"> <li>• In-progress</li> <li>• Successful</li> <li>• Failed</li> </ul>

TABLE 1. DEVICE FIELD DEFINITIONS (CONT.)

Device Type	Field	Description
	Azure Device Compliance Report Time	The time Core reported the device compliance status to Microsoft Intune. A blank field indicates one of the following: <ul style="list-style-type: none"> <li>because that feature is disabled</li> <li>Core just received the data and has yet to call the Microsoft API</li> <li>there is an error such as user_Cancelled or Internal Error so server will not report the device to Microsoft</li> </ul>
	Azure Device Compliance Status	Indicates Azure account has been deactivated or the device is not in compliance. Possible values are: Compliant / Not Compliant.
	Azure Device Identifier	The device ID reported by Microsoft to the iOS or Android device. For example: 007c8232-9489-4074-9b35-345b16f0a72d. This is Microsoft's ID for that device. Core receives this device ID as device users are required to register to Microsoft Authenticator application in order to use this feature.  If unable to retrieve the Device ID, this field is left blank.
	Background Status	True if iOS background status is enabled, otherwise false.
	Battery Level	Percentage of battery left.
	Block Reason	A list of reasons why the device is blocked.
	Blocked	True if the device is blocked, otherwise false.
	Cellular Technology	GSM, CDMA, or blank if the device does not support cellular.
	Client Build Date	The build date of the client, if registered with Mobile@Work client.
	Client Id	The unique client ID if the device was registered with Mobile@Work client.
	Client Last Check-in	Date/Time of last check-in.
	Client Migration Status	Status of Mobile@Work client migration from Core to Cloud (true/false).

TABLE 1. DEVICE FIELD DEFINITIONS (CONT.)

Device Type	Field	Description
	Client Name	The name of the client, if registered with Mobile@Work client.
	Client Version	The version of the client, if registered with Mobile@Work client; otherwise, false.
	Cloud Migration Status	Status of device migration from Core to Cloud (true/false).
	Comment	A field that the admin uses to add their own comments for the device.
	Compliant	True if the device is in compliance, otherwise false.
	Creation Date	The creation date of this device record.
	Current Country Code	Current country code of the device.
	Current Country Name	Current country name of the device.
	Current Operator Name	Short name of the cellular carrier, if there is a cellular service.
	Current Phone Number	Current phone number of device, if the device has cellular service.
	Device Admin Enabled	True if device admin (Android) is enabled, otherwise false.
	Device Encrypted	True if the device is encrypted, otherwise false.
	Device is Compromised	True if the device is compromised, for example, jailbroken.
	Device Locale	Locale of the device.
	Device Owner	Company or Personal.
	Device Space	Name of the space the device belongs to.
	Device UUID	Unique ID of the device generated from Core.
	Display Size	Size of device's display.
	EAS Last Sync Time	Exchange ActiveSync last sync time.



TABLE 1. DEVICE FIELD DEFINITIONS (CONT.)


Device Type	Field	Description
	Ethernet MAC	Ethernet MAC ID.
	Home Country Code	Home (Initial) country code of the device.
	Home Country Name	Home country name of the device.
	Home Operator Name	Home Operator Name.
	Home Phone Number	Home Phone Number.
	IMEI	IMEI (International Mobile Equipment Identity) number.
	IMSI	ISMI (International Mobile Subscriber Identity) number.
	IP Address	<p>Current IP address of the device.</p> <hr/> <p> As new GDPR fields (such as IP Address and eSIM ID) are added throughout Core releases, the administrators who have configured GDPR already will need to edit the GDPR profile if they want to hide the new fields.</p> <hr/>
	Language	Language of the device.
	Last Check-in	Last check-in time of the device.
	Manufacturer	Manufacturer of the device.
	MDM Last Check-in	Last MDM check-in time of the device.
	MDM Managed	True if the device is MDM managed, otherwise false.
	Memory Capacity	Memory capacity of the device.
	Memory Free	Amount of free memory in the device.
	MobileIron Threat Defense Status	Mobile Threat Defense Status.
	MobileIron Tunnel App Installed	True / false if the Tunnel app was installed.
	Model	Model of the device.
	Model Name	Model name of the device.

TABLE 1. DEVICE FIELD DEFINITIONS (CONT.)

Device Type	Field	Description
	Modified Date	Date/Time for last updates to device details.
	MTD Anti-Phishing Status	MTD Anti-Phishing Status.
	Non-compliance Reason	Reason why the device is not in compliance.
	OS Version	OS version number string.
	Passcode	Contains registration PIN for a preregistered device, empty if none exists.
	Passcode Expiration Time	The expiration time for the registration pin for a preregistered device, empty if none exists.
	Platform	Operating system of the device.
	Platform Name	Operating system and OS version of the device.
	Processor Architecture	Architecture of the processor for the device.
	Quarantined	True if the device is quarantined, false otherwise.
	Quarantined Reason	Reason for quarantined, empty if the device is not quarantined.
	Registration Date	Registration date of the device.
	Registration IMSI	Registration of ISMI (international mobile subscriber identity) number.
	Registration UUID	Unique ID when registering from the client.
	Retired	True if the device is retired, otherwise false.
	Roaming	True if the device is roaming, otherwise false.
	SD Card Encrypted	True/false if SD card is encrypted.
	Security State	Security state of the device.
	Serial Number	Serial number of the device.
	Status	Status of the device.

TABLE 1. DEVICE FIELD DEFINITIONS (CONT.)

Device Type	Field	Description
	Storage Capacity	Total storage capacity, in bytes, of the device.
	Storage Free	Number of bytes of free storage on the device.
	Terms of Service Accepted	True if the End user Terms of Service was accepted, otherwise false.
	Terms of Service Accepted Date	Date for when the End User Terms of Service was accepted, otherwise blank.
	Wi-Fi MAC	Wi-Fi MAC address of the device.
<b>iOS Fields</b>	Activation Lock Bypass Code	Code to bypass activation lock.
	Activation Lock is Enabled	True if Activation Lock is enabled on the device, otherwise false. Applicable to iOS.
	APNS Token	Mobile@Work client APNS wakeup token. Applicable to iOS.
	Apple Device Mac Address	iPhone (media access control address) MAC address. Applicable to iOS and OS X.
	Apple Device Version	iPhone version code. Applicable to iOS and OS X.
	Apple OS Update Product Key	Available OS update product key. Applicable to iOS and macOS.
	Apple OS Update Product Version	Available OS update product version. Applicable to iOS and macOS.
	Apple OS Update Status	OS update status. Applicable to iOS and macOS.
	Bluetooth MAC	Bluetooth MAC address. Applicable to and OS X.
	Build Version	MDM build version. Applicable to iOS and OS X.
	Carrier Settings Version	Carrier settings version. Applicable to iOS.
	Current Mobile Country Code	Current mobile country code. Applicable to iOS.
	Current Mobile Network Code	Current mobile network code. Applicable to iOS.
	Data Protection	Applicable to iOS.

TABLE 1. DEVICE FIELD DEFINITIONS (CONT.)


Device Type	Field	Description
	Data Roaming Enabled	True if device is data roaming enabled, otherwise false. Applicable to iOS.
	DEP Device	True if the device is Apple Device Enrolled, otherwise false. Applicable to iOS, macOS, and tvOS.
	DEP Enrolled	True if the device is Apple Device Enrolled, otherwise false. Applicable to iOS.
	Device Locator Service is Enabled	True if device locator service is enabled, otherwise false. Applicable to iOS.
	Device Name	Name of the device. Applicable to iOS and OS X.
	Do Not Disturb is in Effect	True if Do Not Disturb is enabled, otherwise false. Applicable to iOS.
	eSIM ID (EID)	<p>True to allow the cellular carriers to assign the SIM to a specific device. An example eSIM ID is: 89049032004008882600006858322414.</p> <p>The eSIM ID field is GDPR-compliant.</p> <hr/> <p> As new GDPR fields (such as IP Address and eSIM ID) are added throughout Core releases, the administrators who have configured GDPR already will need to edit the GDPR profile if they want to hide the new fields.</p> <hr/>
	Force Encrypted Backup	True if backups are forced to be encrypted, otherwise false. Applicable to iOS.
	Full Disk Encryption Enabled	True if full disk encryption is enabled, otherwise false. Applicable to macOS 10.9+.
	Full Disk Encryption Has Institutional Recovery Key	True if full disk encryption has institutional recovery key, otherwise false. Applicable to macOS 10.9+.
	Full Disk Encryption Has Personal Recovery Key	True if full disk encryption has personal recovery key, otherwise false. Applicable to macOS 10.9+.
	Hardware Encryption Caps	Hardware encryption capabilities. Applicable to iOS.

TABLE 1. DEVICE FIELD DEFINITIONS (CONT.)

Device Type	Field	Description
	iCloud Backup is Enabled	True if Cloud backup is enabled, otherwise false. Applicable to iOS.
	iOS Background Status	True if iOS background status is enabled, otherwise false. Applicable to iOS.
	iOS ICCID	Device's integrated circuit card identifier number. Applicable to iOS.
	IT Policy Result	Applicable to iOS.
	iTunes Store Account Hash	iTunes Store Account Hash.
	iTunes Store Account is Active	True if iTunes Store Account is active, otherwise false. Applicable to iOS.
	Languages	Language of the device. Applicable to tvOS.
	Last Acknowledged Lock PIN	PIN to unlock a locked macOS device. Applicable to macOS.
	Last Acknowledged Wipe PIN	PIN to proceed after wiping a macOS device. Applicable to macOS.
	Last iCloud Backup Date	Last iCloud backup date. Applicable to iOS.
	Last MTD Sync Time	Last MTD check-in time. Applicable to iOS.
	Locales	Locale of the device. Applicable to tvOS.
	macOS User ID	macOS user ID. Applicable to OS X.
	macOS User Long Name	macOS user's long name. Applicable to OS X.
	macOS User Short Name	macOS user's short name. Applicable to OS X.
	Maximum Resident Users	Only for use with iOS Education Shared iPads. Tells the device how many users will have their data cache on the device. When the device reaches this number, the next logged-in user that is not already present will be cached and one of the cached users will be removed from the cache (up to Apple which user.) Applicable to iOS.

TABLE 1. DEVICE FIELD DEFINITIONS (CONT.)

Device Type	Field	Description
	MDM Lost Mode Enabled	True if MDM Lost Mode is enabled, otherwise false. Applicable to iOS.
	MDM Service Enrolled	True if the device is was enrolled via MDM Service (non-over air Apple Device Enrollment), otherwise false. Applicable to iOS.
	MEID	Mobile Equipment Identity Number.
	Modem Firmware Version	Modem firmware version. Applicable to iOS.
	Network Tethered	True if the device was reported as currently network tethered, otherwise false. Applicable to macOS.
	Organization Info	Organization for the device. Applicable to iOS.
	Passcode Compliant	True if passcode is in compliance, otherwise false. Applicable to iOS.
	Passcode Compliant with Profiles	True if passcode is compliant with rules specified from profiles. Applicable to iOS.
	Passcode Present	True if Passcode is present on device, otherwise false. Applicable to iOS.
	Personal Hotspot Enabled	True if Personal Hotspot is enabled, otherwise false. Applicable to iOS.
	Product Code	iPhone Product code. Applicable to iOS and OS X.
	Product Name	Product name. Applicable to iOS and OS X.
	Security Reason Code	Security reason code. Applicable to iOS.
	SIM Label 1, 2, 3	SIM label associated to the phone number.
	SIM MCC 1, 2, 3	SIM card mobile country code associated to the phone number.
	SIM MNC 1, 2, 3	SIM card mobile network code associated to the phone number
	SIM Phone Number 1, 2, 3	The phone number associated with the SIM card / eSIM.

TABLE 1. DEVICE FIELD DEFINITIONS (CONT.)

Device Type	Field	Description
	SIM EID 1, 2, 3	<p>The SIM ID of the carrier assigned to the SIM of a specific device. The EID will be included in the response of the <code>simdetails</code> API call. (For more information, see the <i>V2 API Guide</i>.)</p> <p>In the Device Details page, clicking on the number in the field opens the SIM Information dialog box allowing the administrator to see SIM information, including the EID. Applicable to iOS 14.0 through the latest version of Core.</p>
	SIMs	<ul style="list-style-type: none"> <li>Lists the number of SIMs associated to the device. This includes embedded SIMs (eSIM) and physical SIMs.</li> <li>There can be multiple SIMs associated with the eSIM.</li> <li>For eSIMs in iPhone XS, iPhone XS Max, or iPhone XR with iOS 12.1 or supported newer versions.</li> </ul>
	Subscriber Carrier Network	SIM card subscriber carrier network. Applicable to iOS.
	Subscriber MCC	SIM card mobile country code. Applicable to iOS.
	Subscriber MNC	SIM card mobile network code Applicable to iOS.
	Supervised	True if the device is MDM supervised, otherwise false. Applicable to iOS.
	Time Zone	Lists the time zone applied to the device.
	UDID	iPhone unique device identifier. Applicable to iOS and OS X.
	Voice Roaming Enabled	True if voice roaming is enabled, otherwise false. Applicable to iOS.
	VPN IP Address	VPN IP address. Applicable to iOS and tvOS.
	Wakeup Status	Device Wakeup status.
<b>User Fields</b>	Display Name	The display name of the device user.
	Email Address	Device user's email address.
	First Name	Device user's first name.

TABLE 1. DEVICE FIELD DEFINITIONS (CONT.)

Device Type	Field	Description
	Last Admin Portal Login Time	Date of admin's last log in into Core.
	Last Name	Device user's last name.
	LDAP > Attribute Distinguished Name	The Attribute Distinguished Name for an LDAP user.
	LDAP > Groups > LDAP Group Distinguished Name	LDAP Users who are members of an LDAP group with a specific group distinguished name.
	LDAP > Groups > Name	LDAP Users who are members of an LDAP group with a specific group name.
	LDAP > LDAP User Distinguished Name	The LDAP distinguished Name of the user.
	LDAP > LDAP User Locale	An LDAP User who are members of a specific locale.
	LDAP > Principal	Value of the attribute specified as the User ID in the LDAP server configuration.
	LDAP > upn	Value of the attribute specified as the User Principal Name in the LDAP server configuration.
	LDAP > User Account Control > Account Disabled	Indicates whether the LDAP user account is disabled (true/false).
	LDAP > User Account Control > Locked Out	Indicates whether the LDAP user account is locked out (true/false).
	LDAP > User Account Control > Password Expired	Indicates whether the LDAP user 's password has expired (true/false).
	LDAP > User Attributes > custom1	The value of the LDAP user attribute is defined in <b>Services &gt; LDAP</b> .
	LDAP > User Attributes > custom2	The value of the LDAP user attribute is defined in <b>Services &gt; LDAP</b> .



TABLE 1. DEVICE FIELD DEFINITIONS (CONT.)

Device Type	Field	Description
	LDAP > User Attributes > custom3	The value of the LDAP user attribute is defined in <b>Services &gt; LDAP</b> .
	LDAP > User Attributes > custom4	The value of the LDAP user attribute is defined in <b>Services &gt; LDAP</b> .
	LDAP > User Attributes > memberOf	The value of the LDAP user attribute is defined in <b>Services &gt; LDAP</b> .
	SAM Account Name	The security account name. This was the login name for earlier versions of Windows.
	User ID	The LDAP user ID.
	User UUID	The LDAP Universally Unique Identifier.

For **Windows** field definitions, see <https://docs.microsoft.com/en-us/windows/client-management/mdm/healthattestation-csp>.

## Using the query builder

To use the query builder:

1. Select a field on which to search. **Hint:** you can type a few letters of the field name to see a short list of matching fields, or press **Expand All** within the field list to see all the fields.  
For example, if you select **Status**, the search engine provides only values available for **Status**.
2. Select an operator, such as **Equals**.
3. Click in the **Value** field to enter a value you want to search.
4. Some fields have predetermined values that you can select.
5. Select additional fields and criteria as needed.
6. Click **All** to combine the criteria with a logical AND or click **Any** to combine the criteria with OR.
7. Click **Search** to display the matching devices and their owners.



To include retired devices in the results, uncheck the check box to the left of the **Search** button.

## Using a manually edited search expression

To enter a search expression directly into the expression field:

1. Type or paste the search criteria into the expression field. The automatic syntax check displays a status icon next to the expression field. A green icon indicates that the syntax is correct, and a red icon if incorrect.
2. When the syntax is correct, click **Search** to display the matching devices and their owners.

## Using both the query builder and manual editing

Use the query builder to start an expression, look up field syntax, and select predetermined values. Then, edit the expression directly as needed.

1. Select fields and criteria.
2. Click **All** to combine multiple criteria with a logical AND or **Any** to combine multiple criteria with OR. You can manually edit individual logical operators in the expression field.
3. In the expression field, edit the expression directly.
4. For example, you can add parentheses, change logical operators, or manually edit field names or values.
5. The automatic syntax check displays a status icon next to the expression field. A green icon indicates that the syntax is correct, and a red icon if incorrect.
6. When the syntax is correct, click **Search** to display the matching devices and their owners.

Once you manually edit the expression, the query builder is covered with a gray box to indicate it no longer represents the current state of the expression. Click the **Reset** link to remove your manual edits and continue using the query builder.

**Example:** Find all iOS or Android devices that use AT&T as their service operator.

FIGURE 1. SERVICE OPERATOR IN QUERY BUILDER

**All** **Any** of the following rules are true ✕

Platform	Equals	iOS	+	-
Platform	Equals	Android	+	-
Home Operator Name	Equals	United States	+	-

☒ ("common.platform" = "iOS" OR "common.platform" = "Android") AND "common.home\_operator\_name" = "AT&T" Reset

☒ Exclude retired devices from search results Search Save to Label Clear

Build the expression to match the above example.

1. Click **Advanced Search** to open the query builder.
2. Select **Platform** in the first field, select **Equals** for the operator, then select **iOS** as the platform.
3. Click the plus icon to add another row for criteria.
4. Select **Platform**, **Equals**, and **Android** as the field, operator, and platform value, respectively.
5. Click the plus icon to add a third row for criteria.
6. Select **Home Operator Name** for the field and **Equals** for the operator.

Notice that the value field adjusts automatically to display service operator values by country.

7. Accept the first value field and select **AT&T** in the second value field.

Manually edit the expression.

1. Replace the first **AND** with **OR**.

The syntax is checked automatically as you type. Note a red icon indicating incorrect syntax while you edit the expression.

2. Add parentheses around the phrase to read:

```
("common.platform" = "iOS" OR "common.platform" = "Android") AND  
"common.home_operator_name" = "ATT&T"
```

Note a green icon indicating correct syntax has replaced the red icon. Your advanced search will look the same as the original image (see below).

The screenshot shows an advanced search interface. At the top, there are two tabs: "All" and "Any", followed by the text "of the following rules are true". Below this is a table with three rows of rules. Each row has a field name, an operator, a value, and two buttons (+ and -). The first row is "Platform" equals "iOS". The second row is "Platform" equals "Android". The third row is "Home Operator Name" equals "United States" and "ATT&T". Below the table is a search bar with a green checkmark icon on the left and a "Reset" link on the right. The search bar contains the text: `("common.platform" = "iOS" OR "common.platform" = "Android") AND "common.home_operator_name" = "ATT&T"`. Below the search bar is a checkbox labeled "Exclude retired devices from search results". At the bottom right are three buttons: "Search", "Save to Label", and "Clear".

To revert to the original expression without your manual edits, click the **Reset** link to the right of the expression.

3. Click **Search** to display the matching devices and their owners.

## Negative operators with advanced search

Using negative operators enables you to create filters that exclude devices instead of including them. For example, you can search for:

- Devices that use any platform other than iOS
- Devices with a current country code other than US

TABLE 1. NEGATIVE OPERATORS WITH ADVANCED SEARCH

Operator	Action	Example
Does not equal	Returns a list of devices that do not match the criteria specified in the value field for the selected field.	<p>Select:</p> <ul style="list-style-type: none"> <li>• <b>Home Country Name</b> as the field</li> <li>• <b>Does not equal</b> in <b>Operator</b></li> <li>• <b>United States</b> in <b>Country Name</b></li> </ul> <p>The search returns a list of devices that do not have United States as their home country name.</p>
Does not contain	<p>Returns a list of devices that do not contain the string specified in the selected field.</p> <ul style="list-style-type: none"> <li>• Used only with strings.</li> <li>• Available only in the expression field.</li> </ul>	<p>Select or enter:</p> <ul style="list-style-type: none"> <li>• Go to <b>Common Fields</b> and select <b>Device Space</b>.</li> <li>• In the expression field, enter: does not contain</li> <li>• Place the cursor between the two quote marks in the expression field and enter: <b>Global</b></li> </ul> <p>The search returns a list of devices that are not assigned to the <b>Global</b> space.</p>

## Examples for advanced search with negative operators

To display a list of devices that have countries other than the United States as the assigned home country, create an advanced search expression that provides the necessary information.

1. Go to **Device & Users > Devices**.
2. Click the large magnifying glass icon located at the top right to initiate an advanced search.
3. In **Field**, select **Common Fields**.
4. Select **Home Country Name**.
5. Select **Does not equal** from the list in **Operator**.
6. Select **United States** from the list of countries in **Country Name**.
7. Click **Search**.
8. **Optional:** To save the search to a label, click **Save to Label** and then provide an existing label name or a new label name and description.

9. If Notes for Audit Logs is enabled, a text dialog box opens. Enter the reason for the change and then click **Confirm**. For more information, see ["Best practices: label management" on page 419](#).

Suppose you want to list users within an LDAP group that have a Home Country Code other than the United States (US).

To create the advanced search expression that provides the needed list:

1. Go to **Device & Users > Devices**
2. Click the large magnifying glass icon located at the top right to initiate an advanced search.
3. In the expression field enter the following, including quote marks:  
`"user.ldap.groups.name" = "Corp_Users" AND "common.home_country_code" != "US"`
4. Click **Search**.
5. **Optional:** To save the search to a label, click **Save to Label** and then provide a new label name and description.
6. If Notes for Audit Logs is enabled, a text dialog box opens. Enter the reason for the change and then click **Confirm**. For more information, see ["Best practices: label management" on page 419](#).

## Clearing an advanced search

- In the advanced search, click the **Clear** link, or
- Apply a different search by entering a basic search.

Closing the advanced search query builder does not clear the search.

## Searching for retired devices

By default, retired devices are excluded from search results. To include them, uncheck the Exclude Retired Devices From Search Results check box, located to the left of the Search button in advanced search.

To find only retired devices:

1. Uncheck the check box to exclude retired devices
2. Select the following in the advanced search query builder:
  - Field: **Retired**
  - Operator: **Equals**
  - Value: **true**
3. Click **Search**.

The matching records are displayed.


# Searching for blocked devices

You can search for devices for which the status field value is **Blocked**, which means that the device is blocked from accessing the ActiveSync server. However, the **Status** column does not show the value **Blocked**. Instead, the ActiveSync Association view shows this information. See “Viewing ActiveSync associations” in the *Sentry Guide for Core*.

# Saving a search criterion to a label

Once you create a search criterion, you can save it to a label. Click the **Save To Label** button in advanced search to create a new label using the search criterion. Type a new label name in the **Label** field and type a description. The new filter label is created with the advanced search criterion applied.

FIGURE 1. SAVING A SEARCH CRITERION TO A LABEL



If Notes for Audit Logs is enabled, a text dialog box opens. Enter the reason for the change and then click **Confirm**. For more information, see ["Best practices: label management" on page 419](#).

# Securing Devices

Securing devices is at the heart of Core. The topics in this chapter include the following advanced topics:

- ["Registration-related features and tasks" on the next page](#)
- ["Reprovisioning a device" on the next page](#)
- ["Using self service security features" on the next page](#)
- ["Retiring a device" on page 106](#)
- [Deletion of retired devices](#)
- ["Security-related features and tasks" on page 111](#)
- ["Lock" on page 113](#)
- ["Unlock" on page 113](#)
- ["Unlock AppConnect container" on page 115](#)
- ["Encryption" on page 115](#)
- ["Android Security Patch level" on page 115](#)
- ["Wipe" on page 116](#)
- ["Cancel Wipe" on page 117](#)
- ["Selective Wipe" on page 118](#)
- ["Block AppTunnels" on page 118](#)
- ["Lost" on page 118](#)
- ["Found" on page 119](#)
- ["Locate" on page 119](#)
- ["Reset device PIN" on page 120](#)
- ["Force Device Check-In" on page 120](#)
- ["Setting up background check-ins with APNs" on page 121](#)
- ["Managed iBooks" on page 121](#)
- ["Personal hotspot on/off switch" on page 121](#)
- ["Using custom APN with Android devices" on page 121](#)
- ["Custom Configuration support for Zebra devices" on page 126](#)



- ["Reporting on managed devices" on page 127](#)
- ["Setting the time zone of a device" on page 130](#)

Refer to the *Getting Started with Core* for the most commonly used topics for managing devices, such as:

- Displaying device assets
- Restricting the number of devices a user registers

## Registration-related features and tasks

The following table summarizes features and tasks related to registration.

TABLE 1. REGISTRATION-RELATED TASKS

Feature	Description	Use Case
Reprovisioning a device	Restarts the Core provisioning process for the device	Troubleshooting incomplete registration
Retire	Ends the registration (and Core management) for a device	Moving devices out of inventory

## Reprovisioning a device

Select **Re-provision Device** to restart the Core provisioning process without repeating the whole registration process. For example, you might want to do this if the initial attempt was interrupted, leaving the registration in the Pending state.



This action applies only to devices in the Pending or Verified state. To reinstall the Core Client for devices in the Active state, you can either restore from a backup snapshot or retire the device and re-register it. To reinstall the client in the Wiped state, you must re-register the device.

### Procedure

1. Go to **Device & Users > Devices**.
2. Select the check box for the device.
3. Select **Actions > Re-provision Device**.
4. The same registration settings are used.

## Using self service security features

Users can perform lock, unlock, wipe and retire functions on devices on which they are registered from the new **My Devices** page on the device.

## Procedure

1. Open the Mobile@Work app on the device.
2. Click the menu icon in the upper left corner of the landing page.
3. Click **My Devices**.
4. You are prompted to login. Login is required when accessing the page for the first time.
5. Click **Continue**.  
A list of the devices on which the user is registered is displayed on the **My Devices** page.
6. Select the device. The **Device Details** page is displayed.
7. Choose to **Lock Device** or **Unlock Device**.  
When **Lock Device** or **Unlock Device** is selected the user is prompted to enter their password and confirm the action.
8. Click the menu icon on the upper right to select **Wipe** or **Retire** the device.  
When **Wipe** or **Retire** is selected the user is prompted to enter their password and confirm the action.

## Retiring a device

Retiring a device archives the data for that device and removes the configurations and settings applied by Core (no personal information or settings on the device are impacted). The entry for the device no longer appears in the **Device & Users** page (unless you specifically search for retired devices), and the user is notified that the software has been removed.

If the retired device is also in the ActiveSync Association view, it remains there. However, because the device is retired, it can no longer access the ActiveSync server. You can manually remove the device from the ActiveSync Association page. See "Removing ActiveSync phones" in the *Sentry Guide for Core*.

Retiring an Android device means the device user cannot access any AppConnect apps or data. For details, see the *AppConnect Guide for Core*.

If you have duplicate devices, see [Managing Duplicate Devices](#).

## Procedure

1. Go to **Device & Users > Devices**.
2. Select the check box for the device.
3. Click **Actions > Retire**.  
The **Retire** dialog appears.
4. In the **Retire** dialog, confirm the user and device information and enter a note.

5. Click **Retire**.

The user receives notification of the action.

To see a list of retired devices, see "Searching for retired devices" in the *Getting Started with Core*.

## Retiring and deleting unused and retired devices

As device users leave your enterprise or change to new devices, more and more devices in the Core database are retired or never activated. When you retire a device, Core de-registers it and no longer manages or secures the device. All the configurations and settings that Core had applied to the device are removed. The device can no longer access enterprise data or apps.

However, Core retains retired and unregistered devices in its database. Deleting these devices from the database improves Core performance and frees up disk space. Although Core also provides a web services API and a CLI command to delete these devices, using the Admin Portal display is easier. It also provides an easy way to automatically delete or retire devices on a regular schedule.

With this Admin Portal display, you can:

- Easily navigate to lists of unregistered and retired devices.
- Retire or delete devices that have been retired or not checked in for more than a specified number of days.
- Configure Core to automatically retire or delete devices daily, weekly, or monthly.



You can use this display only if you are assigned to the global space **and** you are assigned the admin role Delete retired device. Otherwise, the actions on this display are disabled.

---

When Core retires or deletes retired devices due to your actions on this display, it records Delete Retired Device events in the audit log. Personal data related to retired devices can be deleted by deleting the local user. However, LDAP users cannot be permanently deleted unless the LDAP server or group has been deleted, in which case the LDAP users become local users and can be deleted. If a user is deleted on the LDAP server, the user is automatically removed from Core during the next LDAP sync.

## Assigning an administrator the role to delete retired devices

If you are a super administrator, you can assign another administrator the capability to delete retired devices. You are a super administrator if you are:

- Assigned to the global space.
- Assigned the role **Manage administrators and device spaces**.

### Procedure

1. In the Admin Portal, go to **Admin > Admins**.
2. Select an administrator.
3. Select **Actions > Edit roles**.
4. For **Admin Space**, select **Global**.
5. Select the **Device Management** role **Delete retired device**.
6. Click **Save**.

## Retiring or deleting retired devices by threshold

A common task, although not necessarily a daily task, is retiring unused or deleting retired devices. You can retire devices that have not checked in or delete retired devices by a threshold amount of time. Deleting these devices from the database improves Core performance and frees up disk space.

### Prerequisites

Make sure you are assigned the required admin role. To delete or retire devices, you must be:

- Assigned to the global space
- Assigned the admin role **Delete retired device**

### Procedure

1. From the Admin Portal, go to **Settings > System Settings**.
2. Select **Users & Devices > Retire and Delete Retired Devices**. The Retire and Delete Retired Devices configuration page opens.

The settings to retire unused devices (top half of the page) are identical to the settings to delete retired devices (bottom half of page). The following steps are correct for either task, and all are optional steps, except saving the configuration.

## Retire And Delete Retired Devices

CancelSave

---

Retire Devices That Have Been Not Checked-In More Than (days)

30

Show not checked-in devices list

Maximum Devices to Retire in Each Session

100

i

☐ Automatically Retire Devices on a Schedule

Retire Now

Last Retire session: None

---

Delete Devices That Have Been Retired More Than (days)

30

Show retired devices list

Maximum Retired Devices to Delete in Each Session

100

i

☐ Automatically Delete Retired Devices on a Schedule

Delete Now

Last delete session: None

3. Specify the number of days after which devices should be retired/deleted, or accept the default of **30 days**.
4. Specify the maximum number of devices to retire/delete in each session, or accept the default of **100 devices**.
5. To set up a regular schedule for retiring/deleting devices, click **Automatically Retire Devices on a Schedule** or **Automatically Delete Retired Devices on a Schedule** to configure the schedule. See ["Creating a schedule to retire or delete devices" on the next page](#).
6. Click **Retire Now** or **Delete Now** to retire or delete the devices that meet the new criteria.
7. Click **Save** to save the configuration.

NOTE: If the **Retire Now/Delete Now** button is disabled, only an administrator who is a "super administrator" can assign you to the global space and assign the Delete retired device admin role to you. The procedure for the super administrator and definition of a super administrator are in ["Assigning an administrator the role to delete retired devices" on page 107](#).

## Creating a schedule to retire or delete devices

You can enable a regular schedule to retire unused devices and delete retired devices. The schedule tool works identically for each task.

### Procedure

1. In the Admin portal, navigate to Settings > System Settings > Users & Devices > Retire and Delete Retired Devices.
2. Click **Automatically Delete Retired Devices on a Schedule**, or **Automatically Retire Devices on a Schedule**. The Schedule Configuration opens.

3. **Frequency:** Select **Daily**, **Weekly**, or **Monthly**.

a. **Daily:** Select the run time from the **At:** drop-down menu. The default is midnight.

☒ Automatically Retire Devices on a Schedule

**RETIRE SCHEDULE CONFIGURATION**

Frequency: ☒ Daily ☐ Weekly ☐ Monthly

At:  ▼

b. **Weekly:** Select the day and time for the clean up. Default value is Sunday at midnight.

☒ Automatically Retire Devices on a Schedule

**RETIRE SCHEDULE CONFIGURATION**

Frequency: ☐ Daily ☒ Weekly ☐ Monthly

On:  ▼ At:  ▼

c. **Monthly:** Select the time for a first-day-of-the-month schedule frequency. Default is first day of the month at midnight.

☒ Automatically Retire Devices on a Schedule

**RETIRE SCHEDULE CONFIGURATION**

Frequency: ☐ Daily ☐ Weekly ☒ Monthly

On First Day At:  ▼

4. Click **Save**.

## Security-related features and tasks

The following table summarizes the features and tasks related to security.

TABLE 1. SECURITY-RELATED FEATURES AND TASKS

Feature	Description	Use Case
Lock	Forces the user to enter a password before accessing the device	Dealing with lost and stolen devices
Unlock	Reverses the Lock function	<p>Accessing the device when the passcode has been forgotten or reassigning the device to a different user</p> <hr/> <p> For security reasons, it is inadvisable to execute this command on lost or stolen devices.</p> <hr/>
Unlock AppConnect Container	Unlocks the AppConnect container (clears the AppConnect passcode)	The device user has forgotten the AppConnect passcode.
Device Encryption Status	Displays the encryption status of the device in the Device Details tab.	Dealing with lost and stolen devices.
Android Security Patch level	Displays the Android Security patch level of the device in the Device Details tab.	Enables an admin to verify that the deployed devices have the latest Android security patches.
Wipe	Removes content and settings to return the device to factory default settings.	<p>Dealing with lost and stolen devices</p> <p>Preparing a device for a different user</p>
Cancel Wipe	Attempts to cancel a wipe action for devices.	<p>Reversing an inadvertent Wipe command.</p> <hr/> <p> Wipe cannot be reversed after it completes.</p> <hr/>
Block AppTunnels	This feature is not supported on Android devices.	
Lost	Flags a device as lost	Dealing with lost and stolen devices



TABLE 1. SECURITY-RELATED FEATURES AND TASKS (CONT.)

Feature	Description	Use Case
Found	Flags a device as found	Dealing with lost and stolen devices
Locate	Reports the last known location for a device	Dealing with lost and stolen devices
Reset PIN	This feature is not supported on Android, iOS, or macOS devices.	

### Related topics

["Samsung Knox Dual Encryption \(DualDAR\) support" on page 504](#)

## Lock

Locking a device forces the user to enter a password to access the device and prevents the user from reversing this restriction. The user is informed of this action via email. If the user has set a password for the device, then that password must be entered. Locking an Android device also causes the device user to be locked out of AppConnect apps. For details, see the *AppConnect Guide for Core*.

### Procedure

1. Go to **Device & Users > Devices**.
2. Select the check box for the device.
3. Select **Lock** from the **Actions** menu.



---

If the Mobile@Work app on the selected device is currently connected, then this action will be applied immediately. If the Mobile@Work app is not currently connected, then Core Core attempts to complete the operation by means of the operator's SMTP service. If SMTP is used, it may take more time to execute the operation, and the time required may vary by operator.

---

## Unlock

Unlocking the device passcode is supported as follows:

TABLE 1. SUPPORT FOR UNLOCKING THE DEVICE PASSCODE ON ANDROID DEVICES

Android Enterprise device	Prior to Android 7.0	Android 7.0 or supported newer versions
Work Managed Devices	Supported	Supported
Work Profile Devices	Supported	Not supported
Work Profile on Company Owned Devices	N/A	Not supported
Android (not using Android Enterprise)	Supported	Not supported Unlock is not supported because these versions of Android do not allow a command to change the device passcode.

### Procedure

1. Go to **Device & Users > Devices**.
2. Select the check box for the device.
3. Click **Actions > Unlock**.

Unlock behavior on Android:

- The Unlock command causes Mobile@Work for Android to attempt to remove the existing passcode from an Android device. If the attempt is successful, the user will be able to access the device with the default Swipe.
- On devices with Mobile@Work, the default passcode is always set to 0000.
- If the Administrator forces a password reset, the Mobile@Work client itself will try to unlock the device, if possible, or the user can unlock the device using the default password, 0000. The user is forced to change that password to one that conforms to password requirements defined in the Security policy. This applies to devices in:
  - Device Admin or Device Owner modes using an OS older than Android 7 or supported newer versions.
  - Managed Device with Work Profile (COPE) mode (Android versions 8-10 only) and Work Profile on Company Owned Devices mode (Android 11 or supported newer versions.)
  - Profile Owner supporting Work Challenge using Android 6 or supported newer versions. Device user of Android 6 device in Profile Owner without Work Challenge support may unlock with "0000" (the default) password, but is not forced to change the password.

- The passcode reset flow would only be triggered when the profile/device is locked. If the administrator sends a "Unlock" command and the profile is not locked then Core will not reset it to 0000 and not bring up the password reset screens. Otherwise, the only time Core will reset to 0000 and bring up the reset screens would be when the profile or Android device is locked. This is applicable to Mobile@Work 11.1.0.0 or supported newer versions and to the following Android Enterprise modes:
  - Device Admin mode (on some devices)
  - Device Owner mode
  - Work Profile mode
  - Managed Device with Work Profile mode
  - Work Profile on Company Owned Device mode
- Android Enterprise Work Managed mode-registered devices that are in kiosk mode move out of kiosk when you send the UNLOCK command from Core. This only happens when the password is mandatory as per the Security Policy on Core.
- For Android Enterprise devices, see ["Unlocking an Android Enterprise device" on page 61](#).

## Unlock AppConnect container

To unlock the AppConnect container (clear the AppConnect passcode):

1. Go to **Device & Users > Devices**.
2. Select the check box for the device.
3. Select **Actions > Android Only > Unlock AppConnect Container**.

## Encryption

The encryption status for a device is now reported on the device details tab.

To check the encryption status of a device:

1. Log into the Admin Portal.
2. Go to **Device & Users > Devices > Device Detail**.

The device encryption status displays as Activating, Active, Active Per User, Active Default Key, Inactive, Unsupported, or None.

## Android Security Patch level

The security patch level of an Android device is reported on the device details tab. This is available on Android devices using Android 6 or supported newer versions. To check the security patch level of an Android device:

1. Go to **Device & Users > Devices**.
2. Select an Android device.
3. Use the drop-down menu to configure search rules to find the patch level.
4. In the first drop-down menu, select **Security Patch Level**.
5. Use the other fields to define your search.
6. Optionally, select the **Exclude retired devices from search** results check box.
7. Click **Search** or click **Save to Label**.

If you click **Save to Label** and Notes for Audit Logs is enabled, a text dialog box opens. Enter the reason for the change and then click **Confirm**. For more information, see ["Best practices: label management" on page 419](#).

8. Go to **Device & Users > Devices > Device Detail**.

The **Security Patch Level** displays in the **Device Details** tab.

## Wipe



This feature can also be used on SD cards, for most devices.

---

When wiping a device, Core informs the user of this action via email.

Starting with version 11.1.0.0, administrators can wipe the device in Direct Boot mode in all Android Enterprise modes.

**WARNING:** Wiping a device returns it to factory defaults, which can result in loss of data.

**Required Role:** The Device Management: Wipe device role is required to use this feature.

### Procedure

1. Go to **Device & Users > Devices**.
2. Select the check box for the device to be wiped.
3. Click **Actions > Wipe**.

4. Optionally, select one or more of the following options:

- **Preserve data plan (iOS 11 and later devices only)** - Select this option to retain the data plan on devices running iOS 11, if one exists.
- **Skip Proximity Setup (iOS 11.3 and later devices only)** - Select this option to skip the proximity setup pane in the iOS Setup Assistant.
- **Send Notification of wipe to registered user** - Select (default) to allow an email / notification to be automatically generated when a Wipe command is sent. The Send Notification of wipe to registered user field is useful for users that have multiple devices. An email / notification will be automatically generated when the Wipe command is sent and prevents confusion to device users who may think Core is wiping their current, active device. De-select the check box to suppress notification when the Wipe command is used.



To customize the email notification, go to **System Settings > Settings > Templates > Other**. Select the template type **Action on Device**.

---

5. Click **Wipe**.



If the Mobile@Work app on the selected device is currently connected, then this action will be applied immediately. However, if the Mobile@Work app is not currently connected, then Core Core will attempt to complete the operation by means of the SMTP configuration.

---

## Related topics

["Cancel Wipe" below](#)

## Cancel Wipe

Cancel Wipe attempts to cancel a wipe command for one or more devices. The ability to cancel a device wipe action helps you avoid mistakes that can be difficult and costly to fix.

A device wipe action does not take effect until the device checks in with Core. Using **Cancel Wipe**, you may be able to stop the wipe action.

**Cancel Wipe** is supported for Android devices with status: **Wipe pending**.

A successful **Cancel Wipe** action sets the device state to **Active**.

1. In the Admin Portal, go to **Device & Users > Devices**.
2. Check the status of the devices for which you need to cancel the device wipe.
3. Select the devices you do not want to wipe that have status **Wipe pending** or **Wiped**.
4. Click **Actions > Cancel Wipe**.

5. In the Cancel Wipe dialog box, select the **Send Notification of wipe to registered user** check box. The Send Notification of wipe to registered user field is useful for users that have multiple devices. An email / notification will be automatically generated when the Cancel Wipe command is sent and prevents confusion to device users who may think Core is wiping their current, active device. De-select the check box to suppress notification when the Cancel Wipe command is used.



To customize the email notification, go to **System Settings > Settings > Templates > Other**. Select the template type **Action on Device**.

---

6. Click **Cancel Wipe**.

The Cancel Wipe action sets the device state to **Active**.

### Related topics

["Wipe" on page 116](#)

## Selective Wipe

The Selective Wipe command is no longer supported, however, the functionality is available using the following methods:

- Selective wipe of email is accomplished through security compliance actions, removing the device from the associated label, or retiring the device.
- For Exchange through integration with selected devices and email apps.

## Block AppTunnels



This feature is not supported on Android devices.

---

## Lost

When a user reports a lost device, you can set its status to **Lost**. Setting this status does not have a functional effect on the phone. It just flags the phone as lost for tracking purposes and to ensure that it appears in the Lost Phones screen.

### Procedure

1. Go to **Device & Users > Devices**.
2. Select the check box for the device.
3. Select **Actions > Lost** from the **Actions** menu.
4. In the displayed dialog, confirm the user and device information and enter a note.

5. Click **Lost**.

The entry for this device will appear with a status of "Lost." Use the Found action to undo this status. See "[Found](#)" below

## Found

If a user reports that a lost phone has been found, you can use the Found action to remove the Lost indicator from the entry for the phone. Setting this status does not have a functional effect on the phone.

### Procedure

1. Go to **Device & Users > Devices**.
2. Select the check box for the device.
3. Select **Actions > Found** from the **Actions** menu.
4. In the displayed dialog, confirm the user and device information and enter a note.
5. Click Found to return the entry for this device to **Active** status.

## Locate

Android devices use both cell towers and GPS to locate the device. On Android 6.0 devices, Location Permissions must be granted to the app at runtime.

Most registered phones can be located on a map using cell tower IDs. When locating a device via cell tower IDs, Mobile@Work records tower data until the next time data is synchronized between Mobile@Work and Core Core. See "Sync policies" in *Getting Started with Core* for information on changing the Sync Interval setting. Using the Force Device Check-in in the Admin Portal or in Mobile@Work will result in immediate synchronization.


### Required role

The **Privacy Control: Locate device** role is required to use this feature.

### Procedure

1. Go to **Device & Users > Devices**.
2. Select the check box for the device.
3. Click **Actions > Actions > Locate**.

4. Click the phone icon on the map to display the date and time stamp of the last known location of the phone.



## Reset device PIN

---

 This feature is not supported on Android devices.


---

## Force Device Check-In

You can use the **Force Device Check-in** feature to force the device to connect to the Core. You might use this feature if Mobile@Work has not connected for some time, or you want to override a long sync interval to download updates.

You can use this feature to troubleshoot Core operations.

---

 Both the **Force Device Check-in** option on the Admin Portal and the Mobile@Work for Android update the policies and settings related to AppConnect. The app check-in interval on the AppConnect global policy does not apply to Android devices.

---



## Procedure

1. Go to **Device & Users > Devices**.
2. Select the check box for the device.
3. Click **Actions > Force Device Check-in**.
4. The **Force Device Check-In** dialog appears.

In the dialog, confirm the user and device information and enter a note.

5. Click **Force Device Check-in**.

## Setting up background check-ins with APNs

This feature is not supported on Android devices.

## Managed iBooks

This feature is not supported on Android devices.

## Personal hotspot on/off switch

This feature is not supported on Android devices.

## Using custom APN with Android devices

Your device uses the APN or Access Point Name settings to set up a connection to the gateway between the carrier's network and the internet. You can configure a custom APN on Android devices in Work Managed Device mode and Managed Device with Work Profile (COPE) mode on Android version 9.0 or supported newer versions. You can also configure custom APNs on Samsung devices. Multiple APN's can be set up for each Android device, but only one configuration is allowed per APN.



The Android APN Settings Configuration takes precedence over other APN settings if already configured in the device manually or by the network operator.

To enter the custom setting for APN:

1. Go to **Policies & Configs > Configurations > Add New > Android > Android APN**.
2. In the New Android APN Setting dialog box, enter the values. See ["APN settings for Samsung devices" below](#) or ["APN settings for Android devices" on page 123](#).  
Settings with fields marked in red are required.
3. Click **Save**.

## APN settings for Samsung devices

Below are the settings for having an APN on Samsung devices.

TABLE 1. NEW APN SETTINGS FOR SAMSUNG DEVICES

Item	Description
Samsung	Select if this APN is directed to Samsung devices. If you want non-Samsung devices, go to <a href="#">"APN settings for Android devices" on the next page</a> .
Preferred APN	Select <b>On</b> to set this APN as preferred. Note that having more than one APN as preferred on a device will be flagged as error by the Mobile@Work client.
Name	Enter a unique name that, together with the Access Point Name, will be displayed on the device.
Description	Enter a description for the APN.
Access Point Name	Enter the name of the access point.
Authentication Type	<p>Select the type of authentication protocol from the following options:</p> <ul style="list-style-type: none"> <li>• <b>Not Set</b> - default</li> <li>• <b>None</b> - Select to not have an Authentication Type.</li> <li>• Select <b>CHAP</b> to use Challenge-Handshake Authentication Protocol (CHAP) to authenticate the user with the cellular carrier.</li> <li>• Select <b>PAP</b> to use Password Authentication Protocol (PAP) to authenticate the user with the cellular carrier.</li> <li>• Select to have Core choose <b>PAP or CHAP</b>, whichever is available first.</li> </ul>
Mobile Country Code	Enter the mobile country code.
Mobile Network Code	Enter the mobile network code.
MMS Proxy Address	Enter the MMS proxy address.
MMS Port Number	Enter the MMS port number (numeric values between 1 to 65535.)
MMS Server Address	Enter the MMS server address.
User Name	Specify the user name to use.
Password	Specify the password to use.
Confirm Password	Confirm the password to use.
Port Number	Enter the port number (numeric value between 1 to 65535.)

TABLE 1. NEW APN SETTINGS FOR SAMSUNG DEVICES (CONT.)

Item	Description
Proxy Address	Enter the proxy address.
Server Address	Enter the IP address, hostname, or URL for the server.
Access Point Type	Select the access point type from the following options: <ul style="list-style-type: none"> <li>• default</li> <li>• SUPL</li> <li>• MMS</li> <li>• Custom</li> </ul>

## APN settings for Android devices

Below are the settings for having an APN on Android devices.

TABLE 2. NEW APN SETTINGS FOR ANDROID DEVICES

Item	Description
Android 9+	Select if this APN is directed to Android devices 9.0 or supported newer versions.
Name	Enter a unique name that, together with the Access Point Name, will be displayed on the device.
Description	Enter a description for the APN.
Access Point Name	Enter the name of the access point.
Authentication Type	Select the type of authentication protocol from the following options: <ul style="list-style-type: none"> <li>• <b>Not Set</b> - default</li> <li>• <b>None</b> - Select to not have an Authentication Type.</li> <li>• Select <b>CHAP</b> to use Challenge-Handshake Authentication Protocol (CHAP) to authenticate the user with the cellular carrier.</li> <li>• Select <b>PAP</b> to use Password Authentication Protocol (PAP) to authenticate the user with the cellular carrier.</li> <li>• Select to have Core choose <b>PAP or CHAP</b>, whichever is available first.</li> </ul>
Access Point Type	Select one or more access point type(s) from the following options:

TABLE 2. NEW APN SETTINGS FOR ANDROID DEVICES (CONT.)

Item	Description
	<ul style="list-style-type: none"> <li>• Default</li> <li>• DUN</li> <li>• IMS</li> <li>• Emergency</li> <li>• MMS</li> <li>• HIPRI</li> <li>• CBS</li> <li>• MCX</li> <li>• SUPL</li> <li>• FOTA</li> <li>• IA</li> </ul>
MVNO Type	<p>Select the type of Mobile Virtual network Operator from the following options:</p> <ul style="list-style-type: none"> <li>• Not Set (default)</li> <li>• SPN</li> <li>• IMSI</li> <li>• GID</li> <li>• ICCID</li> </ul>
Bearer	<p>(Optional) Select one or more types of bearer service(s) used for data transmission from the following options:</p> <ul style="list-style-type: none"> <li>• 1xRTT</li> <li>• EHRPD</li> <li>• EVDO_B</li> <li>• HSDPA</li> <li>• CDMA</li> <li>• EVDO_O</li> </ul>

TABLE 2. NEW APN SETTINGS FOR ANDROID DEVICES (CONT.)

Item	Description
	<ul style="list-style-type: none"> <li>• GPRS</li> <li>• HSPA</li> <li>• EDGE</li> <li>• EVDO_A</li> <li>• GSM</li> <li>• HSPPAP</li> <li>• HSUPA</li> <li>• IDEN</li> <li>• IWLAN</li> <li>• LTE</li> <li>• NR</li> <li>• TD_SCDMA</li> <li>• UMTS</li> </ul>
APN Protocol	<p>Select the APN protocol required for the APN from the following options:</p> <ul style="list-style-type: none"> <li>• Not Set (default)</li> <li>• IPV4</li> <li>• IPV6</li> <li>• IPV4_OR_IPV6</li> <li>• NON_IP</li> <li>• PPP</li> <li>• UNSTRUCTURED</li> </ul>
APN Roaming Protocol	<p>Select the APN roaming protocol required for the APN from the following options:</p> <ul style="list-style-type: none"> <li>• Not Set (default)</li> <li>• IPV4</li> </ul>

TABLE 2. NEW APN SETTINGS FOR ANDROID DEVICES (CONT.)

Item	Description
	<ul style="list-style-type: none"> <li>• IPV6</li> <li>• IPV4_OR_IPV6</li> <li>• NON_IP</li> <li>• PPP</li> <li>• UNSTRUCTURED</li> </ul>
Enable / Disable APN	Select <b>On</b> to enable APN; default is off.
Carrier ID	Enter the numeric value of the carrier ID.
Mobile Country Code	Enter the mobile country code.
Mobile Network Code	Enter the mobile network code.
MMS Proxy Address	Enter the MMS proxy address.
MMS Port Number	Enter the MMS port number (numeric value between 1 to 65535.)
MMS Server Address	Enter the MMS server address.
User Name	Enter the login username.
Password	Enter the login password.
Confirm Password	Confirm the login password.
Port Number	Enter the port number (numeric value between 1 to 65535.)
Proxy Address	Enter the proxy address.

## Custom Configuration support for Zebra devices

You can deploy a custom configuration for your Zebra devices using XML configuration files from Zebra's StageNow software. The custom XML configuration file is uploaded to Core as a text file, and applied to a label. This XML configuration is then pushed to the Zebra device. To deploy the XML configuration file:

1. Go to **Policies & Configs > Configurations > Add New > Android > Android XML Configuration** to display the New Android XML Configuration page.
2. Enter the **Name** and **Description** of the configuration.
3. In the Configuration Type field, select **Zebra**.
4. Click **Browse** to navigate to and select the XML configuration file.
5. Read the warning and select the **I Agree** check box.
6. Click **Save**.



---

XML configuration files is supported on Zebra 4.4 devices. For more information on Zebra devices and Stage Now software go to: <https://www.zebra.com/us/en.html>.

---

Core supports Android remote control of Zebra devices with TeamViewer. For more information, see knowledge base article [Support for Help@work on Zebra devices for Core](#).

## Reporting on managed devices

Core provides a Web Services API that enables you to create reports for many aspects of your managed devices. For more information, see the Ivanti API documentation on the [Ivanti Product Documentation page](#). You can create reports in the following ways:

- "Exporting records to CSV" below
- Using APIs for reporting
- For details, refer to the **Feature Usage** and **Get Last Sync Time and State of ActiveSync Devices** sections in the *Core V2 API Guide*.

## Exporting records to CSV

The enhanced Export to CSV feature provides access to numerous additional device attributes that were previously unavailable. The attributes are organized into platform-specific groups to make it easy to report on the relevant attributes for the devices you're working with.

### Procedure

1. In the Admin Portal, go to **Device & Users > Devices**.
2. Use the **Advanced Search** feature or select a label to filter the devices you are interested in. All of the devices in the table will appear in the exported file.
3. Click **Export to CSV** to open the **Export CSV Spreadsheet** dialog.
4. Select the information to export. The exported fields for each selection are listed below.
5. Click **Export**. to export the DeviceSearchResult.csv file to your computer.

## Export to CSV Field Options


Below describes what is contained inside a .CSV file.

TABLE 1. EXPORT TO CSV FIELD OPTIONS

Type	Supported Variables
Registration SMS (Phones)	\$REG_LINK\$
Registration Email	
Subject (Phones)	\$SENT_NAME\$, \$USER\$, \$PHONE\$
Subject (PDAs)	\$SENT_NAME\$, \$USER\$, \$PHONE\$
Body (Phones)	\$SENT_NAME\$, \$BRAND_COMPANY_NAME\$, \$PHONE\$, \$INAPP_REG_STEPS\$, \$REG_LINK\$
Body (PDAs)	\$SENT_NAME\$, \$BRAND_COMPANY_NAME\$, \$PHONE\$, \$INAPP_REG_STEPS\$, \$REG_LINK\$
Reminder Subject (Phones)	\$SENT_NAME\$, \$USER\$, \$PHONE\$
Reminder Subject (PDAs)	\$SENT_NAME\$, \$USER\$, \$PHONE\$
Reminder Body (Phones)	\$SENT_NAME\$, \$BRAND_COMPANY_NAME\$, \$PHONE\$, \$INAPP_REG_STEPS\$, \$REG_LINK\$
Reminder Body (PDAs)	\$SENT_NAME\$, \$BRAND_COMPANY_NAME\$, \$PHONE\$, \$INAPP_REG_STEPS\$, \$REG_LINK\$
\$INAPP_REG_STEPS\$	
Server	\$SERVER_URL\$
Username	\$USER_ID\$
Password	\$PASSCODE\$, \$PASSCODE_TTL\$
Post Registration Email	
Subject (Phones)	\$BRAND_COMPANY_NAME\$, \$USER\$, \$PHONE\$
Subject (PDAs)	\$BRAND_COMPANY_NAME\$, \$USER\$, \$PHONE\$
Body (Phones)	\$BRAND_COMPANY_NAME\$, \$PHONE\$
Body (PDAs)	\$BRAND_COMPANY_NAME\$, \$PHONE\$
Include Only Basic Device Information	User ID, Device UUID, Current Country Name, Current Operator Name, Current Phone Number, Device Owner, Display Name, Email Address, Home Country Name, Language, Last Check-In, Manufacturer, Model, Passcode, Passcode Expiration Time, Platform Name, Registration Date, Status
Include all device data, including the following options below.	(Select one or more options below)



TABLE 1. EXPORT TO CSV FIELD OPTIONS (CONT.)

Type	Supported Variables
User Attributes	<p>User ID, Device UUID, account_disabled, Attribute Distinguished Name, custom1, custom2, custom3, custom4, Display Name, Email Address, First Name, Last Admin Portal Login Time, Last Name, LDAP Group Distinguished Name, LDAP User Distinguished Name, LDAP User Locale, locked_out, memberOf, Name, password_expired, Principal, sam_account_name, upn, User UUID</p> <hr/> <p> If defined in LDAP settings, custom attributes appear here also.</p> <hr/>
Common Device Attributes	<p>User ID, Device UUID, APNS Capable, Background Status, Battery Level, Block Reason, Blocked, Cellular Technology, Client Build Date, Client Id, Client Last Check-in, Client Name, Client Version, Comment, Compliant, Creation Date, Current Country Code, Current Country Name, Current Operator Name, Current Phone Number, Device Admin Enabled, Device Encrypted, Device Is Compromised, Device Locale, Device Owner, Device Space, Display Size, EAS Last Sync Time, Ethernet MAC, Home Country Code, Home Country Name, Home Operator Name, Home Phone Number, IMEI, IMSI, IP Address, Language, Last Check-In, Manufacturer, MDM Managed, Memory Capacity, Memory Free, Model, Model Name, Modified Date, Non-compliance Reason, OS Version, Passcode, Passcode Expiration Time, Platform, Platform Name, Processor Architecture, Quarantined, Quarantined Reason, Registration Date, Registration IMSI, Registration UUID, Retired, Roaming, SD Card Encrypted, Security State, Serial Number, Status, Storage Capacity, Storage Free, Terms of Service Accepted, Terms of Service Accepted Date, Wi-Fi MAC</p>
Android Attributes	<p>User ID, Device UUID, Admin Activated, Android Client Version Code, Android Enterprise Capable, Attestation, Brand, C2DM Token, Code Name, Device, Device Encryption Status, Device Roaming Flag, GCM/FCM Token Present, ICCID, Incremental, Kiosk Enabled, Manufacturer OS Version, MDM Enabled, Media Card Capacity, Media Card Free, Multi MDM, OS Build Number, OS Update Path, OS Update Status, Platform Flags, Registration Status, Samsung KNOX Version, Secure Apps Enabled, Secure Apps Encryption Enabled, Secure Apps Encryption Mode, Security Detail, Security Patch Level, Security Reason, USB Debugging</p>

## Setting the time zone of a device

This feature is applicable to: iOS 14.0 and tvOS 14.0 devices or supported newer versions. This feature is applicable for supervised devices only and does not require Location Services.

- The time zone device action is also displayed in the Device Details page of a device.
- Time zone changes made in the device will also reflect in the Core server.



This device action triggers an error if the Force automatic Date & Time restriction is enabled in iOS Restrictions configuration.

---

- Administrators can search for a time zone. See ["Advanced searching" on page 79](#).

### Procedure

1. Go to **Devices & Users > Devices**.
2. Select one or more devices.
3. Click **Actions > iOS Only > Set Time Zone** for the selected device(s).
4. Enter the timezone string in the Olson Time Zone ID format, such as Pacific / Midway.
5. Click **Set Time Zone**.

# Managing Custom Attributes

This section addresses all components relating to custom attributes.

- ["Assigning a custom attributes role" below](#)
- ["Adding custom attributes to users and/or devices" below](#)
- ["Viewing custom attributes available for users and/or devices" on the next page](#)
- ["Viewing custom attributes assigned to users" on page 133](#)
- ["Viewing custom attributes assigned to devices" on page 133](#)
- ["Editing custom attributes for users and/or devices" on page 133](#)
- ["Searching for custom attributes for users and/or devices" on page 133](#)
- ["Exporting a log of the custom attributes for users and/or devices" on page 134](#)
- ["Deleting custom attributes from users and/or devices" on page 134](#)
- ["Setting custom attribute values for device or users" on page 134](#)
- ["Pushing label attribute changes to devices and users" on page 135](#)

## Assigning a custom attributes role

An administrator the assigned role of **Manage custom attributes**, can add, view, edit, search, or remove custom user or device attributes. Custom attributes is a role for the global admin space.

### Procedure

1. Log into the Admin Portal.
2. Go to **Admin > Admins**.
3. Select an administrator to assign the custom attributes role.  
This role is for the Global admin space.
4. Select one of the following options for the selected administrator:
  - **Actions > Assign to Space > Global** if the global space has not been assigned
  - **Actions > Edit Roles** if the global space has been assigned
5. Scroll down to the **Settings and Services Management** section.
6. Click the **Manage custom attributes** option and click **Save**.

## Adding custom attributes to users and/or devices

You can add up to 300 custom attributes for users and 300 custom attributes for devices.

## Procedure

1. Log into the Admin Portal.
2. Go to **Settings > System Settings > Users & Devices > Custom Attributes**.
3. In the **Custom Device Attributes** section, click **Add+**.
4. Enter the information for the custom attribute for devices, including:

Field	Description
<b>Attribute Name</b>	Enter a name for the custom attribute.
<b>Attribute Description</b>	Enter a meaningful description for the custom attribute.
<b>Value Type</b>	Select one of three value types: boolean, integer or string. For information on Android Zero Touch custom attributes, see <a href="#">"Zero Touch enrollment with custom attributes" on page 66</a> .
<b>Variable Name</b>	This field is read-only and displays the machine-generated name of the device that is used as a substitution variable in policies and configurations. For example, the substitution variable \$USERNAME\$ is replaced with the actual device username.
<b>Actions</b>	Click <b>Save</b> . The new custom device attribute is created and displays in the table.

5. (Optional) For Apple School Manager, click **Add+** and create a new Custom Device Attribute for device carts, for example, DeviceCartName, and choose the string value type. Remember this custom attribute name as you will need it when you turn on Apple Education in Core.
6. In the **Custom User Attributes** section, click **Add+**.
7. Referring to the table above, enter the information for the custom user attributes.
8. Click **Save**. The new custom user attribute is created and displays in the table.
9. (Optional) Repeat the steps, as needed.

## Viewing custom attributes available for users and/or devices

### Procedure

1. Log into the Admin Portal.
2. Go to **Settings > System Settings > Users & Devices > Custom Attributes**.
3. View all available custom attributes for users and/or devices.

Search for the attribute, if necessary, to see all available attributes.

## Viewing custom attributes assigned to users

### Procedure

1. Log into the Admin Portal.
2. Go to **Devices & Users > Users**.
3. Locate a single user and expand the details.
4. Click the **Custom Attributes** tab.

## Viewing custom attributes assigned to devices

### Procedure

1. Log into the Admin Portal.
2. Go to **Devices & Users > Devices**.
3. Locate a single device and expand the details.
4. Click the **Custom Attributes** tab.

## Editing custom attributes for users and/or devices

### Procedure

1. Log into the Admin Portal.
2. Go to **Settings > System Settings > Users & Devices > Custom Attributes**.
3. Locate the attribute you want to edit.  
Search for the attribute, if necessary.
4. Click in the **ATTRIBUTE DESCRIPTION** field and modify the description.  
This field has a 255 characters limit.
5. Click **Save**.

## Searching for custom attributes for users and/or devices

### Procedure

1. Log into the Admin Portal.
2. Go to **Settings > System Settings > Users & Devices > Custom Attributes**.
3. Enter the search criteria for the name or description.

## Exporting a log of the custom attributes for users and/or devices

### Procedure

1. Log into the Admin Portal.
2. Go to **Logs**.
3. Scroll down the list of filters to **Custom Attributes**.
4. Click the number link of the custom attributes to display the complete list in the details pane.
5. Click **Export to CSV** to export all records to a single file.

## Deleting custom attributes from users and/or devices

You can delete an attribute if it has only been assigned to a user or a device. An attempt to delete a custom attribute assigned to a label will prompt an error message that provides a list of labels to which it has been assigned.

### Procedure

1. Log into the Admin Portal.
2. Select **Settings > System Settings > Users & Devices > Custom Attributes**.
3. Locate the attribute you want to remove.  
Search for the attribute, if necessary.
4. Click **Delete**.

## Setting custom attribute values for device or users

Setting custom attribute values for device or user requires **Edit custom device attribute values** and **Edit custom user attribute values** roles.

To set custom attributes for devices:

1. Log into Admin Portal.
2. Select **Devices & Users > Devices**.
3. Check the box next to one or more devices.
4. Click **Actions > Set Custom Attributes**.
5. Set the value for attributes and click **Save**.

You can also clear the value for an attribute by checking the **Clear Value** box and save.

To set custom attributes for users:

1. Log into Admin Portal.
2. Go to **Devices & Users > Users**.
3. Check the box next to one or more users.
4. Click **Actions > Set Custom Attributes**.
5. Set the value for attributes and click **Save**.

You can also clear the value for an attribute by checking the **Clear Value** box and save.



If you choose a single device or user when setting attribute values, the current attribute values are displayed. If you choose multiple devices or users, the current attribute values are not displayed.

## Applying custom attributes to labels

Applying custom attributes to labels, requires **Label Management** permissions.

### Procedure

1. Log into the Admin Portal.
2. Go to **Devices & Users > Labels**.
3. Click **Add Label > Filter**.
4. Locate the attribute using one of the following options:
  - Search for it in the **Field**, **Operator**, or **Value** fields.
  - Expand **Field > Custom Attributes > Device Attributes**.
  - Expand **Field > Custom Attributes > User Attributes**.

For more information about field definitions, see ["Device field definitions" on page 80](#).

5. Complete the criteria.
6. Click **Save**.

## Pushing label attribute changes to devices and users

Changing attribute values for a user or device label does not trigger an automatic update. If you have changed the attribute values for a label, by default, changes will take effect:

- **For devices:** the next time the device checks in
- **For users:** the next scheduled LDAP sync

If you want the changes to go into effect immediately, take the following action:

- **For devices:** force a device check-in. See ["Force Device Check-In" on page 120](#).
- **For users:** force an LDAP sync. See "Synchronizing with the LDAP server" in *Getting Started with Core*.



# Managing Policies

Core uses policies to regulate the behavior of the devices it manages. Each policy consists of a set of rules. You can create multiple policies for each policy type, but only one active policy of each type can be applied to a specific device.

Refer to *Getting Started with Core* for information on the most commonly used policy topics, such as:

- Default policies
- Security policies
- Privacy policies
- Lockdown policies
- Sync policies

The topics in this chapter include the following advanced topics:

- ["Working with default policies" on the next page](#)
- ["Importing and exporting policies" on page 140](#)
- ["Viewing policy status and platform support" on page 141](#)
- ["Security Policy" on page 143](#)
- ["Device log encryption on Android devices" on page 440](#)
- ["Sync policies and battery use" on page 144](#)
- ["Work Schedule policy" on page 144](#)
- ["Country changes and alerts" on page 147](#)
- ["Android devices and the Client Is Always Connected option" on page 147](#)
- ["Working with Samsung Android kiosk policies" on page 150](#)
- ["Working with Android Quick Setup policies" on page 150](#)
- ["Working with Samsung general policies" on page 154](#)
- ["Notifications of changes to the privacy policy" on page 163](#)
- ["Exporting the devices in the WatchList" on page 198](#)

## Related topics

For information on Mobile Threat Defense, including the MTD Local Actions policy, see the *Mobile Threat Defense Solution Guide for Core*.

## Working with default policies

Default policies are the policies applied to a device automatically when it is registered. Default policy values are also used as a starting point when you create a custom policy. Core provides the values for each default policy specification. It is recommended that you create your own policies. You can use the settings in the default policies as a starting point. If you do edit a default policy's values (not recommended), those new values become the starting point when you create a new custom policy.

Unlike configurations, a device can have only one policy of each type.

Core provides defaults for the following policy types:

- Security (Refer to *Getting Started with MobileIron Core* for details.)
- Privacy (Refer to *Getting Started with MobileIron Core* for details.)
- Lockdown (Refer to *Getting Started with MobileIron Core* for details.)
- Sync (Refer to *Getting Started with MobileIron Core* for details.)
- ActiveSync (See "Working with ActiveSync policies" in the *Sentry Guide for Core*.)
- AppConnect global policy (Refer to the *AppConnect Guide for Core*.)



You cannot delete default policies.

---

The default settings for each policy type are listed in the section for each type.

## Setting an alert that a device's PIN change request was skipped

You can set an alert to have the device user change the password / PIN. You can also identify devices that have prompted the device user to change the password / PIN but the device user skipped the prompt.

### Procedure

1. In your security policy, indicate the value in the Maximum Password Age field the number of days a password is valid for. See to *Getting Started with MobileIron Core* for details.
2. Create a compliance action with the desired number of days (1,2,3...up to 7) that the administrator wants to give as a grace period before taking a compliance action. For example, if the the administrator wants to have immediate effect, the value would be 7 (days.) If the administrator wants to give a grace period of 5 days, the value would be 2 (days.). See ["Adding custom attributes to users and/or devices" on page 131](#).

- Using "Advanced searching" on page 79, create a search that searches for devices that are less than 7 days (for example) of the device's password expiration date. Utilize the Android > Password/PIN Days Before Expiring field as part of your search criteria.



If the Maximum Password Age is 0, that means the PIN is set to never expire. When this happens, it means the Screenlock PIN Change Prompt – Showing value will always display as false and the Password/PIN Days Before Expiring displays as 0. Thus, the compliance policy cannot be a simple rule of just Password/PIN Days Before Expiring > Is less than or equal to > 7. It needs to be Password/PIN Days Before Expiring > Is less than or equal to > 7 and Password/PIN Days Before Expiring > Is greater than > 0 (see below).

The screenshot shows the 'Advanced Search' interface. At the top, there are two tabs: 'All' (selected) and 'Any'. Below the tabs, it says 'of the following rules are true'. There are two rule entries:

- Rule 1: 'Password/PIN Days Before Expiring' (dropdown) 'Is less than or equal to' (dropdown) '7' (text input).
- Rule 2: 'Password/PIN Days Before Expiring' (dropdown) 'Is greater than' (dropdown) '0' (text input).

Below the rules, there is a green checkmark icon and a text box containing the logical expression: `"android.priv_password_expiration_timeout" <= 7 AND "android.priv_password_expiration_timeout" > 0`. At the bottom, there is a checkbox labeled 'Exclude retired devices from search results' which is checked. A blue 'Search' button is located at the bottom right.

- Click **Save to Label**.

Apply the saved search to the appropriate labels (**Actions > Apply to Labels**).

- To view the results, go to Device Details page and in the Details tab, view the values for the following fields:

- **Screenlock PIN Change Prompt - Showing** - Indicates if device user was prompted to change the device's screen lock password / PIN and the device user skipped the prompt. Values are:
  - Unknown - If coming from an older client device, value is unknown.
  - True - Indicates the PIN is to expire in 7 days or less.
  - False - (default) Indicates the device user is not being prompted to change the password / PIN (it has not reached its 7-day expiration window.)

The value listed stays until the device user successfully changes the password /PIN on the device.

- **Password/PIN Days before expiring field** - represents the number of days before the password / PIN will expire. This numerical value is controlled by the Security policy's Maximum Password Age field value.

This field is a dynamic field, its value decreases every day by 1 until the password / PIN is renewed. At renewal, the value returns to the original number stated in the Maximum Password Age field and starts a new daily count-down.

## Importing and exporting policies

You can import and export policies from one deployment of Core to another. Topics in this section include:

- ["Exporting policies or configurations" below](#)
- ["Importing policies or configurations" on the next page](#)



This feature is supported when importing or exporting policies or configurations between Core instances that are running the same version.

---

## Exporting policies or configurations

Exporting policies and configurations help reduce errors when you have multiple instances of Core. You can export a configuration .json file for an existing policy, modify it, then import it to another policy. The export/import features allow you to do this.

### Procedure

1. Select **Policies & Configs > Policies** or **Policies & Configs > Configurations**.

All available policies are listed in the policies table.

All available configurations are listed in the configurations table.

2. Select a single policy or configuration to export.

You can sort, as necessary, to find the one you want to export.

3. Click **Export** to create an export .json file.

No application-related information is captured when exporting a policy or configuration.

4. Enter an export password and confirm it in the two password fields.

This password encrypts sensitive configuration data during export (including passwords and certificates). The same password is required to import the exported data to another Core server.

5. Check **Remember password for this session** if you want to re-use the password during a session.

A session is defined as the length of a single login. The session ends when you log out or when you have been logged out by the system.

6. Locate the .json file, open, modify, and save it, as necessary.



Review this file before reusing it as values are not verified before importing them. For instance, If a security policy .json file has a minimum password length of 2000, the imported profile will have a minimum password length of 2000 and, when pushed to devices, it will enforce all the devices to have such a big password. The encrypted hash of the sensitive data is displayed in the .json file, but the sensitive data is not displayed in plain text format in the .json file.

## Importing policies or configurations

Importing policies and configurations help reduce errors when you have multiple instances of Core. You can export a configuration .json file for an existing policy, modify it, then import it to another policy. The export/import features allow you to do this.

### Procedure

1. Select **Policies & Configs > Policies** or **Policies & Configs > Configurations**.
2. Click **Import** to locate a saved exported .json file.
3. Enter the name of the file or click **Browse** to locate it.
4. Enter the password created when the file was exported.

See ["Enter an export password and confirm it in the two password fields."](#) on the previous page in ["Exporting policies or configurations"](#) on the previous page.

5. Check **Remember password for this session** if you want to re-use the password during a session.  
A session is defined as the length of a single log-in. The session ends when you log out or when you have been logged out by the system.
6. Read the warning message and click the **I Agree** check box.
7. Click **Import** to add the new policy to the policy table.

If you import a policy that already exists, you can override the policy or cancel the import. If an exported policy has child object/s (such as app control rules and compliance actions), Core creates them during import. If the child objects already exist, they are overridden.

## Viewing policy status and platform support

For any given device, you can view the status of a policy you have applied to that device, such as Pending, Sent, or Applied. For any given policy, you can view a list of supported platforms, such as Android, iOS, and Windows.

Topics in this section include:

- "Displaying policy status" below
- "Displaying supported platforms for policies" below

## Displaying policy status

The Device Details pane on the **Device & Users > Devices** page displays status for the following tasks:

- apply lockdown policies
- apply security policies

The categories of status you will see in the **Policies** tab are:

- **Pending:** The process of applying the policy has been started.
- **Sent:** The policy has been successfully sent to the device.
- **Applied:** Core has confirmed that the verifiable settings appear to have been applied to the device. For Android devices, expand the **DETAILS** section of the Policies tab to see the verifiable results for Security and Lockdown policies.
- **Partially Applied:** One or more settings may have been rejected by the device. This can mean that the feature is not supported by the device. For Android devices, expand the **DETAILS** section of the Policies tab to see the verifiable results.

## Displaying supported platforms for policies

To clarify which policies are supported on specific platforms, "Platforms Supported" links are included in the policy dialogs. For example:

FIGURE 1 . PLATFORMS SUPPORTED LINK

The screenshot shows a 'New Security Policy' dialog box. It has a title bar with the text 'New Security Policy' and a close button. The dialog contains several fields and options:
 

- Name:** A text input field with a red dashed border.
- Status:** Two radio buttons, 'Active' (selected) and 'Inactive'.
- Priority:** Two radio buttons, 'Higher than' and 'Lower than' (selected), followed by a dropdown menu.
- Description:** A text input field.
- Password:** A section header with a small triangle icon.
- Password:** Two radio buttons, 'Mandatory' and 'Optional' (selected).
- Password Type:** Three checkboxes: 'Simple', 'Alphanumeric', and 'Don't care' (checked).
- Platforms Supported:** A link highlighted with a red box.

 In the top right corner, there are 'Save' and 'Cancel' buttons.

Each link displays a table outlining the platform support for each policy feature.

## Security Policy

Security policies specify how Core addresses several areas of mobile security. Ivanti recommends you create separate policies for each platform to avoid inconsistencies.

For more information on creating or editing a security policy, see "Security policies" in the *Getting Started with Core*.

### Proactive password security policy

When certificates are applied to the device as certificate settings, certificate enrollment settings, or via a Wi-Fi configuration, Mobile@Work proactively applies a password policy that meets the Android OS certificate installation requirements.

With the proactive password policy, Mobile@Work prompts the user to create a screen lock for their device, even if Core does not enforce a privacy policy.

### Password policy attributes

For all password policy attributes, Core only displays "Unsupported" for Mobile@Work for Android 10.6 or supported newer versions. This Android 10 or above device needs to be in Device Admin (DA) mode. If the device is still using an old version of Mobile@Work, it will not report "Unsupported."

You can view this information in Devices & Users > Device > Device tab. "Unsupported" will display for the following password policy attributes:

- Password
- Password Type
- Minimum Password Length
- Maximum Password Age

Core will not quarantine the device, the security policy will display as "Applied," and the device status will be compliant.

Core will no longer consider Unsupported for the above password policy attributes as a policy violation if the device is Android 10 or above and in Device Admin mode.

Previously if the security policy was in violation, a compliance action could be triggered if one was set. Some compliance actions could be: Send an alert, Block email or Quarantine.

## Device log encryption on Android devices

Log files can be emailed by using the **Send Log** option in Mobile@Work for Android. You can choose whether the log files are encrypted when they are provided to the email app. The choice affects the log files of the following:

- Mobile@Work for Android
- Secure Apps Manager
- AppConnect-enabled apps (including what the app logs and what the AppConnect wrapper around the app logs)

The security policy for a device contains the option for choosing whether the emailed log files are encrypted. The default setting is to **not** encrypt the files.

By default, encrypted log files can be decrypted only by Ivanti Technical Support. If you want to encrypt the log files using your own certificate, see ["Encrypting device logs with your own certificate" on page 441](#).



Regardless of the device log encryption setting, the log files never include passwords, certificate content, license information, or other sensitive authentication data.

---

By encrypting the emailed log files, you improve security because the data is readable only by Ivanti Technical Support when using the default encryption, or by your own enterprise when using your certificate for encryption. Since emailing logs for troubleshooting is a common practice, you typically choose to encrypt the logs.

#### Procedure

1. Go to **Policies & Configs > Policies**.
2. Select the security policy for the appropriate devices.
3. Click **Edit**.
4. In the **Data Encryption** section, for **Device Log Encryption**, select **On**.
5. Click **Save**.

## Sync policies and battery use

If users note significant battery impact on their devices after installing the client (Mobile@Work), consider reviewing and optimizing your sync policies.

## Work Schedule policy

This policy allows administrators to set work schedules for device users. After the scheduled work time, users are blocked from accessing specified apps and services, which include:

- Exchange Active Sync services
- AppConnect-enabled apps
- Managed apps that use Tunnel on Sentry



After the scheduled work time-period, users are unable to open any of these apps or services. In its place, users see a message indicating that access is not available. Message can vary, depending on the app or service they attempt to use. The policy starts and ends after the next scheduled sync following the specified start time and duration period.

This section contains the following procedures:

- ["Adding a Work Schedule policy" below](#)
- ["Applying a Work Schedule policy" on the next page](#)
- ["Managing a Work Schedule policy" on the next page](#)
- ["Setting up Work Schedule policy notifications" on the next page](#)

## Adding a Work Schedule policy

Use this procedure to add a policy that sets a work schedule and blocks apps and services outside of the scheduled time.



Enforcement of this policy requires Standalone Sentry 9.0.0.

---

### Procedure

1. Log into the Admin Portal.
2. Select **Policies & Configs > Policies > Add New > Work Schedule**.
3. Enter the policy name in the **Name** field.
4. Select **Active** to enable the schedule.  
Select **Inactive** to disable the policy.
5. Select **Higher than** or **Lower than** in the **Priority** option, then select the other priority.  
This option is available only if you have two or more Work Schedule policies. Use it to select the priority on one policy over the other in cases of conflicts.
6. Use the drop down to select a **Timezone**, which defines the start and end times for the policy.
7. Set up the weekly work schedule.  
The policy treats unchecked days as a time period outside of the work schedule, blocking affected apps and services for that 24-hour period.
8. Click **Save** to add the policy to the **Policies** page.

## Applying a Work Schedule policy

Core sends the policy to Sentry and Sentry enforces the policy. When you apply the policy to a label, any device associated with the selected label will receive the policy during the next sync between the Sentry and the device.

### Procedure

1. Log into the Admin Portal.
2. Select **Policies & Configs > Policies**.
3. Select the work schedule policy.
4. Select **Actions > Apply to Label**.
5. Select one or more labels and click **Apply**.

## Managing a Work Schedule policy

Use this procedure to modify or delete a work schedule policy.

### Procedure

1. Log into the Admin Portal.
2. Select **Policies & Configs > Policies**.
3. Select the work schedule policy you want to manage.
  - a. Click **Edit** to modify the work schedule, then click **Save**.
  - b. Select **Actions > Delete** to delete the policy.

## Setting up Work Schedule policy notifications

Use this procedure to modify or delete a work schedule policy.

### Procedure

1. Log into the Admin Portal.
2. Select **Logs > Event Settings**.
3. Select **Add New > Device Status Event**.
4. Complete the form and check **Work schedule policy applied**.

See the "Working with Events" section for details.
5. Click **Save**.

## Country changes and alerts

Country changes are monitored by the Mobile@Work client. Assuming that the **Sync While Roaming** option is not set to **No Sync**, each country change causes Mobile@Work to send the change to Core. If Mobile@Work can connect, then the **Event Center** generates the configured alerts, regardless of the sync interval. If connectivity is not established, then Mobile@Work generates a local alert, if configured.

## Android devices and the Client Is Always Connected option

Android devices support the Client is Always Connected option on the sync policy. Enable this option only when FCM (previously GCM) cannot be used. These situations include:

- Regions and countries in which FCM is not available.
- Select commercial and government use cases.
- Devices which do not support FCM, such as the Amazon Kindle.



Google shut down GCM service on May 29, 2019. GCM is replaced by Firebase Cloud Messaging (FCM). Core 8.0 and Mobile@Work for Android 10.2.1.0 or supported newer versions now use FCM. See [Customer Notice - GCM Batch End of life](#).

---

Core uses FCM to immediately send lock, unlock, retire, and wipe, commands to devices. You can also send notification messages to devices using FCM. With **Always Connected** option enabled, Core can send these commands and notification messages to the device at any time without using FCM.

Ivanti recommends that you enable **Always Connected** mode on a maximum of 5000 devices per Core instance. The reason is that the device generates a regular connection status check to Core when using **Always Connected** mode. This status check can impact the device as follows:

- It will cause a small increase in battery power consumption on the device.
- It will cause a small increase in bandwidth usage on the device, which sometimes is a concern when using cellular networks.

## Enabling SafetyNet attestation on Android devices

In the Core Admin Portal, you can enable Google SafetyNet attestation on Android devices to verify the integrity of the devices' software and hardware. This action provides Core with the devices' SafetyNet attestation status. With this status, you can:

- Take actions on untrusted devices.
- Deliver policies, configurations, and apps to only trusted devices.
- Assess whether the Mobile@Work app running on a device is valid, or if it is a malicious app pretending to be Mobile@Work.

This feature attests, or verifies, various information about the device. Specifically, this feature:

- certifies the manufacturer and model of devices
- provides information about Mobile@Work
- certifies the device is intact and has not been tampered with
- verifies that the Google Play version installed on the device supports SafetyNet

SafetyNet attestation works with any Android deployment, including work profiles, managed devices, and managed devices with work profiles. It also works when the device is in device admin mode.

If SafetyNet is enabled on the security policy of the device, Core initiates a SafetyNet attestation check when:

- the device has been rebooted or
- the last SafetyNet check was performed more than 24 hours ago.




Safety attestation requires that the device is running Mobile@Work 10.1 for Android or supported newer versions.

---

## SafetyNet attestation flow

When Core initiates a SafetyNet attestation check for a device, it sends a request to Mobile@Work. Mobile@Work requests Google Play Services to do the check, and Google Play Services communicates with Google Play. Google Play Services returns the results to Mobile@Work, which returns the results to Core. The following figure illustrates this flow.

FIGURE 1. SAFETYNET ATTESTATION FLOW



## Setting SafetyNet attestation

To configure Core to initiate SafetyNet attestation for devices, do the following.

## Procedure

1. Log into the Admin Portal.
2. Go to **Policies & Configs > Policies**.
3. Select a security policy and click **Edit**.  
Alternatively, create a new security policy by clicking **Add New > Security**.
4. Scroll down to the **Android** section.
5. Select **"Require Google SafetyNet Attestation"**.
6. Click **Save**.

## Related topics

"Security policies" in *Getting Started with Core*

## Basic integrity check and CTS profile verification

SafetyNet attestation provides two checks for the device:

- the basic integrity check

Verifies that the device has not been tampered with.

- the Google Compatibility Test Suite (CTS) profile verification.

Verifies that the device meets the requirements of a device that has passed Android compatibility testing.

## SafetyNet attestation information in device details

In the Admin Portal, in the **Device Details** of a device at **Devices & Users > Devices**, you can view the following fields about SafetyNet attestation. You can also use these fields in Advanced Search, including creating labels.

TABLE 1. SAFETYNET ATTESTATION INFORMATION

Status on Device	Description
SafetyNet Enabled	Indicates whether the security policy applied to the device has SafetyNet enabled.
SafetyNet Exception	Indicates an exception occurred while running SafetyNet attestation on the device.
SafetyNet Timestamp	The date and time when Core last received a SafetyNet attestation response from the device.
SafetyNet Status	The results of the last SafetyNet attestation, described in the next table.

The following table explains the values of the SafetyNet Status field in a device's Device Details.

TABLE 2. SAFETYNET STATUS VALUES

Core Status	Description
Compatible	Core received a successful response, indicating a positive response to both the basic integrity test and the CTS profile verification.
Basic	Core received a successful response to the basic integrity check, but received a failed response to the CTS profile verification.
Fail	Core received a response, but received failed responses to basic integrity and CTS profile. This status indicates that a device is uncertified.
Unsupported	This status occurs when either: <ul style="list-style-type: none"> <li>• Mobile@Work determines that SafetyNet attestation is not supported on the device.</li> <li>• The device is running a version of Mobile@Work for Android prior to Mobile@Work 10.1.</li> </ul>
Unknown	Either Mobile@Work timed out waiting for results, or Core did not receive results in the acceptable time interval.  Examples of legitimate reasons for an Unknown state are when a user is in airplane mode or has lost network connectivity. Therefore, be cautious about the actions you assign to devices that display this status.
Tampered Client	Core received a response that Mobile@Work is not valid, indicating the device has been tampered with.
Error	Either an exception occurred when calling SafetyNet or there was some other error.

## Working with Windows Update policies

This feature is not supported on Android devices.

## Working with Samsung Android kiosk policies



Samsung kiosk mode is deprecated in Android 8.1 and above. You must implement Android kiosk mode instead. See ["Setting kiosk policy for Android Managed devices" on page 542](#).

See ["Samsung Android kiosk policy" on page 534](#) for information on configuring this policy.

## Working with Android Quick Setup policies

The Android Quick Setup policy offers additional options for getting devices configured quickly:

- optional Device Administrator role for Mobile@Work
- cache registration password for Exchange and Wi-Fi configuration.

#### **Procedure**

1. Go to **Policies & Configs > Policies**.
2. Click **Add New > Android > Android Quick Setup**.

3. Use the following guidelines to complete the form:

Action	Example
Name	<p>Required. Enter a descriptive name for this policy. This is the text that will be displayed to identify this policy throughout the Admin Portal. This name must be unique within this policy type.</p> <p><b>Tip:</b> Though using the same name for different policy types is allowed (e.g., Executive), consider keeping the names unique to ensure clearer log entries.</p>
Status	<p>Select Active to turn on this policy. Select Inactive to turn off this policy.</p> <p><b>Why:</b> Use the Status feature to turn a policy on or off across all phones affected by it. The policy definition is preserved in case you want to turn it on again.</p>
Priority	<p>Specifies the priority of this custom policy relative to the other custom policies of the same type. This priority determines which policy is applied if more than one policy is associated with a specific device.</p> <p>Select "Higher than" or "Lower than", then select an existing policy from the drop-down list. For example, to give "Policy A" a higher priority than Policy B, you would select "Higher than" and "Policy B".</p> <p>Because this priority applies only to custom policies, this field is not enabled when you create the first custom policy of a given type.</p>



Action	Example
Description	Enter an explanation of the purpose of this policy.
Policy Parameters	<p>Clear the <b>Device Administrator</b> option to complete registration without applying the Device Administrator role to the Mobile@Work app. Clearing this option streamlines the registration process by eliminating the need for the device user to approve granting the Device Administrator role.</p> <p>Clearing the option also disables the following features on the device:</p> <ul style="list-style-type: none"> <li>• Password requirements</li> <li>• Device encryption</li> <li>• Device lock/unlock</li> <li>• Wipe</li> <li>• Camera lock</li> <li>• Lockdown policies</li> <li>• Samsung Knox features</li> <li>• Samsung native email configuration</li> <li>• Samsung Knox container</li> <li>• Kiosk mode</li> </ul>
Use registration password for	<p>Select the Exchange and/or Wi-Fi check box to cache the registration password on the device for use in configuring the Exchange and/or Wi-Fi settings.</p> <p>Selecting these options streamlines the configuration process if you are using LDAP for authentication as part of the registration and Exchange/Wi-Fi configuration processes.</p> <p>Note that the password is cached in memory only. Terminating the app drops the password from memory.</p>

4. Click **Save**.
5. Apply the policy to the appropriate labels (**Actions > Apply to Labels**).

## Working with Samsung general policies

Use the Samsung general policy to manage Samsung Knox license keys on Samsung devices.

**Upgrade Note:** The Samsung Knox license key for Samsung Knox activation has been moved from the Samsung (Knox) Container policy (**Policies & Configs > Configurations**) to the Samsung General policy (**Policies & Configs > Policies**). If a license key is configured in the Container policy, then a new Samsung general policy is automatically created.

### Procedure

1. Go to **Policies & Configs > Policies**.
2. Select **Add New > Android > Samsung General**.
3. Use the following guidelines to complete this form:

Item	Description
Name	Enter a unique name for the policy.
Status	Select Active to turn on this policy. Select Inactive to turn off this policy.
Priority	Select Higher than or Lower than, then select an existing policy from the drop-down list.  If you have multiple policies, use the Priority setting to select which policy gets applied. See "Prioritizing policies" in <i>Getting Started with Core</i> .
Description	Enter a description for the policy.
Knox License Key	Enter the Samsung Knox license key  <b>Important:</b> MobileIron Core does not validate the Knox license key. If the license key is invalid, AppConnect apps on the device cannot be used.
Knox Device Attestation Enabled	To enable attestation, first select the "I understand" check box, then select Knox Device Attestation Enabled.  See also: " <a href="#">Attestation support for Samsung Knox</a> " on the next page
Audit Collection Controls	Select Enable to enable event logging to the device logs on Samsung Knox devices.  See " <a href="#">Configuring audit collection controls for Samsung Knox devices</a> " on page 158.

4. Click **Save**.

## Attestation support for Samsung Knox

In a BYOD environment, it is possible for employees to use rooted Android devices with customized firmware. An enterprise can validate a device's integrity before it installs a Samsung Knox container on the device using the attestation feature.

The attestation feature requires Samsung Android devices that are attestation capable.

Attestation works by sending a challenge to the device to test its integrity. The device responds, and MobileIron Core returns its final verification. A device responds to the challenge in one of three ways:

- Correctly, resulting in attestation state of PASS
- Incorrectly, resulting in attestation state of FAIL
- No response, resulting in attestation state of UNKNOWN.

A device without attestation support does not respond. A device that supports attestation may also not respond, for example, if it has no network connectivity, or if it was compromised and sends no response.

An attestation challenge is sent to a device when the device checks-in with MobileIron Core, but not more frequently than once per hour. The attestation result determines whether a Samsung Knox container is removed, installed, or left unchanged. Additional compliance actions triggered by an attestation fail can be defined in a security policy.



*For all Samsung Android devices, whether or not they are attestation-capable, enabling attestation for the device removes a pre-existing Samsung Knox container from the device.*

---

See ["Attestation behavior on the device" on page 157](#) for more details.

## Configuring attestation on MobileIron Core

### Before you begin

- You must have a Samsung Knox License Key to enable attestation.
- Samsung Android devices that support attestation are required to take advantage of this feature.

### Recommendations

- For the best user experience, apply attestation to a new device deployment. If you enable attestation on a previously deployed device, any existing Samsung Knox container will be removed, and replaced only if the device passes the attestation challenge.
- MobileIron recommends enabling attestation in a homogeneous environment where all the devices are known to support attestation. For example, where all attestation-capable Samsung devices are corporate owned and assigned to an LDAP group.
- MobileIron strongly recommends against enabling attestation to groups of devices where attestation support is unknown or mixed.

## Configuring attestation step-by-step

Follow these steps to enable attestation, create a related security policy with optional custom compliance actions, and assign the policy to devices.

### Procedure

1. Create a label to use for attestation-related policies and devices:
  - a. Go to **Device & Users > Labels**.
  - b. Select **Add Label**. Name the label "Attestation Label", for example.
2. Enable attestation in the Samsung General Policy:
  - a. Go to **Policies & Configs > Policies**.
  - b. Select **Add New > Android > Samsung General**. The **New Samsung General Policy** dialog appears.
  - c. Enter the **Name**.
  - d. Enter the **Knox License Key**.
  - e. Read the **Caution** statement, and then select the "I understand" beneath it.
  - f. Select **Knox Device Attestation Enabled**.
  - g. Click **Save**.
3. Assign the Samsung General Policy to a label:
  - a. Select the policy.
  - b. Select **Actions > Apply to Label**.
  - c. Select the desired label (for example, Attestation Label).
  - d. Click **Apply**.
4. Optionally, create a custom compliance action to use in the attestation security policy:
  - a. Go to **Policies & Configs > Compliance Actions**.
  - b. Select **Add**.
  - c. Select the actions to take if attestation fails.
  - d. Click **Save**.

5. Create a security policy to define the consequences when attestation fails:
  - a. Go to **Policies & Configs > Policies**.
  - b. Select **Add New > Security**. The **New Security Policy** dialog appears.
  - c. Enter a name. For example, "Attestation Security Policy".
  - d. Scroll down to **Access Control** and find the **For Android devices** section.
  - e. Select the check box for "**when Samsung Knox device attestation fails**".
  - f. Choose the compliance action from the drop-down. If you created a custom compliance action for attestation, it appears as one of the options.
  - g. Click **Save**.
6. Assign the Security Policy to a label:
  - a. Select the policy.
  - b. Select **Actions > Apply to Label**.
  - c. Select the desired label (for example, Attestation Label).
  - d. Click **Apply**.
7. Assign devices to the label with the attestation policies.
  - a. Go to **Device & Users > Devices**.
  - b. Select attestation-capable Samsung device(s).
  - c. Select **Actions > Apply to Label**.
  - d. Select the label with attestation policies (for example, Attestation Label).
  - e. Click **Apply**.

WARNING: For all Android devices, Knox containers that were created before attestation is enabled are removed when the attestation policy is applied.

## Attestation behavior on the device

A label that includes a Samsung Global Policy with the attestation feature enabled is applied to a device. MobileIron Core sends attestation challenges to the device periodically. The behavior of each device type is detailed below.



*Applying attestation to non-attestation capable devices is not recommended.*

---

### Android devices that are not attestation-capable

- Attestation state is reported as UNKNOWN in Device Details in the Admin Portal.
- Attestation state will always be UNKNOWN because the device is incapable of responding to an attestation challenge.
- Any existing Samsung Knox container is removed from the device.
- No new Samsung Knox container is installed.

### **Android devices that are attestation-capable**

An attestation-capable device will respond to the attestation challenge. A challenge result can be PASS, FAIL, or UNKNOWN.

If the attestation result is PASS:

- Attestation state is reported as PASS in Device Details in the Admin Portal.
- For a new device deployment, a Samsung Knox container is installed.
- For an existing device which has a Knox container that was installed before attestation was enabled:
  - Pre-attestation Knox container is removed.
  - New Knox container is installed.
- For a device that previously passed, the Knox container remains unchanged.

If the attestation result is FAIL:

- Attestation state is reported as FAIL in Device Details in the Admin Portal.
- Samsung Knox container is removed.
- Additional compliance actions are taken based on the security policy in effect for the device, triggered by the “when Samsung Knox device attestation fails” condition.

If there is no response, the attestation result is UNKNOWN:

- Attestation state is reported as UNKNOWN in Device Details in MobileIron Core.
- If the device has previously passed attestation, it continues to function as if it has passed. The Knox container remains unchanged.
- If the device has not ever passed attestation, then:
  - Any pre-attestation Knox container is removed.

## **Configuring audit collection controls for Samsung Knox devices**

The Samsung General Policy provides audit collection control settings. These settings control what audit events are logged to the device logs on Samsung Knox devices based on an event’s severity, outcome, and audit group. These settings impact logs collected on the Samsung device: logs made by the Samsung platform, as well as logs made by Mobile@Work.

You pull these device logs to MobileIron Core, and then can access them using the System Manager.

### Procedure

1. In the Admin Portal, go to **Policies & Configs > Policies**.
2. Select the Samsung General Policy that you are using.
3. Click **Edit**.
4. For **Audit Collection Controls**, select **Enable**.
5. For **Severity Rule**, select the severity level of events you want to collect. Only audit events of the chosen severity level or higher will be collected. For example, if you select **Error**, only **Error**, **Critical**, and **Alert** audit events will be collected. The severity levels are, from most severe to least severe, are:
  - Alert
  - Critical
  - Error (the default)
  - Warning
  - Notice
6. For **Outcome Rule**, select whether you want to collect only events indicating success, events indicating failure, or all.
7. For **Audit Groups**, select the groups of events you want to collect. Select one or more of **Security**, **System**, **Network**, **Events**, or **Application**. The default is that all of the groups are selected.
8. If you selected **Events** in the **Audit Groups** field, the **Audit Events** field is enabled. The possible individual events in the **Events** group are displayed in the **Audit Events** drop-down. Select the individual events that you want to collect.
9. In the **UID** section, click the + sign to add a UID. Each UID is an integer, defined by Samsung, for enabling Samsung-specific logging.
10. Click **Save**.

### Related topics

["Pull client logs for client devices" on page 442](#)

## Working with Wear OS device policies

The Wear OS policy is used to send various Wear OS details to the server. If there isn't a policy in place or the watch app is not installed, then the Wear OS tab will not be displayed. If there is a policy and there are no watches paired to Mobile@Work, the Wear OS tab does not display. If there is a policy and the watch is paired (via Bluetooth) to the phone but the watch app is not installed on the watch, then Wear OS tab will not display. Once the policy has been implemented, the device continues to report watch details and inventory even when the device is quarantined.



Mobile@Work for Android (phone) receives Wear OS data from the Wear OS device (watch) and the Android system tends to cache this data for an unknown time frame. There is a possibility that the true value of the "Wear OS Client Installed" field in Device Details > Wear OS tab is delayed for several hours.

---

### Procedure

To create a new Wear OS policy:

1. Select **Policies & Configs > Policies**.
2. Click **Add New > Android > Wear OS policy**.
3. In the Add Wear OS Policy dialog box, use the guidelines to complete this form.
4. Click **Save**.
5. Apply the policy to a label.



TABLE 1. WEAR OS POLICY SETTINGS

Item	Description
Name	Enter a name for the Wear OS policy.
Status	<p>Select the relevant radio button to indicate whether the policy is <b>Active</b> or <b>Inactive</b>.</p> <p>You can have multiple active policies, and assign different labels to the various policies, but because only one policy is assigned to any given device, the highest-priority policy for a device is assigned.</p>
Priority	<p>Specifies the priority of this policy relative to the other custom policies of the same type. This priority determines which policy is applied if more than one policy is available.</p> <p>Select <b>Higher than</b> or <b>Lower than</b>, then select an existing policy from the dropdown list.</p> <p>For example, to give Policy A higher priority than Policy B, you would select "Higher than" and "Policy B".</p>

TABLE 1. WEAR OS POLICY SETTINGS (CONT.)



Item	Description
Description	Enter an explanation of the purpose of this policy.
Collect Wear OS device details	<ul style="list-style-type: none"> <li>• Enables (default) the collection of the device's Wear OS details to the server.</li> <li>• De-select to turn off the collection of Wear OS device details, including app inventory.</li> </ul> <hr/> <p> If the "Collect Wear OS device details" and "Collect Wear OS application inventory" fields are both selected, the collection of both device inventory and app inventory will occur.</p> <hr/>
Collect Wear OS application inventory	<ul style="list-style-type: none"> <li>• Select to enable the collection of Wear OS application inventory.</li> </ul>

TABLE 1. WEAR OS POLICY SETTINGS (CONT.)

Item	Description
	<ul style="list-style-type: none"> <li>De-select (default) to turn off the collection of Wear OS application inventory. Once this field is de-selected, old application inventory data will display in the Wear OS tab until the client explicitly sends a report to Core with no application inventory details or updated inventory details.</li> </ul> <hr/> <div>  De-selecting this field will also de-select the "Collect Wear OS device details" field. </div>

**Related topics**

["Viewing paired watch information " on page 12](#)

## Notifications of changes to the privacy policy

This feature is not available on Android devices.

## Exporting the devices in the WatchList

The number in the **WatchList** field indicates the number of devices for which the configuration is still in queue.

To export the **WatchList**:

1. In the Core Admin Portal, go to **Policies & Configs > Configurations**.
2. Click the number in the WatchList field for the configuration for which you want to export the WatchList.

The Pending Devices window appears. The window displays a list of devices for which the configuration is queued.

3. Click Export to export the list of devices.
4. The list is downloaded as .CSV file.

# Managing Compliance

Core uses compliance policies to ensure that managed devices comply with security and administrator-defined compliance policies. Actions you define in policies, such as placing a device in quarantine, take effect when a device is non-compliant.

Refer to the following technical note for more information on compliance:

<https://help.mobileiron.com/s/article-detail-page?Id=kA134000000QyFvCAK>

The topics in this chapter include the following advanced topics:

- ["Managing device compliance checks" below](#)
- ["Tiered compliance" on page 172](#)
- ["Compliance actions policy violations" on page 173](#)
- ["Viewing quarantine information" on page 179](#)
- ["Viewing configurations removed due to quarantine" on page 179](#)
- ["Custom compliance policies" on page 180](#)

## Managing device compliance checks

Devices are checked for compliance with assigned policies each time they check in with Core. In addition, Core checks all devices for compliance at regular intervals to detect out-of-compliance devices that have not checked in with Core.

Using Core, you can:

- update device compliance status at any time
- set the timing for device compliance checks
- update the device last check-in and policy update time



Core receives information regarding device compliance status and last check-in only after devices actually check-in with Core. While you can request a device check-in using the Admin Portal, many factors can affect whether a device actually checks in, such as network connectivity, or whether a device is switched on or off.

---

## Setting the device compliance check interval

By default, all devices are checked for policy compliance every 24 hours. You can change the time between compliance checks. The Compliance Check Interval setting applies to compliance checks by the server only. Out of compliance conditions include:

- Device is out of contact for the time limit you set.
- Device's root detection logic has found an issue.
- Device Admin privileges have been lost.
- Device has been decrypted.
- Device OS version is below the expected version.



It is best to run LDAP Sync and the compliance check at different times to avoid any potential Core performance problems.

---

## Procedure

1. In the Admin Portal, go to **Policies & Configs > Compliance Actions**.
2. Click **Preferences**.
3. In **Edit Compliance Preferences**, select one of the timings for **Compliance Check Interval** (2, 4, 8, 12 or 24 hours).

NOTE: Checking the compliance status of all devices every two or four hours may impact Core performance.

4. Click **Save**.

## Updating device compliance status

You can manually request a device check-in to update device compliance status for one device, several devices, or all the devices registered to Core. Updating device compliance status enables:

- administrators to update the compliance status of any device without waiting for the scheduled compliance check to run
- users to return to productive work when a compliance check is resolved, rather than wait for the next scheduled compliance check
- administrators to update the following information about a device:
  - Last check-in, updated when the device checks in
  - Policy update time

Without the ability to update device status, the device in the following example could be locked for almost 24 hours after complying with the defined security policy:

- a device status is jailbreak when Monday's daily compliance check is done (the compliance check is set for 24 hours)
- the device is blocked when this status is detected, due to the defined security policy

- the device is brought back into compliance two hours after Monday's compliance check
- the user cannot use the device until the Tuesday daily compliance check is run 22 hours from the time the device is back in compliance

### Procedure

1. In the Admin Portal, go to **Device & Users > Devices**.
2. Select one or more devices to update.
3. Select **Actions > Check Compliance**.
4. A message is displayed, letting you know that the compliance check has begun.



The compliance status of the chosen devices may not change for one to two minutes after selecting **Check Compliance**.

---

To update device compliance information for all devices:

1. In the Admin Portal, go to **Policies & Configs > Compliance Actions**.
2. Click **Check Compliance** to display a message asking if you want to update compliance status for all devices.
3. Click **Yes** to check compliance status for all devices or click **No** to cancel the action.

NOTE: The compliance status of the devices may not change for one to two minutes after selecting **Check Compliance**.

## Compliance triggers and actions

Compliance actions, configured by the administrator, may be implemented locally on the device by Mobile@Work when certain system events have occurred that cause a compliance verification check, and only when the Enforce Compliance Actions Locally on Devices check box is selected for compliance action. Compliance verification checks also occur at the device check-in interval. Out of compliance conditions include:

- Out of Contact: the device has had no communication with the Core server for greater than the time period selected which is specified in days.
- Compromised: the device is suspected to be rooted or an app has been installed for rooted devices.
- Device Admin lost: the device administration privileges have been revoked.
- Decrypted: it has been detected that the device is no longer encrypted
- OS Version: the version of the operating system on the device is below the expected version

## Server compliance conditions and actions

Server compliance actions resulting from compliance conditions are listed in the table below.

TABLE 1. SERVER COMPLIANCE CONDITIONS AND ACTIONS

Action and OS	Out of Contact	Compromised	Device Admin lost	Decrypted	OS Version
<b>Wipe</b> (Android only, when enabling Android custom ROM)	Wipe the device when it has been out of contact.	Wipe the device when the device has been compromised.	The device cannot be wiped when the administrator privileges have been removed.	Wipe the device when it has been detected that the device has been decrypted.	Wipe the device when the OS version is less than expected.
<b>Alert</b> <ul style="list-style-type: none"> <li>Android</li> <li>iOS</li> </ul>	Send an alert when the device is out of contact.  You can send alerts to device users, admins, or both users and admins, using SMS, push notifications, or email.	Send an alert when the device has been compromised.  You can send alerts to device users, admins, or both users and admins, using SMS, push notifications, or email.	Send an alert when administrator privileges have been removed.  You can send alerts to device users, admins, or both users and admins, using SMS, push notifications, or email.	Send an alert when it has been detected that the device as been decrypted.  You can send alerts to device users, admins, or both users and admins, using SMS, push notifications, or email.	Send an alert when the OS version is less than expected.  You can send alerts to device users, admins, or both users and admins, using SMS, push notifications, or email.
<b>Remove Apps</b> <ul style="list-style-type: none"> <li>Android</li> <li>iOS</li> </ul> Removal of apps is only possible if the MDM profile is sent by Core and is present on the device OR if the app	Remove managed apps when the device is out of contact.	Remove managed apps when the device has been compromised.	Managed apps cannot be removed when administrator privileges have been removed.	Remove managed apps when the device has been decrypted.	Remove managed apps when the OS version is less than expected.



Action and OS	Out of Contact	Compromised	Device Admin lost	Decrypted	OS Version
settings have the "Remove app when device is quarantined of signed-out" check box selected.					
<b>Quarantine All</b> <ul style="list-style-type: none"> <li>Android</li> <li>iOS</li> </ul> <p>All Android Enterprise apps and functionality are hidden, except Downloads, Google Play Store, and Mobile@Work. (Applicable only if the "Quarantine app when device is quarantined" check box is selected.)</p>	Remove all configurations when the device is out of contact.	Remove All configurations when the device has been compromised.	Remove All configurations when administrator privileges have been removed.	Remove All configurations when the device has been decrypted.	Remove All configurations when the OS version is less than expected.
<b>Quarantine All Except Wi-Fi</b> <ul style="list-style-type: none"> <li>Android</li> <li>iOS</li> <li>macOS</li> </ul>	Remove all configurations except for Wi-Fi.	Remove all configurations except for Wi-Fi when compromised.	Remove all configurations except for Wi-Fi when administrator privileges have been removed.	Remove all configurations except for Wi-Fi when the device has been decrypted.	Remove all configurations except for Wi-Fi when the OS version is less than expected.

Action and OS	Out of Contact	Compromised	Device Admin lost	Decrypted	OS Version
(For Android Enterprise apps, this is applicable only if the "Quarantine app when device is quarantined" check box is selected.)					
<b>Quarantine All Except Wi-Fi on Wi-Fi Only</b> <ul style="list-style-type: none"> <li>Android</li> <li>iOS</li> <li>macOS</li> </ul> (Applicable only if the "Quarantine app when device is quarantined" check box is selected.)	Remove all configurations except for Wi-Fi on Wi-Fi only devices.	Remove all configurations except for Wi-Fi on Wi-Fi only devices when compromised.	Remove all configurations except for Wi-Fi on Wi-Fi only devices when administrator privileges have been removed.	Remove all configurations except for Wi-Fi on Wi-Fi only devices when the device has been decrypted.	Remove all configurations except for Wi-Fi on Wi-Fi only devices when the OS version is less than expected.
<b>Block or retire AppConnect apps</b> <ul style="list-style-type: none"> <li>iOS</li> </ul> "Block" means blocking access to AppConnect apps.	not applicable	Block (unauthorized) or retire (unauthorize and wipe) AppConnect apps	not applicable	not applicable	not applicable


## Local compliance conditions and actions

Local compliance actions do not apply to Mobile Threat Defense functionality included with Mobile@Work clients. There are also no local compliance actions for Mobile@Work for macOS devices.

Local compliance enforcement actions resulting from compliance conditions are listed in the table below.

TABLE 2. LOCAL COMPLIANCE CONDITIONS AND ACTIONS

Situation	OS	Action
<b>When the device can communicate with Core to perform a Compliance Check</b>	<b>Alert</b> <ul style="list-style-type: none"> <li>Android</li> <li>iOS</li> </ul>	<p>Send an alert when the device is out of contact.</p> <p>Alerts are sent to device users, admins, or both users and admins, using SMS, push notifications, or email.</p>
	<b>Block AppConnect apps</b> <ul style="list-style-type: none"> <li>Android</li> <li>iOS</li> </ul>	Blocks access to AppConnect apps.
	<b>Quarantine</b> <ul style="list-style-type: none"> <li>iOS</li> </ul> <p>(Applicable only if the "Quarantine app when device is quarantined" check box is selected.)</p>	When the device is out of contact, all configurations, managed apps and iBooks content are removed. New app downloads are disallowed.
	<b>Quarantine</b> <ul style="list-style-type: none"> <li>Android</li> </ul> <p>(Applicable only if the "Quarantine app when device is quarantined" check box is selected.)</p>	When the device is out of contact, all configurations and managed apps are removed. New app downloads are disallowed.
	<b>Quarantine</b> <ul style="list-style-type: none"> <li>Android Enterprise</li> </ul>	All Android Enterprise apps and functionality are hidden, except Downloads, Google Play Store, and Mobile@Work.
<b>When the device can NOT communicate with Core to perform a Compliance check</b>	<b>Alert</b> <ul style="list-style-type: none"> <li>Android</li> <li>iOS</li> </ul>	<p>Send an alert when the device is out of contact.</p> <p>Alerts are sent to device users, admins, or both users and admins, using SMS, push notifications, or email.</p>
	<b>Block AppConnect apps</b> <ul style="list-style-type: none"> <li>Android</li> <li>iOS</li> </ul>	Blocks access to AppConnect apps.

Situation	OS	Action
	<b>Quarantine</b> <ul style="list-style-type: none"> <li>iOS</li> </ul> (Applicable only if the "Quarantine app when device is quarantined" check box is selected.)	When the device is out of contact, all configurations, managed apps and iBooks content are removed. New app downloads are disallowed.  Quarantine action requires all appConnect apps to be re-installed after the device is back in compliance.
	<b>Quarantine</b> <ul style="list-style-type: none"> <li>Android</li> </ul> (Applicable only if the "Quarantine app when device is quarantined" check box is selected.)	When the device is out of contact, all configurations and managed apps are removed. New app downloads are disallowed.
	<b>Quarantine</b> <ul style="list-style-type: none"> <li>Android Enterprise</li> </ul>	All Android Enterprise apps and functionality are hidden, except Downloads, Google settings, Google Play Store, and Mobile@Work.
	<b>Retire</b> <ul style="list-style-type: none"> <li>Android Enterprise</li> </ul>	The work profile is deleted or the managed device will be factory reset.  <hr/>  This action is not reversible.

## Tiered compliance

Administrators can apply multiple compliance actions over time on violating devices using tiered compliance. The following example describes a possible 3-tiered compliance action:

1. Send device users a warning message that their device is out of compliance, and give them time to fix the violation.
2. If the device is violating the same policy 24 hours later, Core sends users a second message and blocks the device.
3. If the device continues to violate the same policy another 24 hours later, Core sends users a third message and quarantines the device.

The increasing penalties over time allow a user that is unintentionally violating a policy to get back under compliance before punitive measures are taken, rather than immediately pulling email configurations, for example, off the device and interrupting normal work flow.



Tiers beyond the first one are only used by compliance policy rules, and are not used for security policies.


### Tiered compliance behavior

- Tiered compliance checks do not run based on delay times. For example, if the delay time is 4 hours, Core does not automatically run a tiered compliance check after 4 hours. Instead, the next compliance check will occur in one of the following cases:
  - Device Check-in
  - Compliance check from the Devices page
  - Periodic compliance check (if the device has not checked in since the last periodic compliance check)
- If a device check-in or compliance check occurs during the interval between two tiers, Core will not take action based on the next tier. Core will only take action for the next tier after the delay time between tiers has elapsed.
- Delays between tiers are cumulative. For example, if the delay for tier 2 is 4 hours, and 8 hours for tier 3, then Core takes tier 3 action after 12 hours.

## Compliance actions policy violations

You can assign compliance actions for security policy violations and for compliance policy violations. When you configure access control in either type of policy, you can select default compliance actions that are provided with Core. You can also select custom compliance actions that you create.

FIGURE 1. COMPLIANCE ACTIONS POLICY VIOLATIONS




To create the custom compliance actions, see ["Custom compliance actions" on the next page.](#)

## Default compliance actions

The following table describes the default compliance actions:

TABLE 1. DEFAULT COMPLIANCE ACTIONS TABLE

Default compliance action	Description
Send Alert	<p>Sends alert that you configured for the policy violation.</p> <p>To configure the alert, see <a href="#">"Policy violations event settings" on page 391</a>.</p>
Block Email, AppConnect Apps And Send Alert	<ul style="list-style-type: none"> <li>Sends alert that you configured for the policy violation.</li> <li>Restricts access to email via ActiveSync if you are using a Standalone Sentry for email access.</li> </ul> <hr/> <p> If you manually block, allow, or wipe a device on the <b>ActiveSync Associations</b> page, blocking email access in a compliance action has no impact. The manual action overrides Core's automatic decision-making about access to email via ActiveSync. See "Overriding and re-establishing Core management of a device" in the .</p> <hr/> <ul style="list-style-type: none"> <li>Immediately blocks access to the web sites configured to use the standard and Advanced AppTunnel feature.</li> <li>Unauthorizes AppConnect apps.</li> </ul> <p>AppConnect apps become unauthorized when the next device checkin occurs. When the device user tries to launch an AppConnect app, the Secure Apps Manager displays a small pop-up message with the reason the app is unauthorized.</p> <p>This action impacts AppConnect apps, as well as third-party AppConnect for Android apps.</p>
Customized compliance actions	<p>These actions can contain 4 tiers of actions. Tiers 2-4 are only used in compliance policies; they are not used by legacy security policies. Security policies only perform the action defined in tier 1.</p>

## Custom compliance actions

You can customize the compliance actions that you want to take for the settings on the Compliance Actions page under Policies & Configs. After you create your customized compliance actions, the actions you created appear in a drop-down list in the **Access Control** section of your security policies.

Custom compliance actions enable you to specify combinations of the following actions:

- Send alert
- Block email access and AppConnect apps (includes blocking app tunnels)

- Quarantine: block email access, block app tunnels, block AppConnect apps, and wipe AppConnect app data
- Remove configurations (i.e., profiles)
- Specify exceptions for Wi-Fi-only devices

Once you create a set of these actions, you can select that set from the drop downs in the **Access Control** section of security policies.

## Creating a compliance action

With custom compliance actions, you can create actions to better manage access control. With tiered compliance actions, you can customize them to include up to 4 levels of action to better manage compliance actions.

### Procedure

1. Log into the Admin Portal.
2. Go to **Policies & Configs > Compliance Actions**.
3. Click **Add+** to open the **Add Compliance Action** dialog box.
4. Select the appropriate fields as described in the ["Add Compliance Action table" below](#).

**NOTE:** If you have selected **Show** for the **Custom ROM Related Functions** in **Settings > System Settings > Android > Android Custom ROM**, then the wipe action is available. To enable wipe, first read and select the caution statement. You can then select **Wipe the device**. The wipe option applies to Android devices only.

5. If you want to add another set of actions, click the plus (+) button and select the fields, as necessary, to complete the second compliance action.
6. If you want to add another set of actions, click the plus (+) button and select the fields, as necessary, to complete the third compliance action.
7. Click **Save** to add the new compliance action for access control and compliance actions.
8. You can select them by going to:
  - **Policies & Configs > Policies > policy > Edit > Access Control** section (1 tier only).
  - **Policies & Configs > Compliance Policies > Add+ > Compliance Policy Rule > Compliance Actions** drop-down (1-4 tiers).

## Add Compliance Action table

The following table describes the Add Compliance Actions options:

TABLE 2. ADD COMPLIANCE ACTION FIELDS

Item	Description
Name	Enter an identifier for this set of compliance actions. Consider specifying the resulting action so that the action will be apparent when you are editing a security policy.
Enforce Compliance Actions Locally on Devices	Select this to enable the Mobile@Work app to enforce compliance actions on the device for security violations without requiring action from Core. Core also continues to enforce compliance actions.
ALERT: Send a compliance notification or alert to the user	Select if you want to trigger a message indicating that the violation has occurred. Core sends alerts to users, administrators, or both. To configure the alert, see <a href="#">"Policy violations event settings" on page 391</a> .
BLOCK ACCESS: Block email access and AppConnect apps	<p>Selecting this option has the following impact to the device:</p> <ul style="list-style-type: none"> <li>Restricts access to email via ActiveSync if you are using a Standalone Sentry for email access.</li> <li>Immediately blocks access to the web sites configured to use the standard and Advanced AppTunnel feature.</li> </ul> <p>This action blocks tunnels that AppConnect apps and iOS managed apps use.</p> <ul style="list-style-type: none"> <li>Unauthorizes AppConnect apps.</li> </ul> <p>AppConnect apps become unauthorized when the next app checkin occurs. When launched, an AppConnect app displays a message and exits. Some iOS AppConnect apps that have portions that involve only unsecured functionality can allow the user to use only those portions. AppConnect apps become unauthorized when the next device check in occurs. When the device user tries to launch an AppConnect app, the Secure Apps Manager displays a small pop-up message with the reason the app is unauthorized.</p> <p>This action impacts AppConnect apps, as well as third-party AppConnect for Android apps.</p>
QUARANTINE: Quarantine the device (Select this check box to display the other Quarantine options.)	<p>Selecting this option has the following impact to the device:</p> <ul style="list-style-type: none"> <li>Immediately blocks access to the web sites configured to use the standard and Advanced AppTunnel feature.</li> </ul> <p>This action blocks tunnels that AppConnect apps use.</p> <ul style="list-style-type: none"> <li>AppConnect apps are retired, which means they become unauthorized <i>and their secure data is deleted (wiped)</i>.</li> </ul>



Item	Description
	<p>AppConnect apps become unauthorized <i>and their data is wiped</i> when the next device checkin occurs. When the device user tries to launch an AppConnect app, the Secure Apps Manager displays a small pop-up message with the reason the app is unauthorized.</p> <p>This action impacts AppConnect apps, as well as third-party AppConnect for Android apps.</p> <ul style="list-style-type: none"> <li>For Android Enterprise devices, all Android Enterprise apps and functionality are hidden, with these exceptions: Downloads, Google Play Store, and the Mobile@Work app. (Applicable only if the "Quarantine app when device is quarantined" check box is selected.)</li> </ul> <p>NOTE: In the App Catalog, the individual setting configured on each app takes precedence over this quarantined action. If the app config setting associated with the individual (specific) app is not selected to "Quarantine app when device is quarantined", then the app will be quarantined when the user device is quarantined.</p>
<p>QUARANTINE: Remove All Configurations and SaaS Sign-on Policy</p>	<p>Select to remove the following configurations:</p> <ul style="list-style-type: none"> <li>Exchange</li> <li>VPN</li> <li>Wi-Fi</li> <li>Docs@Work</li> </ul> <p>However, because of Android limitations, this action does not remove any certificates used in Certificate Enrollment, Certificate, and Wi-Fi configurations. These certificates are installed into the device's credential storage. Only the device user can remove them by using the Clear Credential Storage command in the Android Settings app on the device. Certificates used in Exchange and VPN configurations are removed because these certificates are stored in the respective apps.</p> <p>Also, certificates installed in a Samsung Knox device's credential store <i>are</i> removed.</p>
<p>QUARANTINE: Do not remove Wi-Fi settings for Wi-Fi only devices</p>	<p>Select if you want to retain the Wi-Fi configurations devices that do not have cellular access. Select this option to ensure that you can still contact these devices.</p>

Item	Description
QUARANTINE: Do not remove Wi-Fi settings for all devices (iOS and Android only)	Select this option to retain the Wi-Fi configurations for any device, regardless of whether it has cellular access. You might select this option to preserve limited network access despite the policy violation.
QUARANTINE: Remove iBooks content, managed apps, and block new app downloads	Select this option to remove Managed Apps from the device and block access to Apps@Work when the device is not compliant. (Applicable only for Android Enterprise apps and only if the "Quarantine app when device is quarantined" check box in the App Catalog is selected.)
Retire: Retire the Work profile or factory reset the managed device	Select to trigger a local retire action on an Android Enterprise device. See the "Retiring an Android Enterprise device" section in the <a href="#">"Managing the Android Enterprise device life cycle" on page 56</a> topic for the specific actions that are taken. This selection protects work profile data from data leakage by retiring the work profile on a personal device or performing a factory reset on a managed device. These actions are performed only locally on the device by Mobile@Work. Also, the Retire action is only visible when you select the <b>Enforce Compliance Actions Locally on Devices</b> check box and it is only available in tier 1.  WARNING: This action cannot be reversed.

## When the compliance action takes effect

When you first apply a security policy, several factors affect the amount of time required to communicate the changes to targeted devices:

- sync interval
- time the device last checked in
- battery level
- number of changes already queued
- whether **Enforce Compliance Actions Locally on Devices** is selected.

Once the change reaches the device, Core checks the device for compliance. If the device is out of compliance, then the action is performed.

If the action for a security violation can be enforced locally on the device, and that option is selected in the Compliance Action dialog, then Mobile@Work initiates the compliance action without requiring contact with Core.

## Viewing quarantine information

Devices that have had configurations removed due to policy violations are considered quarantined. You can view quarantine information in the following places:

- **Device & Users > Devices** page
- **Policies & Configs > Configurations** page
- **Dashboard** page

### Procedure

1. Go to **Device & Users > Devices**.
2. Click **Advanced Search**
3. Enter the search phrase: "common.quarantined" = true
4. Click **Search**.

To view information about an individual quarantined device:

1. Go to **Device & Users > Devices**.
2. Note devices that have been highlighted and appear with a quarantine icon.
3. Expand the device details for a quarantined device.
4. Click the **Configurations** tab in the device details panel to see which configurations have been removed due to quarantine.

## Viewing configurations removed due to quarantine

You can view the configurations that Core has removed due to quarantine on the Configurations page.

1. Go to **Policies & Configs > Configurations**.
2. Click a number link in the **Quarantined** column to display a list of devices that have had the configuration removed.

## Dashboard page: Device by Compliance chart

To see how many devices are quarantined:

1. Go to **Dashboard**.
2. View the **Device by Compliance** chart. (If the chart is not visible, click **Add** to add it.)
3. To see a list of all quarantined devices, click the quarantined category.

## Custom compliance policies

Core provides security policies for 10 static definitions to mark a device as non-compliant. These policies have limited customization options, but are a quick and easy way to begin to set up compliance policy rules. The Compliance Policies feature allows administrators to define their own criteria for marking devices non-compliant. They can combine dozens of device and user fields to create non-compliant matching criteria.

Compliance policy rules use the **Advanced Search** filter criteria to define non-compliant devices. Each compliance policy rule has a filter criteria and an associated compliance action object. Access compliance policies by selecting **Policies & Configs > Compliance Policies** from the Admin Portal.

Core uses custom device and user attributes to set up compliance policy rule conditions. These settings, listed under **Devices & Users > Devices > Advanced Search > User Fields > LDAP > User Account Control** in the Admin Portal, are:

- Account Disabled
- Locked Out
- Password Expired

Compliance policies are enforced by Core during device check-in.

The work flow to set up and use compliance policies is:


- ["Assigning compliance roles" below](#)
- ["Managing compliance policy rules" on page 182](#)
- ["Managing compliance policy groups" on page 187](#)
- ["Device search fields for compliance rules" on page 191](#)

## Assigning compliance roles

The following describes how to assign compliance roles.

### Procedure

1. Log into the Admin Portal.
2. Go to **Admin > Admins**.
3. Select a user then click **Actions > Edit Roles**.
4. Select an Admin Space.
5. Scroll down the window to the **Compliance Policy Management** section.



6. Select one or more of the roles:

- **View compliance policy:** Allows the selected user to view rules, groups, lists, and configuration.
- **Modify compliance policy:** Allows the selected user to create, edit, and delete rules and groups.
- **Apply and remove compliance policy labels:** Allows the selected user to add or remove groups from labels.

7. Scroll to the **Settings and Services Management** section.

8. Select **View settings and services**.

9. Click **Save**.

## Managing compliance policy rules

Compliance policy rules are the building blocks in compliance policy groups used to manage device compliance. Administrators create compliance policy groups, add compliance policy rules to the groups, apply the groups to labels pushed to devices. Administrators can create a group with no rules or add compliance policy rules while creating the compliance policy group, if rules have already been created. They can also modify the group, including the name, description, and selected rules. This section describes:

- ["Creating compliance policy rules" below](#)
- Substitution variables for compliance policy rules
- ["Viewing and modifying compliance policy rules" on page 186](#)
- ["Deleting compliance policy rules" on page 187](#)
- ["Searching for compliance policy rules" on page 187](#)

### Creating compliance policy rules

A single rule can be in multiple compliance policy groups.

#### Procedure

1. Go to the Admin Portal.
2. Select **Policies & Configs > Compliance Policies**.
3. Click **Compliance Policy Rule** tab and then click **Add+**.
4. Add a unique name in the **Rule Name** field.
5. Select the **Status** to **Enabled** or **Disable**.
6. Enter a description of the rule if desired.
7. Build a **Condition** using **Advance Search** to define non-compliance.



It is recommended to have one Condition set to include when Mobile@Work last checked in within the last 30 days. See the TIP below.

---

8. In the **Compliance Actions** field, select from the drop-down to use on devices matching the condition.

9. (Optional) In the **Message** field, enter text for alerts generated by violations of the policy rule. When configuring the message accompanying the compliance action, custom attributes (see ["Adding custom attributes to users and/or devices" on page 131](#)) and substitution variables can be inserted into the text. To do this, copy the appropriate variable (see the ["Substitution variable" on page 185](#) table) located to the right of the Message field and paste it into the text box. Before sending the message to the device, Core will replace the substitution variable to the actual value of the custom attribute for that device. For example, \$FIRST\_NAME\$ would insert the first name of the target user into the message.
10. If you don't want the search results to include retired devices, select the **Exclude retired devices from search results** check box.
11. Click **Save**.

TIP: It is recommended to have a Compliance Policy Rule with one condition set to include when Mobile@Work last checked in with Core. This is helpful if you need assurance that Mobile@Work is running on devices (for example, for use in Mobile Threat Defense).

## Procedure

1. Go to the Admin Portal.
2. Select **Policies & Configs > Compliance Policies**.
3. Click **Compliance Policy Rule** tab and then click **Add+**.
4. Enter *ClientLastCheckIn* in the **Rule Name** field.
5. Enter **Condition > All**.
6. Go to **Field** and type in "Client Last Check-In" or select **Common Fields > Client Last Check-In**.  
The regular expression is listed below; green check mark indicates regular expression is accepted.
7. Select **within the last** in the **Value** field; enter **30 days** in the remaining two fields.
8. Keep the default setting of **Exclude retired devices from search results**.
9. In the **Compliance Actions** field, select **Send Alert** from the drop-down.
10. Click **Save**.

## **Substitution variables for compliance policy rules**



TABLE 1. SUBSTITUTION VARIABLES FOR COMPLIANCE POLICY RULES

Category	Substitution variable
Compliance policy rule customized message	<p>The substitution variables are available for use in compliance policy rules for all devices. To use in a compliance action message, copy/paste the variable into the Message field.</p> <ul style="list-style-type: none"> <li>• \$CN\$</li> <li>• \$CONFIG_UUID\$</li> <li>• \$DEVICE_CLIENT_ID\$</li> <li>• \$DEVICE_ID\$</li> <li>• \$DEVICE_IMEI\$</li> <li>• \$DEVICE_IMSI\$</li> <li>• \$DEVICE_MAC\$</li> <li>• \$DEVICE_PIVD_ACTIVATION_LINK\$</li> <li>• \$DEVICE_SN\$</li> <li>• \$DEVICE_UDID\$</li> <li>• \$DEVICE_UUID\$</li> <li>• \$DEVICE_UUID_NO_DASHES\$</li> <li>• \$DISPLAY_NAME\$</li> <li>• \$EMAIL\$</li> <li>• \$EMAIL_DOMAIN\$</li> <li>• \$EMAIL_LOCAL\$</li> <li>• \$FIRST_NAME\$</li> <li>• \$GOOGLE_AUTOGEN_PASSWORD\$</li> <li>• \$ICCID\$</li> <li>• \$LAST_NAME\$</li> <li>• \$MI_APPSTORE_URL\$</li> <li>• \$MODEL\$</li> </ul>

TABLE 1. SUBSTITUTION VARIABLES FOR COMPLIANCE POLICY RULES (CONT.)

Category	Substitution variable
	<ul style="list-style-type: none"> <li>• \$NULL\$</li> <li>• \$OU\$</li> <li>• \$PASSWORD\$</li> <li>• \$PHONE_NUMBER\$</li> <li>• \$RANDOM_16\$</li> <li>• \$RANDOM_32\$</li> <li>• \$RANDOM_64\$</li> <li>• \$REALM\$</li> <li>• \$SAM_ACCOUNT_NAME\$</li> <li>• \$TIMESTAMP_MS\$</li> <li>• \$USERID\$</li> <li>• \$USER_CUSTOM1\$</li> <li>• \$USER_CUSTOM2\$</li> <li>• \$USER_CUSTOM3\$</li> <li>• \$USER_CUSTOM4\$</li> <li>• \$USER_DN\$</li> <li>• \$USER_LOCALE\$</li> <li>• \$USER_UPN\$</li> </ul>

#### Viewing and modifying compliance policy rules

You can view or modify a compliance policy rule. Viewing a rule requires the View role and modifying a rule requires the Modify role.

You can modify a rule without removing it from an assigned group. For instance, you can change its status from Enabled to Disabled to troubleshoot it. When you modify a rule, the change is applied to all the groups that use the rule.

To view or modify a compliance policy rule:

1. Go to the Admin Portal.
2. Select **Policies & Configs > Compliance Policies > Compliance Policy Rule**.
3. Select the name of the rule you want to modify and click **Edit**.
4. Modify details, as necessary, including disabling the rule.
5. Click **Save**.

#### Deleting compliance policy rules

To delete one or more compliance policy rules:

1. Go to the Admin Portal.
2. Select **Policies & Configs > Compliance Policies > Compliance Policy Rule**.
3. Select the name of one or more rules to delete.
4. Click **Actions > Delete**.

#### Searching for compliance policy rules

To search for compliance policy rules:

1. Go to the Admin Portal.
2. Select **Policies & Configs > Compliance Policies > Compliance Policy Rule**.
3. Enter a name in the search field.
4. Use one of the following filters:
  - All
  - Enabled
  - Disabled
5. Click **Search**.

## Managing compliance policy groups

Compliance policy groups are applied to devices to manage device compliance. Administrators create compliance policy groups, add compliance policy rules to the groups, apply the group's rules to devices matching the label criteria.

Administrators can create a group with no rules or add compliance policy rules while creating the compliance policy group, if rules have already been created. They can also modify the group, including the name, description, and selected rules. This section describes:

- ["Creating compliance policy groups" on the next page](#)
- ["Modifying compliance policy groups" on the next page](#)

- ["Adding compliance policy rules to a group" below](#)
- ["Applying compliance policy groups to labels" on the next page](#)
- ["Removing compliance policy groups from labels" on the next page](#)
- ["Deleting compliance policy groups" on page 190](#)
- ["Searching for compliance policy groups" on page 190](#)

### Creating compliance policy groups

You can create a group without adding rules, which can be added later. One rule can be member of multiple groups. The following provides the steps to add one or more compliance policy rules to a compliance policy group.

#### Procedure

1. Go to the Admin Portal.
2. Select **Policies & Configs > Compliance Policies**.
3. Click **Compliance Policy Group** tab.
4. Click **Add+**. The Add Compliance Policy Group page displays.
5. Enter a unique name in the **Group Name** field.
6. Select Enabled in the **Status** field.
7. Move one or more rules from **Available Rules** to the **Selected Rules** list.
8. Click **Save**.

### Modifying compliance policy groups

The following provides the steps to modify compliance policy groups.

#### Procedure

1. Go to the Admin Portal.
2. Select **Policies & Configs > Compliance Policies > Compliance Policy Group**.
3. Select the name of the group you want to modify.
4. Modify details, as necessary, including the name, description, or to enable or disable the group.
5. Click **Save** in the **Details** section.
6. Click **Edit** in the Rules section.
7. Modify rules, as necessary, by adding or removing rules.
8. Click **Save** in the **Rules** section.

### Adding compliance policy rules to a group

One rule can be a member of multiple groups. This procedure requires that you have already created one or more rule. See ["Creating compliance policy rules" on page 182](#) for details.

To apply a compliance policy rule to a compliance policy group:

1. Go to the Admin Portal.
2. Select **Policies & Configs > Compliance Policies > Compliance Policy Group**.
3. Double-click the name of the group to which you want to add one or more rules.
4. Go to the **Rules** section and click **Edit**.
5. Move one or more rules from the **Available Rules** list to the **Selected Rules** list.
6. Click **Save** in the **Rules** section.

Applying compliance policy groups to labels

Once a group (and its underlying rules) is assigned to devices, status of the devices are evaluated based on the conditions in the rules for compliance. Compliance Policy rules are evaluated against each device in the following ways:

- During device check-in
- Periodically, during the compliance policy check interval. This is set at **Policies & Configs > Compliance Actions > Preferences**.
- When a manual Check Compliance is initiated by the administrator. This can be set at **Policies & Configs > Compliance Actions > Check Compliance** or on the **Devices** page under **Actions**.

## Procedure

1. Go to the Admin Portal.
2. Select **Policies & Configs > Compliance Policies > Compliance Policy Group**.
3. Select the name of the compliance policy group you want to apply to label.
4. Click **Actions > Apply to Labels**.
5. Select one or more of the labels.
6. Click **Apply**.

Removing compliance policy groups from labels

Once a group (and its underlying rules) is assigned to devices, status of the devices are evaluated based on the conditions in the rules for compliance. The following describes the steps to apply a compliance policy groups to one or more labels.

## Procedure

1. Go to the Admin Portal.
2. Select **Policies & Configs > Compliance Policies > Compliance Policy Group**.
3. Select the name of the compliance policy group you want to remove from a label.
4. Click **Actions > Remove from Labels**.
5. De-select one or more of the labels.
6. Click **Apply**.  
After the next device check in, these changes will apply.

Deleting compliance policy groups

The following provides the steps to delete one or more compliance policy groups.

## Procedure

1. Go to the Admin Portal.
2. Select **Policies & Configs > Compliance Policies > Compliance Policy Group**.
3. Select the name of one or more groups to delete.
4. Click **Actions > Delete**.

Searching for compliance policy groups

The following provides the steps to search for compliance policy group.

## Procedure

1. Go to the Admin Portal.
2. Select **Policies & Configs > Compliance Policies > Compliance Policy Group**.
3. Enter a name in the search field.
4. Use one of the following filters:
  - All
  - Enabled
  - Disabled
5. Click **Search**.

## Device search fields for compliance rules

This section includes the compliance action objects the compliance policy rules use for device search fields. In addition to the fields listed in the below table, any Custom Device Attributes or Custom User Attributes that were added in **Settings > System Settings > Users & Devices > Custom Attributes** will also be available for searching.

The following table lists the available objects, including:

- Common fields
- Custom fields
- Android devices
- iOS devices
- Windows devices
- User fields (including LDAP fields)

TABLE 2. DEVICE SEARCH FIELDS FOR COMPLIANCE RULES

Category	Compliance policy objects
Common	The following search fields are available for use in compliance rules for all devices: cellular_technology, client_name, client_build_date, client_version, creation_date, current_country_code, current_country_name, country_name, current_operator_name, carrier_short_name, current_phone_number, current_phone_number, data_protection_enabled, data_protection_reasons, device_admin_enabled, device_encrypted, device_is_compromised, eas_last_sync_time, ethernet_mac, home_country_code, home_country_name, home_operatory_name, home_phone_number, imei, imsi, language, last_connected_at, locale, location_last_captured_at, manufacturer, mdm_managed, mdm_tos_accepted, mdm_tos_accepted_date, model, model_name, os_version, owner, pending_device_passcode, pending_device_passcode_expiration_time, platform_name, platform, registration_date, registration_imsi, retired, roaming, security_state, status, uuid, wifi_mac_address
Android	The following search fields are available for use in compliance rules for all Android devices: admin_activated, attestation, afw_capable, brand, Client_version_code, device_roaming_flag, Knox_version, manufacturer_os_version, mdm_enabled, multi-mdm, os_build_number, os_update_status, registration_status, samsung_dm, secure_apps_encryption_enabled, secure_apps_encryption_mode, security_detail, security_patch, usb_debugging, dpm_encryption_status
iOS	The following search fields are available for use in compliance rules for all iOS devices: BluetoothMAC, BuildVersion, CarrierSettingsVersion, Current MCC, Current MNC, DataRoamingEnabled, data_protection, forceEncryptedBackup, iCloud Backup Is Enabled, iOSBackgroundStatus, iPhone PRODUCT, iPhone VERSION, IsDeviceLocatorServiceEnabled, IsDEPEnrolledDevice, IsDoNotDisturbInEffect, IsMDMLostModeEnabled, IsMDMServiceEnrolledDevice, iTunesStoreAccountIsActive, ProductName, PasscodePresent, PasscodeIsCompliantWithProfiles, PasscodeIsCompliant, Personal Hotspot Enabled, SerialNumber, Supervised, SIM MCC, SIM MNC, Subscriber Carrier Network, Voice Roaming Enabled, osUpdateStatus,



TABLE 2. DEVICE SEARCH FIELDS FOR COMPLIANCE RULES (CONT.)

Category	Compliance policy objects
Windows	<p>The following search fields are available for use in compliance rules for all Windows devices:</p> <p>dm_client_version, wp_firmware_version, wp_hardware_version, wp_os_edition, health_data_issued, health_data_aik_present, health_data_dep_policy, health_data_bit_locker_status, health_data_boot_manager_rev_list_version, health_data_code_integrity_rev_list_version, health_data_secure_boot_enabled, health_data_boot_debugging_enabled, health_data_os_kernel_debugging_enabled, health_data_code_integrity_enabled, health_data_test_signing_enabled, health_data_safe_mode, health_data_win_pe, health_data_elam_driver_loaded, health_data_vsm_enabled, health_data_pcr0, health_data_sbcp_hash,</p>
User	<p>The following search fields are available for use in compliance rules user-related fields, including LDAP:</p> <p>email_address, user_id, attr_dn, dn, name, locale, principal, upn, account-disabled, locked_out, password_expired, custom1, custom2, custom3, custom4, &lt;dynamically created custom user-attribute field name #1&gt;, &lt;dynamically created custom user-attribute field name #2&gt;, &lt;dynamically created custom user-attribute field name #3&gt;, &lt;dynamically created custom user-attribute field name #4&gt;, &lt;dynamically created user-attribute field names&gt;</p>

# Managing Device Settings with Configurations

This section addresses the automation of major settings via configurations that can then be applied to a large inventory of different devices.

- ["Management of device settings with configurations" below](#)
- ["Configurations page " on the next page](#)
- ["Default configurations" on the next page](#)
- ["Displaying configurations status" on page 196](#)
- ["Adding new configurations" on page 196](#)
- ["Editing configurations" on page 197](#)
- ["Deleting configurations" on page 197](#)
- ["Exporting configurations" on page 197](#)
- ["Importing configurations" on page 198](#)
- ["Applying configurations to labels" on page 198](#)
- ["Exporting the devices in the WatchList" on page 198](#)
- ["Impact of changing LDAP server variables" on page 199](#)

## Management of device settings with configurations

Configuring major settings across a large inventory of different devices can mean a major daily time investment for IT personnel. You can automate this process by specifying and distributing configurations, previously called app settings. A configuration is a group of settings to be applied to devices.

The following table summarizes the device settings managed by Core. Configurations are found on the **Policies & Configs > Configurations** page.

TABLE 1. DEVICE SETTINGS

Category	Configuration Type
Infrastructure	<ul style="list-style-type: none"><li>• Exchange</li><li>• Email</li><li>• Wi-Fi</li><li>• VPN</li></ul>

TABLE 1. DEVICE SETTINGS (CONT.)

Category	Configuration Type
	<ul style="list-style-type: none"> <li>• Certificates</li> <li>• Certificate Enrollment</li> </ul>
MobileIron AppConnect	<ul style="list-style-type: none"> <li>• App Configuration</li> <li>• Container Policy</li> </ul>
MobileIron Features	<ul style="list-style-type: none"> <li>• Docs@Work</li> <li>• Web@Work</li> </ul>

## Configurations page

A configuration (previously called app settings) is a group of settings that are applied to devices. Go to the **Policies & Configs > Configurations** page to create and manage configurations. It displays the following information for each configuration.

TABLE 1. CONFIGURATIONS PAGE OPTIONS

Field	Description
Name	Indicates a name for this group of settings.
Configuration Type	Indicates the kind of configuration.
Bundle/Package ID	If this configuration is links to a App Catalog entry, the Bundle/Package ID will display here.
Description	Displays additional information about this group of settings.
# Phones	Indicates the number of phones to which this group of settings has been applied. Click the link to display a list of the devices.
Labels	Lists the labels to which this group of settings has been applied.
WatchList	Displays the number of devices for which this group of settings is queued. Click the link to display a list of the devices.
Quarantined	Displays the number of devices that have had configurations removed due to policy violations. Click the link to display a list of the devices. See <a href="#">"Creating a compliance action" on page 175</a> for information on quarantining devices.

Required role: Administrator must have the **View configuration** role to access the Configurations page.

## Default configurations

These configurations do not apply to Android devices.

## Displaying configurations status

To see the status of configurations for each device:

1. Go to **Device & Users > Devices**
2. Select a device, and click the caret to open the device details
3. Click the **Configurations** tab.

The statuses you will see are:

- **Pending:** The process of applying the settings has been started.
- **Sent:** The settings have been successfully sent to the device.
- **Applied:** Core has confirmed that the verifiable settings appear to have been applied to the device. Use the **View Details** button to see the verifiable results.
- **Partially Applied:** One or more settings may have been rejected by the device. This can mean that the feature is not supported by the device. Use the **View Details** button to see the verifiable results.
- **Update Pending:** The administrator has edited the setting in the Admin Portal. The process of applying the updated setting has begun.

Click the **View Details** button to see information on each configuration.

## Adding new configurations



Add new configurations through integration with selected devices and email apps plus Sentry and ActiveSync.

---

To add new configurations:

1. Go to **Policies & Configs > Configurations**.
2. Click **Add New**.
3. Select the type of configuration you want to create.
4. Complete the displayed form for the configuration.
5. Click **Save**.
6. To push the configuration to devices, apply it to the appropriate labels. Select **Actions > Apply to Label**.

## Editing configurations

---



Add new configurations through integration with selected devices and email apps plus Sentry and ActiveSync.

---

To edit configurations:

1. In the Configurations screen, select the configuration you want to edit.
2. Click **Edit**.
3. Make your changes.
4. Click **Save**.

A pop-up displays.

5. Click **Yes** to continue.

The configuration will be re-pushed to matching devices even you made no changes. However, if the only change made is to the description, the configuration will **not** be re-pushed to the devices.

## Deleting configurations

---



Add new configurations for Android devices through integration with selected devices and email apps plus Sentry and ActiveSync.

---

To delete configurations:

1. In the Configurations screen, select the settings you want to delete.
2. Click **Delete**.

## Exporting configurations

Export and importing setting configurations helps reduce errors when you have multiple instances of Core. You can export a configuration .json file for an existing setting, modify it, then import it to another configuration.

To export a configuration:

1. Select **Policies & Configs > Configurations**.

All available configurations are listed in the table.

2. Select a single configuration to export.

You can sort, as necessary, to find the configuration you want to export.

3. Click **Export** to create an export configuration .json file.

No application-related information is captured when exporting a configuration.

4. Locate the .json file, open, modify, and save it, as necessary.



Review this file before reusing it as values are not verified before importing them.

---

## Importing configurations

To import a configuration:

1. Log into Core.
2. Select **Policies & Configs > Configurations**.
3. Click **Import** to locate a saved exported configuration .json file.
4. Enter the name of the file or click **Browse** to locate it.
5. Read the warning message and click in the **I Agree** check box.
6. Click **Import** to add the new configuration to the configuration table.

If you import a configuration that already exists, you can override the file or cancel the import.

## Applying configurations to labels

Use labels to apply configurations to devices. Refer to the “Using labels to establish groups” section in the *Getting Started with Core* for more information.

To apply a configuration to a label:

1. Select **Policies & Configs > Configurations** to display the configurations table with all available settings configurations.
2. Select the check box next to a configuration you want to apply to a label.  
Search for a configuration by entering the configuration name or description in the search box.
3. Click **Actions > Apply To Label**.  
Select the label.
4. You can search by label name or description to help find the label.
5. Click **Apply**.

## Exporting the devices in the WatchList

The number in the **WatchList** field indicates the number of devices for which the configuration is still in queue.

To export the **WatchList**:

1. In the Core Admin Portal, go to **Policies & Configs > Configurations**.
2. Click the number in the WatchList field for the configuration for which you want to export the WatchList.

The Pending Devices window appears. The window displays a list of devices for which the configuration is queued.

3. Click Export to export the list of devices.
4. The list is downloaded as .CSV file.

## Impact of changing LDAP server variables

A change to a LDAP server variable (such as \$EMAIL\$, \$FIRST\_NAME\$, \$LAST\_NAME\$, \$DISPLAY\_NAME\$, \$USER\_UPN\$, \$USER\_CUSTOM1, \$USER\_CUSTOM2, \$USER\_CUSTOM3\$, or \$USER\_CUSTOM4\$) now causes a setting that uses the variable to be re-pushed to the device. The impacted settings are:

- Exchange setting
- Email setting
- Wi-Fi setting
- VPN setting
- CalDAV setting
- CardDAV setting
- Subscribed calendar setting
- AppConnect app configuration
- Docs@Work setting

# Configuring Email

This section addresses email account configuration, enabling S/MIME encryption and synchronizing account data.

- ["Exchange settings" below](#)
- ["Configuring POP and IMAP email settings \(for iOS and macOS\)" on page 207](#)
- ["Synchronizing Google account data" on page 207](#)
- ["Setting up Gmail with Android Enterprise" on page 214](#)

## Exchange settings

To specify the settings for the ActiveSync server that devices use, go to **Policies & Configs > Configurations**, then click **Add New > Exchange**. The ActiveSync server can be a Microsoft Exchange server, an IBM® Lotus® Notes Traveler server, Microsoft Office 365, or another server.

The Exchange configuration works:

- Through Sentry and ActiveSync
- With Samsung Knox devices running the Samsung native email app and the Android versions listed in the Mobile@Work for Android Release Notes.

Note that AppConnect-enabled Email+ for iOS and Email+ for Android do not use an Exchange setting. Instead, you configure the email clients using an AppConnect app configuration.

Android Enterprise email clients are configured using AppConnect app configurations. See ["Setting up Gmail with Android Enterprise" on page 214](#).

The following table describes the Exchange settings you can specify.

TABLE 1. EXCHANGE SETTINGS

Section	Field Name	Description
<i>General</i>	Name	Enter brief text that identifies this group of Exchange settings.
	Description	Enter additional text that clarifies the purpose of this group of Exchange settings.
	Server Address	Enter the address of the ActiveSync server.  If you are using Standalone Sentry, do the following: <ul style="list-style-type: none"><li>• Enter the Standalone Sentry's address.</li></ul>



TABLE 1. EXCHANGE SETTINGS (CONT.)

Section	Field Name	Description
		<ul style="list-style-type: none"> <li>If you are using Lotus Domino server 8.5.3.1 Upgrade Pack 1 for your ActiveSync server, set the server address to <b>&lt;Standalone Sentry's fully qualified domain name&gt;/traveler</b>.</li> <li>If you are using a Lotus Domino server earlier than 8.5.3.1 Upgrade Pack 1, set the address to <b>&lt;Standalone Sentry fully qualified domain name&gt;/servlet/traveler</b>.</li> <li>If you are using load balancers, contact Ivanti. Professional Services.</li> </ul> <p>When using Integrated Sentry, set the server address to Microsoft Exchange Server's address.</p> <hr/> <p>When using Sentry, you can do preliminary verification of your Exchange configuration choices for the ActiveSync User Name, ActiveSync User Email, and ActiveSync Password fields. To do so, first set the server address to the ActiveSync server. After you have verified that users can access their email using this Exchange configuration, change the server address to the appropriate Sentry address.</p> <hr/> <p>For more information about configuring Sentry, see the Sentry Guide for Core.</p>
	Use SSL	<p>Select to use secure connections.</p> <p>SSL is always used, regardless of whether this setting is selected.</p>
	Use alternate device handling	Replaces the <b>Use Standalone Sentry</b> option. Use this option only under the direction of Ivanti Technical Support.
	Domain	Specify the domain configured for the server.

TABLE 1. EXCHANGE SETTINGS (CONT.)

Section	Field Name	Description
	Google Apps Password	<p>This check box only appears if you have configured a Google account with Core.</p> <p>When linking to Google Apps, select this option to use the Google Apps password to log in to the Google account you have configured to work with Core. This password allows device users to access their Email, Contacts, and Calendar data on their managed devices.</p> <p>When selected, Core grays out the <b>ActiveSync User Name</b> and <b>ActiveSync User Password</b>.</p> <p>This check box only appears if you have configured a Google account with Core, as described in <a href="#">"Synchronizing Google account data" on page 207</a>.</p>
	ActiveSync User Name	<p>Specify the variable for the user name to be used with this Exchange configuration. You can specify any or all of the following variables \$EMAIL\$, \$USERID\$, \$PASSWORD\$. You can also specify custom formats, such as \$USERID\$_US. Custom attribute variable substitutions are supported.</p> <p>Typically, you use \$USERID\$ if your ActiveSync server is a Microsoft Exchange Server, and you use \$EMAIL\$ if your ActiveSync server is an IBM Lotus Notes Traveler server. You cannot use \$NULL\$ for this field.</p>
	ActiveSync User Email	<p>Specify the variable for the email address to be used with this Exchange configuration. You can specify any or all of the following variables \$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, CUSTOM_USER_Attributename\$, or \$NULL\$. You can also specify custom formats, such as \$USERID\$_US. Custom attribute variable substitutions are supported.</p> <p>Typically, you use \$EMAIL\$ in this field; you cannot use \$NULL\$.</p>

TABLE 1. EXCHANGE SETTINGS (CONT.)



Section	Field Name	Description
	ActiveSync User Password	<p>Specify the variable for the password to be used with this Exchange configuration. You can specify any or all of the following variables: \$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, CUSTOM_USER_Attributename\$, or \$NULL\$. You can also specify custom formats, such as \$USERID\$_US. Custom attribute variable substitutions are supported.</p> <p>Enter additional variables or text in the text box adjacent to the <b>Password</b> field. Entries in this text box are kept hidden and will not be visible to any Core administrator.</p> <hr/> <p> All variables and text up to the last valid variable will be visible. Anything after the last valid variable will not be visible. The valid variable may appear in either of the password fields. Valid variables are variables in the drop-down list.</p> <hr/>
	Identity Certificate	<p>Select the Certificate Enrollment entry you created for supporting Exchange ActiveSync, if you are implementing certificate-based authentication.</p> <hr/> <p> When setting up email for devices with multi-user sign-in, the exchange profile must always use a user-based certificate. The user-based certificate will ensure secure access to email for all users. Using a device-based certificate can result in one user sending or receiving emails for another user. When configuring the user-based certificate, select the <b>Proxy enabled</b> and <b>Store certificate keys on MobileIron Core</b> options. This allows the user certificate and private key to be delivered each time they log in on the shared device.</p> <hr/>

TABLE 1. EXCHANGE SETTINGS (CONT.)

Section	Field Name	Description
	Password is also required	Specify whether to prompt device users for a password when certificate authentication is implemented. The password prompt is turned off by default. Once you specify an Identify Certificate, this option is enabled. Select the option if you want to retain the password prompt.
	Items to Synchronize (Android, Windows)	This feature is not supported.
	Items to Synchronize (iOS)	This feature is not supported on Android devices.
	Past Days of Email to Sync	Specify the maximum amount of email to synchronize each time by selecting an option from the drop-down list.  This setting works only with these email apps: <ul style="list-style-type: none"> <li>• Samsung Knox devices' native email app</li> <li>• Email+</li> </ul>
	Move/Forward Messages to Other Email Accounts	This feature is not supported for Android devices.
<b>S/MIME</b>	Enable for Android and iOS 9.3.3 (or earlier)	Select to enable S/MIME signing and encryption on devices running Android or iOS 9.3.3 or earlier.
<b>S/MIME Signing</b>		
	S/MIME Signing: Enable	This feature is not supported for Android devices.
	S/MIME Signing identity	This feature is not supported for Android devices.
	Signing Identity: User Overrideable	This feature is not supported for Android devices.
	S/MIME Signing: User Overrideable	This feature is not supported for Android devices.
<b>S/MIME Encryption</b>		
	Encryption by Default	This feature is not supported for Android devices.

TABLE 1. EXCHANGE SETTINGS (CONT.)

Section	Field Name	Description
	Encryption Identity	This feature is not supported for Android devices.
	Encryption Identity: User Overrideable	This feature is not supported for Android devices.
	Encryption by Default: User Overrideable	This feature is not supported for Android devices.
	Per-Message Encryption Switch	This feature is not supported for Android devices.
<i>ActiveSync</i>		Limited support for Android.
	Sync during	
	Peak Time	Select the preferred synchronization approach for peak times. This feature is not supported for Android devices.
	Off-peak Time	Select the preferred synchronization approach for off-peak times. This feature is not supported for Android devices.
	Use above settings when roaming	Specify whether to apply synchronization preferences while roaming.
	Send/receive when send	Specify whether queued messages should be sent and received whenever the user sends a message.
	Peak Time	
	Peak Days	Specify which days should be considered peak days.
	Start Time	Specify the beginning of the peak period for all peak days.
	End Time	Specify the end of the peak period for all peak days.
<i>iOS 5 and Later Settings</i>		These features are not supported for Android devices.

TABLE 1. EXCHANGE SETTINGS (CONT.)


Section	Field Name	Description
<i>Android</i>		
	Exchange App Priority	<p>Drag and drop email configurations to specify which are allowed. Change the order of selected configurations to specify priority.</p> <p>If there are no email apps specified in the <b>Selected</b> column, then Mobile@Work uses the following provisioning priority:</p> <ol style="list-style-type: none"> <li>1. Android Email+ (AppConnect-enabled)</li> <li>2. Android Email+</li> <li>3. Native email app</li> </ol>
<i>General</i>		
	Accept all SSL certificates: Enable	<p>Enables device users to set Android devices to accept all SSL certificates. This setting applies to Android Email+ and Samsung Knox email and is intended for use when the Sentry uses self-signed certificates.</p> <hr/> <p> Use caution when enabling this setting, as device users might unknowingly expose the device to attack.</p> <hr/>
	Copy/Paste: Enable	Prevents use of the copy and paste commands in Android Email+.
	Allow access to secure info from outside container	<p>Specify whether to publish contacts and calendar items to non-secure email clients running on the same device.</p> <p>For Secure Android Email+, you can allow access to both contacts and calendar.</p>
	NitroDesk TouchDown	Enter the license key.
<i>Samsung SAFE (Knox)</i>	Supported on all Samsung Knox devices	

TABLE 1. EXCHANGE SETTINGS (CONT.)

Section	Field Name	Description
	HTML Email : Allow	Select this option to allow viewing of HTML email. This option is not enabled by default, which prevents rendering of HTML-based email.
	SmartCard Authentication: Enable	This feature is not supported.
	<i>Windows 10 Desktop</i>	This feature is not supported for Android devices.

## Multiple Exchange Support for Android

Multiple Exchange mailboxes are supported for devices running Android versions no earlier than 4.0 or Samsung Knox 4.0 devices, using either Android Email+ or Samsung Native Email client apps. For Samsung Native Email client, Certificate Enrollment is not supported as the authentication method with multiple mailboxes.

The Core administrator can configure and apply up to two Exchange settings for each device. Exchange settings are found in the Admin Portal under **Policies & Configs > Configurations**. When it receives the configuration, the device must be running Mobile@Work version 6.0 or supported newer versions.

On the device, both mailboxes appear in a single email app. The email app is determined by 1) the email app's priority as specified in the Exchange Setting's **Exchange App Priority**, and 2) the email app's availability on the device. For example, if both Samsung Native Email and Email+ are available on the device, the app with the highest priority is used.



Mobile@Work's **Options > Email Status** is not supported for multiple Exchange accounts.

## Configuring POP and IMAP email settings (for iOS and macOS)

This feature is not supported for Android devices.

## Synchronizing Google account data

You can synchronize email, contacts, calendar, and tasks with mail apps on devices managed by Core. To enable synchronization, you need to authorize apps to use Google APIs for communication between servers without accessing user information. This requires a service account that makes API calls on behalf of an app, as well as credentials that authenticate the identity of the app.

You create these credentials in the Google Developers Console, and then upload the credentials both to the Google Admin Console and Core. You can then configure an Exchange setting to synchronize Google email data (including email, contacts, calendar, and tasks) with managed devices. You can alternatively choose to synchronize only some email data, such as calendar and contacts only, or email alone.

The Exchange setting also allows you to control the Google Apps password through Core.

### **Main steps**

Synchronizing Google Apps data involves the following main steps:

- ["Using OAuth to enable access to Google APIs" below](#)
- ["Uploading OAuth credentials to the Google Admin Console" on the next page](#)
- ["Linking Google Apps credentials with Core" on the next page](#)
- ["Setting up your Exchange setting for access to Google Apps data" on page 211](#)
- ["Renewing the Google Apps password for a given set of users" on page 213 \(optional\)](#)

### **Before you begin**

You need a Google administrator account.

Review the following Google documentation:

- [https://developers.google.com/admin-sdk/?hl=en\\_US](https://developers.google.com/admin-sdk/?hl=en_US)
- <https://support.google.com/googleapi/answer/6158857?hl=en>
- <https://support.google.com/googleapi/answer/6158849?hl=en#serviceaccounts>

## **Using OAuth to enable access to Google APIs**

You must login to the Google Developers Console to enable access to Google APIs from clients using OAuth.

For detailed information, see the Google documentation here:

- <https://developers.google.com/identity/protocols/OAuth2>
- <https://developers.google.com/identity/protocols/OAuth2ServiceAccount>

Following are the main steps of this procedure.

### **Main steps**

1. Login to <https://console.developers.google.com>
2. In the Google Developers Console, create a new project.
3. Enable the Admin SDK and/or APIs.
4. Create credentials for the OAuth 2.0 client.
5. Create a consent form.



6. Enter the relevant information, as shown in the following table.

Item	Description
Application type	Select web application.
Name	Enter the name of the iOS app.
Authorized JavaScript origins	Enter JavaScript origins here or redirect URIs below (or both). Cannot contain a wildcard (http://*.example.com) or a path (http://example.com/subdir).
Authorized redirect URIs	Must have a protocol. Cannot contain URL fragments or relative paths. Cannot be a public IP address.

7. Download the credentials in the form of a JSON file for the web client.

## Uploading OAuth credentials to the Google Admin Console

You must now upload to the Google Admin Console the JSON file you created in "[Using OAuth to enable access to Google APIs](#)" on the previous page. The JSON file contains the credentials you created for client access.

For detailed information, see the Google documentation here:

- <https://developers.google.com/identity/protocols/OAuth2>
- <https://developers.google.com/identity/protocols/OAuth2ServiceAccount>

Following are the main steps of this procedure.

### Main steps

1. Go to <https://admin.google.com> and login with your administrator ID.
2. Enable API access.
3. Enter the client name and API scope.
4. Authorize the JSON file so that clients may access it.

## Linking Google Apps credentials with Core

You must upload the JSON credentials file you downloaded from the Google Developers console to link your Google credentials with Core. For more information, see "[Using OAuth to enable access to Google APIs](#)" on the previous page.

### Procedure

1. In the Admin Portal, go to **Services > Google**.
2. In the **Google Admin Username** field, enter your Google administrator email address.
3. Next to the **JSON File** field, click **Browse**.

**Google Apps API**

1 Download the Public and Private key pair as a JSON file from Google Developers Console.

2 Use your Google Apps domain admin account to enable API access and allow OAuth for your domain.

3 Enter your Google Apps admin username below, and upload the JSON file you downloaded in Step 1

**Google Admin Username:**

**JSON File:**  
 **Browse...**

**Save**

4. Select the JSON file you downloaded from the Google Developers Console.
  - a. Click **Save**.

The results are displayed in the lower left of the page.

5. Go to **Settings > Preferences**.
6. Scroll down to the **Google Apps API** section.
7. Click **Password Settings**.
8. Configure password settings as follows:
  - Password length must be: Enter the minimum password length.
  - Require a password change every: Check the box and enter the number of days after which device users must change their password.



Password expiration and password length values should match whatever is configured in Google. For example, if you configured a 90 day expiration period in Google with a password length of 8 to 90, then you would configure the same expiration and password length values in Core.

9. Click **Save**.

10. Optionally, view the Google Apps account status by clicking **View Account**.

## Setting up your Exchange setting for access to Google Apps data

Create an Exchange setting to connect Core to Google servers, such that device users will be able to access their email, calendar, and contacts. Apply the Exchange setting to the relevant labels, such that Core pushes the new setting to the correct devices. The Exchange setting must include the Google Apps Password flag, which tells Core to generate a Google Apps password and send it to Google servers.

When sending an event to a device, Core checks whether the Google Apps Password flag is toggled on or off. If a Google Apps password is required, but the password has not yet been generated and sent to Google, then Core sends the password to Google first before sending the Exchange setting to the device.

If Core cannot find a user on Google, Core logs an error, and does not push the Exchange setting again.

Under some circumstances, you may need to renew the Google Apps password. For more information, see ["Renewing the Google Apps password for a given set of users" on page 213](#).


Note The Following:

- If you intend to distribute an AppConnect email app to devices, such as Email+ for iOS, you must add the key email\_password with a value of \$GOOGLE\_AUTOGEN\_PASSWORD\$ to the AppConnect app configuration for the email app. For more information, see "Configuring an AppConnect app configuration" in the *AppConnect Guide for Core*.
- Set the Exchange Username field to \$EMAIL\$ when using \$GOOGLE\_AUTOGEN\_PASSWORD\$ in the Password field and when using Android Enterprise managed configurations or AppConnect KVPs.

### Procedure

1. In the Admin Portal go to **Policies & Configs > Configurations**.
2. Click **Add New > Exchange**.

3. In the Exchange Setting dialog box, enter the following:

Item	Description
<i>General</i>	
Name	Enter brief text that identifies this group of Exchange settings.
Description	Enter additional text that clarifies the purpose of this group of Exchange settings.
Server Address	<p>Enter the address of the mail server, such as <b>m.google.com</b>.</p> <p>If you are using Standalone Sentry, do the following:</p> <ul style="list-style-type: none"><li>• Enter the address of Standalone Sentry.</li><li>• Go to <b>Services &gt; Sentry</b> and edit your Standalone Sentry. In the <b>ActiveSync Server</b> field, enter <b>m.google.com</b>.</li><li>• If you are using load balancers, contact Ivanti Professional Services.</li></ul> <p>For more information about configuring Sentry, see the <i>Sentry Guide for Core</i>.</p>
Use SSL	<p>Select to use secure connections.</p> <hr/> <p> You must use SSL to link to Google Apps.</p> <hr/> <p>SSL is always used, regardless of whether this setting is selected.</p>

Item	Description
Google Apps Password	<p>When linking to Google Apps, select this option to use the Google Apps password to log in to the Google account you have configured to work with Core. This password allows device users to access their mail, contacts, and calendar data on their managed devices.</p> <p>When selected, Core grays out the <b>ActiveSync User Name</b> and <b>ActiveSync User Password</b>.</p> <p>This check box only appears if you have configured a Google account with Core, as described in <a href="#">"Synchronizing Google account data" on page 207</a>.</p>
ActiveSync User Email	<p>Specify the variable for the email address to be used with this Exchange configuration. You can specify any or all of the following variables \$EMAIL\$, \$USERID\$, \$PASSWORD\$. You can also specify custom formats, such as \$USERID\$_US. Custom attribute variable substitutions are supported.</p> <p>Typically, you use \$EMAIL\$ in this field.</p>
Items to Synchronize	Select the items you want to synchronize with Google Apps: Contacts, Calendar, Email, Tasks.

4. Click **Save**.
5. Check the box next to the Exchange setting you created, and select **Actions > Apply To Label**.
6. Select the labels to which you want to apply the Exchange setting and click **Apply**.

## Renewing the Google Apps password for a given set of users

If there is a communication error when sending a Google Apps password to Google, Core sends the old password to the device. Core tracks the number of attempts to send updated passwords to Google. If it reaches the preset maximum number of attempts to contact Google servers, Core stops trying and the password is set to failure state. At this point, you must manually renew the Google Apps password.

You can renew the Google password for an individual user or a set of users on the Users page in the Core Admin Portal. After you generate it, Core pushes the new password to Google when the device checks in.

### Procedure

1. Go to **Devices & Users > Users**.
2. Select the user or users whose Google password you want to renew.
3. Select **Actions > Renew Google Apps Password**.

The Admin Portal shows a dialog that lists the users whose Google Apps password you want to renew.

4. Click **Renew Google Apps Password**.

The Admin Portal sends the request to renew the Google Apps password for the selected users.

5. Click **Close**.

## Setting up Gmail with Android Enterprise

You can deploy Gmail to Android Enterprise devices if you have set up Core for Android Enterprise.



If you want to set up Email+ with Android Enterprise, please see *Email+ for Android Guide*.


Add Gmail to the App Catalog on Core as you would any Android Enterprise app. That is, in the Admin Portal, in **Apps > App Catalog**, add Gmail from Google Play. When adding it, be sure to select **Install this app for Android enterprise**.

When you add the Gmail app, its app configurations are displayed in the **Configuration Choices** section. Edit these choices according to the following table:

TABLE 1. GMAIL CONFIGURATION PARAMETERS

Settings	Description
Email Address	Enter substitution variables to define the email address. Typically, you enter \$EMAIL\$. You can also enter combinations of these variables, depending on your ActiveSync server requirements: \$USERID\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$
Hostname or Host	Enter the host name of the mail server to use. Enter the fully qualified domain name of the Exchange server or the Standalone Sentry you are using.
Username	Use variables to define the username for the email account.
SSL Required	Select if you want secure communication using https: to the server that you specified for Exchange host.
Trust all certificates	Select only if you want the app to automatically accept untrusted certificates. Use this option only for debugging or development when working in a test environment.
Login certificate alias	Enter the alias for the login certificate. The value should be a string alias representing a certificate with private key stored in the work profile keystore. For example: \$CERT_ALIAS:<certificate config name>\$

TABLE 1. GMAIL CONFIGURATION PARAMETERS (CONT.)

Settings	Description
	<div>  <p>When a certificate alias is used with a password, Gmail does not send the certificate alias to the server and an "Unable to connect to server" error is displayed. This is a Google issue.</p> </div>
Default email signature	\$USERID\$
Default sync window	Use the Default sync window drop-down menu to select an interval in minutes for the device to sync with app or data updates.

**Related topics**

- ["Setting up Core for Android Enterprise" on page 14](#)
- "Deploying public Android Enterprise apps" in the *Core Apps@Work Guide*

# Managing Wi-Fi Settings

This section addresses the Wi-Fi settings.

- ["Wi-Fi settings" below](#)
- ["Wi-Fi profiles and password caching" on page 218](#)
- ["Wi-Fi network priority for Android devices" on page 218](#)
- ["Using Wi-Fi priority values" on page 222](#)
- ["How an Android device chooses its Wi-Fi network" on page 222](#)
- ["Wi-Fi network manual override behavior" on page 223](#)
- ["Wi-Fi authentication types" on page 223](#)

## Wi-Fi settings

To configure wireless network access, in the Admin Console, go to **Policies & Configs > Configurations**. Click **Add New > Wi-Fi** to create a new configuration.



Do not assign multiple Wi-Fi profiles to a device if the Network Name SSID (Service Set Identifier) differs only by case. For example, if one profile has an SSID value of "yourco" and another has an SSID of "YourCo," those two must not be assigned to the same device. Doing so will cause check-in problems, and full device details will not be properly recorded.

## Android 10 devices

On Android 10 devices or supported newer versions, upon installation or upgrade, device users can configure Wi-Fi and location settings in specific modes.



Administrators are required to leave in all modes of deployment to enable Wi-Fi and MTD configurations to be successfully applied. This means having the Allow the user to turn on location sharing lockdown field selected (checked.)

The table below depicts the behavior changes in different configuration modes:



TABLE 1. WI-FI CHANGES IN SPECIFIC CONFIGURATION MODES

Item	Description
All modes	Disconnect Wi-Fi local action is disabled in all modes on Android 10 devices. For all modes of deployment, to enable Wi-Fi and MTD configurations to be successfully applied, the Allow the user to turn on location sharing lockdown field must be selected.
(Android Enterprise) <ul style="list-style-type: none"> <li>• Work Profile mode</li> <li>• Work Profile on Company Owned devices (Android 11 or supported newer versions)</li> </ul>	<p>Device users are requested to activate location for the device and for the managed profile. In order for administrators to update Wi-Fi and to have Mobile Threat Defense detect Wi-Fi-based threats, device users must activate location. If the device user chooses No, the device will be flagged with an unblocking error for non-compliance and Core will report a configuration error.</p> <p>Administrators will not be able to disable Wi-Fi through UEM configurations in Work managed device mode on Android 10 devices.</p>
(Android Enterprise) <ul style="list-style-type: none"> <li>• Work Managed Device (COPE) mode</li> </ul>	In the background, Core will turn on the location services setting without device user intervention. Wi-Fi and MTD configurations should be successful with no errors. If there is no MTD configuration or a Wi-Fi configuration, the device user can switch location service on or off.
Device Administrator (DA) mode	Wi-Fi configurations will not be supported and will show as Sent on the server with config error. MTD configurations will be still accepted for non-network threats but the Wi-Fi related threats will not work for Device Administrators and MAM. Administrators will not be able to disable Wi-Fi through UEM configurations in Device Administrator mode on Android 10 devices.
Kiosk mode	<p>Administrators wanting users to enable/disable Wi-Fi but not connect to any other Wi-Fi network settings are not supported. Options available to administrators are:</p> <ul style="list-style-type: none"> <li>• Scenario 1 - Administrators wanting users to enable/disable Wi-Fi and connect to any available Wi-Fi will need to have the following settings in Kiosk mode: Lockdown settings: Allow Wi-Fi (de-selected) and Allow Wi-Fi to be configured (de-selected). Kiosk Mode Settings: Allow users to Access Wi-Fi Settings (selected).</li> <li>• Scenario 2 - Administrators wanting to block users from any Wi-Fi controls will need to have the following Lockdown settings:               <ul style="list-style-type: none"> <li>- Allow Wi-Fi (selected)</li> <li>- Allow Wi-Fi to be configured (selected).</li> </ul> </li> </ul>

## Wi-Fi profiles and password caching

To make deployments easier, Core offers the option of caching a user's Wi-Fi password. This option is turned off by default. Cached passwords are encrypted, stored on Core, and used only for authentication. Note that the password must match the LDAP password in order for this feature to be of use.

## Wi-Fi network priority for Android devices



---

Wi-Fi priority values do not work with Android devices from version 8 and higher.

---

Within the Core user interface, you set the Wi-Fi network priority for Android devices in two places in the user interface. First, set the Lockdown policy option for Android Wi-Fi devices, then you can set the Wi-Fi configuration. The Lockdown policy option "**Always Connect Device to Managed Wi-Fi**" ensures that Android devices pro-actively connect to the highest priority managed Wi-Fi network in range. By enabling this field in the Lockdown policy and using Wi-Fi priority settings, administrators can control which Wi-Fi network a device connects to. In addition, the Wi-Fi network configuration settings allow you specify a direct or automatic Wi-Fi connection to a Wi-Fi proxy setting, increasing the network security of your Wi-Fi devices. Both the Wi-Fi network priority and the **Always Connect Device to Managed Wi-Fi** lockdown policy option apply to *all* Android devices.

With **Always Connect Device to Managed Wi-Fi**:

- **ENABLED**: an Android device will always connect to the highest priority managed Wi-Fi network available, actively disconnecting from any unmanaged networks.
  - The Wi-Fi Priority value you set provides a preference for the highest priority network if multiple managed networks are available.
  - The connection to the managed Wi-Fi network is maintained as long as the signal is in range, even if a managed Wi-Fi network with a higher priority becomes available.
  - Exception: a newly received Wi-Fi configuration goes into effect after the current Wi-Fi connection disconnects.
- **DISABLED**: an Android device will connect to the highest priority Wi-Fi network as determined by Android.

Caution: When enabling **Always Connect Device to Managed Wi-Fi** in the Lockdown policy, because the device will actively connect to managed Wi-Fi SSID with the highest priority, if there is an error in the Wi-Fi configuration it is possible for the device to lose Wi-Fi access.



---

When **Always Connect Device to Managed Wi-Fi** is enabled and a managed Wi-Fi network is in range, the user cannot override the Wi-Fi connection choice and cannot choose to connect to an unmanaged network.

---

## Setting up enforced Wi-Fi network priority

First, set up the Lockdown policy to enable **Always Connect Device to Managed Wi-Fi** and apply the policy to the device.

### Procedure

1. Go to **Policies & Configs > Policies**.
2. Click **Add New > Lockdown**.
3. In the New Lockdown Policy dialog box, enter a **Name**.
4. Scroll down to the Android section. For **Always Connect Device to Managed Wi-Fi**, select **Enable**.
5. Fill out the rest of the Lockdown policy as needed.
6. Click **Save**.
7. Apply the policy to a label to assign it to the appropriate Android devices.

Next, provide values for network priority settings for all Wi-Fi configurations. From this menu, you can select a direct or automatic proxy server as well as specific servers to exclude.

In the Core Admin Portal:

1. Go to **Policies & Configs > Configurations**.
2. Select an existing **Wi-Fi** configuration, and click **Edit** in the right-side panel.
3. Locate the **Android Settings** section in the dialog box.
4. For **Priority**, enter a number between 1 (lowest priority) and 100 (highest priority), inclusive, or leave it blank (default priority).



Devices use the priority that is provided when the Wi-Fi configuration is provisioned. Future changes to the priority value are not sent to the device.

---

5. Select an optional **Proxy Type** that is supported on Android 8.0 or supported newer versions. Use the drop-down menu to select from the following options:

- a. **None:** This is the default value, indicating that no proxy server is specified.
- b. **Direct:** Select to specify a direct connection to a proxy server. After you make this selection, the menu expands and the following fields are displayed:

**Host Exclusions List:** Click + to enter one or more domains of traffic that will not be proxied. This setting applies to the URL traffic, but it does not apply to the proxy server.

**Proxy Server:** Enter the host name or IP address of a proxy server.

**Proxy Port:** Specify a proxy server port.

- c. **Auto:** Select to specify an automatic connection to the proxy server. After you make this selection, the following field is displayed:

**PAC URL:** Enter the proxy auto-config (PAC) URL of the Wi-Fi proxy server. The PAC URL provides a mapping of URLs that the software uses to locate the proxy server automatically.

6. Click **Save**.

The Wi-Fi configuration is now pushed to *all* devices that have the configuration's labels applied. The Priority designation applies to both newly provisioned and previously provisioned network settings.

7. Apply the Wi-Fi configurations to a label to assign them to the appropriate devices.

When the Wi-Fi configuration and the Lockdown policy as described are applied to a device, the highest priority Wi-Fi network is enforced.

## Android 10 specific Wi-Fi settings


On Android 10 devices or supported newer versions, upon installation or upgrade, device users can configure Wi-Fi and location settings in specific modes.

Note The Following:

- For all modes of deployment, to enable Wi-Fi and MTD configurations to be successfully applied, the Allow the user to turn on location sharing lockdown field must be selected.
- Administrators will not be able to disable Wi-Fi through UEM configurations in Work managed device mode and Device Administrator mode on Android 10 devices.
- Administrators are required to leave in all modes of deployment to enable Wi-Fi and MTD configurations to be successfully applied.

Wi-Fi configuration now requires end users to allow location services on the device. The behavior changes in different configuration modes and is documented in the table below.

TABLE 1. ANDROID 10 Wi-Fi SETTINGS

Item	Description
(Android Enterprise) Work Profile mode	Device users are requested to activate location for the device and for the Managed Profile. In order for administrators to update Wi-Fi and to have Mobile Threat Defense detect Wi-Fi-based threats, device users must activate location. If the device user chooses No, the device will be flagged with an unblocking error for non-compliance and Core will report a configuration error.
(Android Enterprise) <ul style="list-style-type: none"> <li>• Work Managed Device mode</li> <li>• Managed Device with Work Profile (COPE)</li> </ul>	<p>In the background, Core will programmatically turn on the location services setting without device user intervention. Wi-Fi and MTD configurations should be successful with no errors.</p> <hr/> <p> If there is no MTD configuration or a Wi-Fi configuration, the device user can switch location service on or off.</p> <hr/>
Device Administrator (DA) Mode	Wi-Fi configurations will not be supported and will show as Sent on the server with config error. MTD configurations will be still accepted for non-network threats but the Wi-Fi related threats will not work for Device Administrators and MAM.
Kiosk Mode	<p>Administrators wanting users to enable/disable Wi-Fi but not connect to any other Wi-Fi network settings are not supported. Options available to administrators are:</p> <ul style="list-style-type: none"> <li>• <b>Scenario 1:</b> Administrators wanting users to enable/disable Wi-Fi and connect to any available Wi-Fi will need to have the below settings in Kiosk. <ul style="list-style-type: none"> <li>◦ Lockdown settings &gt; Allow Wi-Fi (de-selected)</li> <li>◦ Lockdown settings &gt; Allow Wi-Fi to be configured (de-selected)</li> <li>◦ Kiosk Mode Settings &gt; Allow users to Access Wi-Fi Settings (selected)</li> </ul> </li> <li>• <b>Scenario 2:</b> Administrators wanting to block users from any Wi-Fi controls. <ul style="list-style-type: none"> <li>◦ Lockdown Settings &gt; Allow Wi-Fi (selected)</li> <li>◦ Lockdown Settings &gt; Allow Wi-Fi to be configured (selected)</li> </ul> </li> </ul>

## Using Wi-Fi priority values

Administrators can use the Wi-Fi priority feature to influence the network connections that devices make. The table below describes how to set Wi-Fi priorities to achieve the noted results.

TABLE 1. WI-FI PRIORITY VALUES

Desired outcome	Settings required
Allow any Wi-Fi connection, equally	(This is the default state.) For <b>Always Connect Device to Managed Wi-Fi</b> in Lockdown policy: <b>Disable</b> For Wi-Fi configuration: The <b>Priority</b> field is ignored
Ensure that managed Wi-Fi networks always get priority over non-managed networks; actively disconnect from unmanaged networks when a managed network is available.  Do not allow users to override the Wi-Fi connection choice with an unmanaged network.	For <b>Always Connect Device to Managed Wi-Fi</b> in Lockdown policy: <b>Enable</b> For Wi-Fi configuration: set the <b>Priority</b> field for each Wi-Fi configuration. 1 = lowest, 100 = highest.

## How an Android device chooses its Wi-Fi network

If a device has multiple Wi-Fi networks configured, then it will automatically connect to an SSID in the following priority order, assuming a signal is available:

1. a managed SSID with the highest priority as set by the administrator (if **Always Connect Device to Managed Wi-Fi** is enabled.)
2. an unmanaged SSID, (or a managed SSID if **Always Connect Device to Managed Wi-Fi** is disabled) as chosen by the Android operating system.

When multiple Wi-Fi networks have the same priority, the Android operating system typically prioritizes the most recently used SSID.

When the device receives a new highest-priority Wi-Fi configuration, the configuration takes effect after the current Wi-Fi connection is ended for any reason.

### When multiple Wi-Fi signals become available

In Mobile@Work with the Lockdown policy setting **Always Connect Device to Managed Wi-Fi** set to **Enable**, an existing unmanaged Wi-Fi connection is pro-actively disconnected if a managed SSID signal comes into range.

For example, if a user connects to an unmanaged network, and walks into range of one or more managed networks, the device disconnects from the unmanaged network and connects to the highest-priority managed network.

With the Lockdown policy setting **Always Connect Device to Managed Wi-Fi** set to Disable, Wi-Fi connections are not actively disconnected. The next time the Wi-Fi connection is reestablished, Android will automatically choose the highest priority network.

## Wi-Fi network manual override behavior

A user’s ability to manually choose a Wi-Fi network depends on the **Always Connect Device to Managed Wi-Fi** setting in the Lockdown policy, as shown in the table.

TABLE 1. Wi-Fi NETWORK MANUAL OVERRIDE BEHAVIOR

Lockdown Policy Setting	Wi-Fi SSID manual override behavior
<b>Always Connect Device to Managed Wi-Fi:</b> Disable	A user can select and override a Wi-Fi SSID connection by connecting manually.
<b>For Always Connect Device to Managed Wi-Fi:</b> Enable	<p>A user can attempt to select an SSID by connecting manually, however, if at any time a higher priority network is in range, the device disconnects from an unmanaged network and connects to the highest priority managed network.</p> <p>If the user manually connects to a managed network, the connection is maintained even if a higher priority managed network comes into range.</p>

## Wi-Fi authentication types

The fields that appear in the **New Wi-Fi Setting** dialog change based on values selected. The following tables describe the fields required **for each selection in the Authentication field**:

### Open authentication

Use the following guidelines to set up Open authentication.

TABLE 1. WI-FI OPEN AUTHENTICATION FIELD DESCRIPTIONS

Item	Description
Name	Enter the name to use to reference this configuration in Core.
Network Name (SSID)	Enter the name (i.e., service set identifier) of the Wi-Fi network these settings apply to. This field is case sensitive.
Description	Enter additional text to clarify the purpose of this group of Wi-Fi settings.
Hidden Network	Select this option if the SSID is not broadcast.
Authentication	Select Open.
Data Encryption	<p>Select the data encryption method associated with the selected authentication type. The selection affects which of the following fields are displayed. For Open authentication, the following encryption options are available:</p> <ul style="list-style-type: none"> <li>• Disabled</li> <li>• WEP</li> </ul>
Network Key	<p>WEP encryption</p> <p>Enter the network key necessary for accessing this network. The network key should be 5 or 13 ASCII characters or 10 or 26 hexadecimal digits.</p>
Key Index	<p>WEP encryption</p> <p>If using multiple network keys, select a number indicating the memory position of the correct encryption key.</p>
Confirm Network Key	Re-enter the network key to confirm.
User Name	<p>WEP Enterprise encryption</p> <p>Specify the variable to use as the user name when establishing the Wi-Fi connection. See <a href="#">"Supported variables for Wi-Fi authentication" on page 237</a></p>
Password	<p>WEP Enterprise encryption</p> <p>Specify the variable to use and any necessary custom formatting for the Wi-Fi password. The default variable selected is \$PASSWORD\$.</p> <p>Enter additional variables or text in the text box adjacent to the Password field. Entries in this text box are kept hidden and will not be visible to any Core administrator.</p>



TABLE 1. Wi-Fi OPEN AUTHENTICATION FIELD DESCRIPTIONS (CONT.)

Item	Description
	<p>Note The Following:</p> <ul style="list-style-type: none"> <li>If you specify \$PASSWORD\$, also enable <b>Save User Password</b> under <b>Settings &gt; System Settings &gt; Users &amp; Devices &gt; Registration</b>.</li> <li>All variables and text up to the last valid variable will be visible. Anything after the last valid variable will not be visible. The valid variable may appear in either of the password fields.</li> </ul> <p>See <a href="#">"Supported variables for Wi-Fi authentication" on page 237</a>.</p>
Apply to Certificates	<p>WEP Enterprise encryption</p> <p>Configure this field with the CA certificate needed to validate the Identity Certificate presented by the Wi-Fi Access Point. It is <b>not</b> the CA certificate needed to validate the Identity Certificate sent to the device in the Wi-Fi config.</p>
Trusted Certificate Names	<p>WEP Enterprise encryption.</p> <p>If you did not specify trusted certificates in the Apply to Certificates list, then enter the names of the authentication servers to be trusted. You can specify a particular server, such as server.mycompany.com or a partial name such as *.mycompany.com.</p>
Allow Trust Exceptions	<p>WEP Enterprise encryption.</p> <p>Select this option to let users decide to trust a server when the chain of trust can't be established. To avoid these prompts, and to permit connections only to trusted services, turn off this option and upload all necessary certificates.</p>
Use Per-connection Password	<p>WEP Enterprise encryption.</p> <p>Select this option to prompt the user to enter a password each time the device connects to the Wi-Fi network.</p>
EAP Type	<p>Select the authentication protocol used:</p> <ul style="list-style-type: none"> <li>PEAP</li> <li>TLS</li> <li>TTLS</li> </ul> <p>You must select only one protocol.</p>

TABLE 1. WI-FI OPEN AUTHENTICATION FIELD DESCRIPTIONS (CONT.)

Item	Description
	<p><b>If you select EAP-FAST</b>, then you also need to specify the Protected Access Credential (PAC).</p> <p><b>If you select TLS</b>, then you must specify an Identity Certificate.</p> <p><b>If you select TTLS</b>, then you must also specify the Inner Identity Authentication Protocol. You may optionally specify an Outer Identity, which on Android devices is propagated to the Anonymous Identity field in the Android system Wi-Fi settings.</p>
Connects To	Select Internet or Work.
Apple Settings	These features are not supported on Android devices.
Windows Settings	These features are not supported on Android devices.

### Related topics

- ["Shared authentication" below](#)
- ["WPA Enterprise authentication" on page 229](#)
- ["WPA2 / WPA3 Enterprise authentication" on page 232](#)
- ["WPA Personal authentication" on page 234](#)
- ["WPA2 / WPA3 Personal authentication" on page 236](#)
- ["Supported variables for Wi-Fi authentication" on page 237](#)

## Shared authentication

Use the following guidelines to set up shared authentication:

TABLE 1. WI-FI SHARED AUTHENTICATION FIELD DESCRIPTIONS

Item	Description
Name	Enter the name to use to reference this configuration in Core.
Network Name (SSID)	Enter the name (i.e., service set identifier) of the Wi-Fi network these settings apply to. This field is case sensitive.
Description	Enter additional text to clarify the purpose of this group of Wi-Fi settings.
Hidden Network	Select this option if the SSID is not broadcast.

TABLE 1. WI-FI SHARED AUTHENTICATION FIELD DESCRIPTIONS (CONT.)

Item	Description
Authentication	Select Shared.
Data Encryption	<p>Select the data encryption method associated with the selected authentication type. The selection affects which of the following fields are displayed. For Shared authentication, the following encryption options are available:</p> <ul style="list-style-type: none"> <li>• Disabled</li> <li>• WEP</li> </ul>
Network Key	<p>WEP encryption</p> <p>Enter the network key necessary for accessing this network. The network key should be 5 or 13 ASCII characters or 10 or 26 hexadecimal digits.</p>
Key Index	<p>WEP encryption</p> <p>If using multiple network keys, select a number indicating the memory position of the correct encryption key.</p>
Confirm Network Key	Re-enter the network key to confirm.
User Name	<p>WEP Enterprise encryption</p> <p>Specify the variable to use as the user name when establishing the Wi-Fi connection. See <a href="#">"Supported variables for Wi-Fi authentication" on page 237</a>.</p>
Password	<p>WEP Enterprise encryption</p> <p>Specify the variable to use and any necessary custom formatting for the Wi-Fi password. The default variable selected is \$PASSWORD\$.</p> <p>Enter additional variables or text in the text box adjacent to the Password field. Entries in this text box are kept hidden and will not be visible to any Core administrator.</p> <p>Note The Following:</p> <ul style="list-style-type: none"> <li>• If you specify \$PASSWORD\$, also enable <b>Save User Password</b> under <b>Settings &gt; System Settings &gt; Users &amp; Devices &gt; Registration</b>.</li> </ul>

TABLE 1. Wi-Fi SHARED AUTHENTICATION FIELD DESCRIPTIONS (CONT.)

Item	Description
	<ul style="list-style-type: none"> <li>All variables and text up to the last valid variable will be visible. Anything after the last valid variable will not be visible. The valid variable may appear in either of the password fields.</li> </ul> <p>See <a href="#">"Supported variables for Wi-Fi authentication" on page 237</a>.</p>
Apply to Certificates	<p>WEP Enterprise encryption</p> <p>Configure this field with the CA certificate needed to validate the Identity Certificate presented by the Wi-Fi Access Point. It is <b>not</b> the CA certificate needed to validate the Identity Certificate sent to the device in the Wi-Fi config.</p>
Trusted Certificate Names	<p>WEP Enterprise encryption.</p> <p>If you did not specify trusted certificates in the Apply to Certificates list, then enter the names of the authentication servers to be trusted. You can specify a particular server, such as server.mycompany.com or a partial name such as *.mycompany.com.</p>
Allow Trust Exceptions	<p>WEP Enterprise encryption.</p> <p>Select this option to let users decide to trust a server when the chain of trust can't be established. To avoid these prompts, and to permit connections only to trusted services, turn off this option and upload all necessary certificates.</p>
Use Per-connection Password	<p>WEP Enterprise encryption.</p> <p>Select this option to prompt the user to enter a password each time the device connects to the Wi-Fi network.</p>
EAP Type	<p>Select the authentication protocol used:</p> <ul style="list-style-type: none"> <li>PEAP</li> <li>TLS</li> <li>TTLS</li> </ul> <p>You must select only one protocol.</p> <p><b>If you select EAP-FAST</b>, then you also need to specify the Protected Access Credential (PAC).</p> <p><b>If you select TLS</b>, then you must specify an Identity Certificate.</p>

TABLE 1. WI-FI SHARED AUTHENTICATION FIELD DESCRIPTIONS (CONT.)

Item	Description
	<b>If you select TTLS</b> , then you must also specify the Inner Identity Authentication Protocol. You may optionally specify an Outer Identity, which on Android devices is propagated to the Anonymous Identity field in the Android system Wi-Fi settings.
Connects To	Select Internet or Work.
Apple Settings	These features are not supported on Android devices.

### Related topics

- ["Open authentication" on page 223](#)
- ["WPA Enterprise authentication" below](#)
- ["WPA2 / WPA3 Enterprise authentication" on page 232](#)
- ["WPA Personal authentication" on page 234](#)
- ["WPA2 / WPA3 Personal authentication" on page 236](#)
- ["Supported variables for Wi-Fi authentication" on page 237](#)

## WPA Enterprise authentication

Use the following guidelines to set up WPA Enterprise authentication:

TABLE 1. WI-FI WPA ENTERPRISE AUTHENTICATION FIELD DESCRIPTIONS

Item	Description
Name	Enter the name to use to reference this configuration in Core.
Network Name (SSID)	Enter the name (i.e., service set identifier) of the Wi-Fi network these settings apply to. This field is case sensitive.
Description	Enter additional text to clarify the purpose of this group of Wi-Fi settings.
Hidden Network	Select this option if the SSID is not broadcast.
Authentication	Select WPA Enterprise.
Data Encryption	Select the data encryption method associated with the selected authentication type. For WPA Enterprise authentication, the following encryption options are available: <ul style="list-style-type: none"> <li>• AES</li> </ul>

TABLE 1. Wi-Fi WPA ENTERPRISE AUTHENTICATION FIELD DESCRIPTIONS (CONT.)

Item	Description
	<ul style="list-style-type: none"> <li>• TKIP</li> </ul>
User Name	Specify the variable to use as the user name when establishing the Wi-Fi connection. See <a href="#">"Supported variables for Wi-Fi authentication" on page 237</a>
Password	<p>Specify the variable to use and any necessary custom formatting for the Wi-Fi password. The default variable selected is \$PASSWORD\$.</p> <p>Enter additional variables or text in the text box adjacent to the Password field. Entries in this text box are kept hidden and will not be visible to any Core administrator.</p> <p>Note The Following:</p> <ul style="list-style-type: none"> <li>• If you specify \$PASSWORD\$, also enable Save User Password under <b>Settings &gt; System Settings &gt; Users &amp; Devices &gt; Registration</b>.</li> <li>• All variables and text up to the last valid variable will be visible. Anything after the last valid variable will not be visible. The valid variable may appear in either of the password fields.</li> </ul> <p>See <a href="#">"Supported variables for Wi-Fi authentication" on page 237</a></p>
Apply to Certificates	<p>Configure this field with the CA certificate needed to validate the Identity Certificate presented by the Wi-Fi Access Point. It is <b>not</b> the CA certificate needed to validate the Identity Certificate sent to the device in the Wi-Fi configuration.</p> <p>If you configure multiple certificates, either as root certificates in separate files, or chain certificates in a single file, they appear in the CA cert drop-down on the client, however, "unspecified" is the selected value for the certificate.</p>
Trusted Certificate Names	<p>This feature is not supported on Android devices.</p> <p>If you did not specify trusted certificates in the Apply to Certificates list, then enter the names of the authentication servers to be trusted. You can specify a particular server, such as server.mycompany.com or a partial name such as *.mycompany.com.</p>
Allow Trust Exceptions	This feature is not supported on Android devices.

TABLE 1. Wi-Fi WPA ENTERPRISE AUTHENTICATION FIELD DESCRIPTIONS (CONT.)

Item	Description
	Select this option to let users decide to trust a server when the chain of trust can't be established. To avoid these prompts, and to permit connections only to trusted services, turn off this option and upload all necessary certificates.
Use Per-connection Password	This feature is not supported on Android devices. Select this option to prompt the user to enter a password each time the device connects to the Wi-Fi network.
EAP Type	Select the authentication protocol used: <ul style="list-style-type: none"> <li>• PEAP</li> <li>• TLS</li> <li>• TTLS</li> </ul> <p>You must select only one protocol.</p> <p><b>If you select EAP-FAST</b>, then you also need to specify the Protected Access Credential (PAC).</p> <p><b>If you select TLS</b>, then you must specify an Identity Certificate.</p> <p><b>If you select TTLS</b>, then you must also specify the Inner Identity Authentication Protocol. You may optionally specify an Outer Identity, which on Android devices is propagated to the Anonymous Identity field in the Android system Wi-Fi settings.</p>
Connects To	Select Internet or Work.
Apple Settings	These features are not supported on Android devices.

**Related topics**

- ["Open authentication" on page 223](#)
- ["Shared authentication" on page 226](#)
- ["WPA2 / WPA3 Enterprise authentication" on the next page](#)
- ["WPA Personal authentication" on page 234](#)
- ["WPA2 / WPA3 Personal authentication" on page 236](#)
- ["Supported variables for Wi-Fi authentication" on page 237](#)

## WPA2 / WPA3 Enterprise authentication

Use the following guidelines to configure WPA2 or WPA3 Enterprise authentication.

Except for Apple TV, WPA2 Enterprise is applicable to iOS 8.0 or supported newer versions.

WPA3 Enterprise is applicable to iOS 13.0 or supported newer versions.

TABLE 1. Wi-Fi WPA2 / WPA3 ENTERPRISE AUTHENTICATION FIELD DESCRIPTION

Item	Description
Network Name (SSID)	Enter the name (i.e., service set identifier) of the Wi-Fi network these settings apply to. This field is case sensitive.
Description	Enter additional text to clarify the purpose of this group of Wi-Fi settings.
Hidden Network	Select this option if the SSID is not broadcast.
Authentication	Select one: <ul style="list-style-type: none"><li>• WPA2 Enterprise</li><li>• WPA2 Enterprise (iOS 8 or later except Apple TV)</li><li>• WPA3 Enterprise (iOS 13 or later)</li></ul>
Data Encryption	Select the data encryption method associated with the selected authentication type. For WPA2 Enterprise authentication, the following encryption options are available: <ul style="list-style-type: none"><li>• AES</li><li>• TKIP</li></ul>
User Name	Specify the variable to use as the user name when establishing the Wi-Fi connection. See <a href="#">"WPA2 / WPA3 Enterprise authentication" above</a> .
Password	<p>Specify the variable to use and any necessary custom formatting for the Wi-Fi password. The default variable selected is \$PASSWORD\$.</p> <p>Enter additional variables or text in the text box adjacent to the Password field. Entries in this text box are kept hidden and will not be visible to any Core administrator.</p> <p>Note The Following:</p> <ul style="list-style-type: none"><li>• If you specify \$PASSWORD\$, also enable <b>Save User Password</b> under <b>Settings &gt; System Settings &gt; Users &amp; Devices &gt; Registration</b>.</li></ul>



TABLE 1. Wi-Fi WPA2 / WPA3 ENTERPRISE AUTHENTICATION FIELD DESCRIPTION (CONT.)

Item	Description
	<ul style="list-style-type: none"> <li>All variables and text up to the last valid variable will be visible. Anything after the last valid variable will not be visible. The valid variable may appear in either of the password fields. Valid variables are variables in the drop-down list.</li> </ul>
Apply to Certificates	<p>Configure this field with the CA certificate needed to validate the Identity Certificate presented by the Wi-Fi Access Point. It is <b>not</b> the CA certificate needed to validate the Identity Certificate sent to the device in the Wi-Fi configuration.</p> <p>If you configure multiple certificates, either as root certificates in separate files, or chain certificates in a single file, they appear in the CA cert drop-down on the client, however, “unspecified” is the selected value for the certificate.</p>
Trusted Certificate Names	This feature is not supported on Android devices.
Allow Trust Exceptions	This feature is not supported on Android devices.
Use Per-connection Password	This feature is not supported on Android devices.
EAP Type	<p>Select the authentication protocol used:</p> <ul style="list-style-type: none"> <li>PEAP</li> <li>TLS</li> <li>TTLS</li> </ul> <p>You must select only one protocol.</p> <p><b>If you select EAP-FAST</b>, then you also need to specify the Protected Access Credential (PAC).</p> <p><b>If you select TLS</b>, then you must specify an Identity Certificate.</p> <p><b>If you select TTLS</b>, then you must also specify the Inner Identity Authentication Protocol. You may optionally specify an Outer Identity, which on Android devices is propagated to the Anonymous Identity field in the Android system Wi-Fi settings.</p>
Connects To	Select Internet or Work.
Apple Settings	These features are not supported on Android devices.

## Related topics

- ["Open authentication" on page 223](#)
- ["Shared authentication" on page 226](#)
- ["WPA Enterprise authentication" on page 229](#)
- ["WPA Personal authentication" below](#)
- ["WPA2 / WPA3 Personal authentication" on page 236](#)
- ["Supported variables for Wi-Fi authentication" on page 237](#)

## WPA Personal authentication

Use the following guidelines to configure WPA Personal authentication.

TABLE 1. WI-FI WPA PERSONAL AUTHENTICATION FIELD DESCRIPTIONS

Item	Description
Name	Enter the name to use to reference this configuration in Core.
Network Name (SSID)	Enter the name (i.e., service set identifier) of the Wi-Fi network these settings apply to. This field is case sensitive.
Description	Enter additional text to clarify the purpose of this group of Wi-Fi settings.
Hidden Network	Select this option if the SSID is not broadcast.
Authentication	Select WPA Personal.
Data Encryption	Select the data encryption method associated with the selected authentication type. For WPA Personal authentication, the following encryption options are available: <ul style="list-style-type: none"><li>• AES</li><li>• TKIP</li></ul>
Network Key	Enter the network key necessary for accessing this network. The key should be at least 8 characters long.
Confirm Network Key	Re-enter the network key to confirm.

TABLE 1. WI-FI WPA PERSONAL AUTHENTICATION FIELD DESCRIPTIONS (CONT.)

Item	Description
EAP Type	Not applicable.
Connects To	Select Internet or Work.
Apple Settings	These features are not supported on Android devices.

## WPA2 Personal authentication

Use the following guidelines to configure WPA2 Personal authentication.

TABLE 2. WI-FI WPA2 PERSONAL AUTHENTICATION FIELD DESCRIPTIONS

Item	Description
Name	Enter the name to use to reference this configuration in Core.
Network Name (SSID)	Enter the name (i.e., service set identifier) of the Wi-Fi network these settings apply to. This field is case sensitive.
Description	Enter additional text to clarify the purpose of this group of Wi-Fi settings.
Hidden Network	Select this option if the SSID is not broadcast.
Authentication	Select WPA2 Personal.
Data Encryption	<p>Select the data encryption method associated with the selected authentication type. For WPA Personal authentication, the following encryption options are available:</p> <ul style="list-style-type: none"> <li>• AES</li> <li>• TKIP</li> </ul>
Network Key	Enter the network key necessary for accessing this network. The key should be at least 8 characters long.
Confirm Network Key	Re-enter the network key to confirm.
EAP Type	Not applicable.
Connects To	Select Internet or Work.
iOS Settings	These features are not supported on Android devices.

## Related topics

- ["Open authentication" on page 223](#)
- ["Shared authentication" on page 226](#)
- ["WPA Enterprise authentication" on page 229](#)
- ["WPA2 / WPA3 Enterprise authentication" on page 232](#)
- ["WPA2 / WPA3 Personal authentication" below](#)
- ["Supported variables for Wi-Fi authentication" on the next page](#)

## WPA2 / WPA3 Personal authentication

Use the following guidelines to configure WPA2 or WPA3 Personal authentication.

WPA3 Personal is applicable to iOS 13.0 or supported newer versions.

TABLE 1. WI-FI WPA2 / WPA3 PERSONAL AUTHENTICATION FIELD DESCRIPTIONS

Item	Description
Name	Enter the name to use to reference this configuration in Core.
Network Name (SSID)	Enter the name (i.e., service set identifier) of the Wi-Fi network these settings apply to. This field is case sensitive.
Description	Enter additional text to clarify the purpose of this group of Wi-Fi settings.
Hidden Network	Select this option if the SSID is not broadcast.
Authentication	Select one: <ul style="list-style-type: none"><li>• WPA2 Personal</li><li>• WPA3 Personal (iOS 13 or later)</li></ul>
Data Encryption	Select the data encryption method associated with the selected authentication type. For WPA Personal authentication, the following encryption options are available: <ul style="list-style-type: none"><li>• AES</li><li>• TKIP</li></ul>
Network Key	Enter the network key necessary for accessing this network. The key should be at least 8 characters long.

TABLE 1. Wi-Fi WPA2 / WPA3 PERSONAL AUTHENTICATION FIELD DESCRIPTIONS (CONT.)

Item	Description
Confirm Network Key	Re-enter the network key to confirm.
EAP Type	Not applicable.
Connects To	Select Internet or Work.
Apple Settings	These features are not supported on Android devices.

### Related topics

- ["Open authentication" on page 223](#)
- ["Shared authentication" on page 226](#)
- ["WPA Enterprise authentication" on page 229](#)
- ["WPA2 / WPA3 Enterprise authentication" on page 232](#)
- ["WPA Personal authentication" on page 234](#)
- ["Supported variables for Wi-Fi authentication" below](#)

## Supported variables for Wi-Fi authentication

You can use the following variables in fields that support variables.

- \$PASSWORD\$ (only supported in the password field)
- \$EMAIL\$
- \$USERID\$
- \$DEVICE\_MAC\$
- \$NULL\$
- \$USER\_CUSTOM1\$... \$USER\_CUSTOM4\$ (custom fields defined for LDAP)

Custom attribute variable substitutions are supported.

### Related topics

- ["Open authentication" on page 223](#)
- ["Shared authentication" on page 226](#)
- ["WPA Personal authentication" on page 234](#)
- ["WPA2 / WPA3 Personal authentication" on the previous page](#)

- ["WPA Enterprise authentication" on page 229](#)
- ["WPA2 / WPA3 Enterprise authentication" on page 232](#)

# Managing VPN Settings

This section addresses the VPN settings. If you do not see information for the relevant VPN setting, check the *Core Device Management Guide* of the relevant OS.

- ["VPN settings overview" on the next page](#)
- ["Configuring new VPN settings" on the next page](#)
- ["Check Point Capsule" on the next page](#)
- ["Cisco AnyConnect \(iOS only\)" on the next page](#)
- ["Cisco Legacy AnyConnect" on page 241](#)
- ["F5 SSL" on page 249](#)
- ["IKEv2 \(iOS Only\)" on page 255](#)
- ["IKEv2 \(Windows\)" on page 256](#)
- ["IPSec \(Blue Coat\)" on page 256](#)
- ["IPSec \(Cisco\)" on page 256](#)
- ["Juniper SSL" on page 256](#)
- ["L2TP" on page 264](#)
- ["Tunnel \(iOS and macOS\)" on page 264](#)
- ["Tunnel \(Android\)" on page 264](#)
- ["Tunnel \(Samsung Knox Workspace\)" on page 265](#)
- ["Tunnel \(Windows\)" on page 265](#)
- ["NetMotion Mobility VPN \(iOS\)" on page 265](#)
- ["OpenVPN" on page 265](#)
- ["Palo Alto Networks GlobalProtect" on page 267](#)
- ["PPTP" on page 279](#)
- ["Pulse Secure SSL" on page 284](#)
- ["KNOX VPN Support" on page 291](#)
- ["Samsung Knox IPsec" on page 305](#)
- ["SonicWall Mobile Connect" on page 308](#)
- ["Custom SSL" on page 308](#)

## VPN settings overview

VPN is a technology that creates a secure network connection over a public network. A mobile device uses a VPN client to securely access protected corporate networks.

To use VPN:

- On the device, the user installs a VPN client app.

You determine how the user obtains the VPN client app. You can, for example, add the app as a Google Play Store app to the App Catalog. See “Managing Mobile Apps for Android” in the *Apps@Work Guide*.

NOTE: If the device has a VPN already set on the device before installing the VPN client app, Mobile@Work displays an error message. The message instructs the device user to install the VPN client app before setting the VPN connection setting.

- Define a VPN setting in Core.
- Apply labels to the VPN setting so that the VPN setting is sent to the appropriate devices.
- Depending on the type of VPN, additional set up steps may be required to complete the VPN configuration.

Mobile@Work uses the VPN client and the VPN setting to enable access to corporate networks.

## Configuring new VPN settings

In the Admin Portal, go to **Policies & Configs > Configurations** and click **Add New > VPN** to configure VPN access.

For macOS only, select one of the following Channel options:

- **Device channel** - the configuration is effective for all users on a device. This is the typical option.
- **User channel** - the configuration is effective only for the currently registered user on a device.

The following sections describe the fields required for each selection in the Connect Type field. For Tunnel support for Android, select Tunnel (Android) in the Connection Type field.

## Check Point Capsule

This VPN connection type is supported on iOS, macOS, and Windows devices only. It is not supported on Android devices

## Cisco AnyConnect (iOS only)

This VPN connection type is supported on iOS devices only. It is not supported on Android, macOS, and Windows devices.



## Cisco Legacy AnyConnect

This VPN connection type is supported on iOS devices (up to version 12.0), macOS, Android, and Windows devices.

Cisco Legacy AnyConnect is a universal app that can be used with Samsung Knox or with any Android device. This app can be used for all VPN modes:

- per-app inside the Knox container
- per-app outside the Knox container
- per-container (Knox)
- per-device (Knox)
- per-device (Android)

Use the following guidelines to configure Cisco Legacy AnyConnect VPN.

- ["Proxy - None \(default\)" below](#)
- ["Proxy - Manual " on page 243](#)
- ["Proxy - Automatic" on page 246](#)

Within these selections, you may make settings for:

- ["Custom Data" on page 248](#) (does not apply to Android devices)

### Proxy - None (default)

Use the following guidelines to configure a Cisco Legacy AnyConnect VPN without a proxy.

TABLE 1. PROXY - NONE SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.
Description	Provide a description that clarifies the purpose of these settings.
Channel	For macOS only. Select one of the following distribution options: <ul style="list-style-type: none"><li>• Device channel - the configuration is effective for all users on a device. This is the typical option.</li><li>• User channel - the configuration is effective only for the currently registered user on a device.</li></ul>
Connection Type	Select <b>Cisco Legacy AnyConnect</b> .
Samsung Knox	When selecting this option, a Samsung Knox license is required.

TABLE 1. PROXY - NONE SETTINGS (CONT.)



Item	Description
	<p>A VPN setting with this option selected cannot be successfully applied to a non-Samsung Android device.</p> <p>This setting is ignored on non-Android devices.</p>
Deploy inside Knox Workspace	<p>Select this option to deploy the VPN client app inside the Knox Workspace (container). Deploying the app inside the container means that the Knox security platform protects the app and its data.</p> <p>This option is available only if you select the <b>Samsung Knox</b> option.</p> <p>See:</p> <ul style="list-style-type: none"> <li>• <a href="#">"Configuring VPN modes when VPN client is outside the Knox container" on page 294</a></li> <li>• <a href="#">"Configuring VPN modes when VPN client is inside the Knox container" on page 301</a></li> </ul>
Server	Enter the IP address, hostname, or URL for the VPN server.
Proxy	<b>None</b> is the default setting. To configure a <b>Manual</b> or <b>Automatic</b> proxy, go to <a href="#">"Proxy - Manual " on the next page</a> or <a href="#">"Proxy - Automatic" on page 246</a> .
Username	<p>Specify the user name to use. The default value is \$USERID\$. Use this field to specify an alternate format, such as:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as the following:</p> <ul style="list-style-type: none"> <li>• \$USERID\$: \$EMAIL\$</li> <li>• \$USERID\$_\$EMAIL\$</li> </ul> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p> <hr/> <p> Some enterprises have a strong preference concerning which identifier is exposed.</p> <hr/>
User Authentication	<p>Select the user authentication to use:</p> <ul style="list-style-type: none"> <li>• Password - see next row for information.</li> <li>• Certificate - If you select Certificate, select the identity certificate to be used as the account credential.</li> </ul>

TABLE 1. PROXY - NONE SETTINGS (CONT.)

Item	Description
	If you select Certificate, and extended authentication (EAP) is not used, this certificate will be sent out for IKE client authentication. If extended authentication is used, this certificate can be used for EAP-TLS.
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
Group Name	Specify the name of the group to use.
VPN On Demand	If the Samsung Knox and per-App VPN fields are both selected, then select this option to use VPN On Demand.
Per-App VPN	<p>Select <b>Yes</b> to create a per-app VPN setting.</p> <p>You cannot delete a per-app VPN setting that is being used by an app. Remove the per-app VPN setting from the app before you delete the setting.</p> <p>You can enable per-app VPN for an app when you:</p> <ul style="list-style-type: none"> <li>• add the app in the App Catalog.</li> <li>• edit an in-house app or an App Store app in the App Catalog.</li> </ul> <hr/> <p> When multiple labels are assigned to associate the selected VPN configurations in the Per-App VPN section, then VPN prioritization will happen in the order of the selected list.</p> <hr/> <p>See the <i>Core Apps@Work Guide</i> for information about how to add or edit apps.</p>
Provider Type	This setting applies to iOS and macOS devices only.

Continue to "Custom Data" on page 248.

## Proxy - Manual

If you select **Manual**, you must specify the proxy server, port number, and proxy domain information.

TABLE 2. PROXY - MANUAL SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.
Description	Provide a description that clarifies the purpose of these settings.
Channel	For macOS only. Select one of the following distribution options: <ul style="list-style-type: none"> <li>• Device channel - the configuration is effective for all users on a device. This is the typical option.</li> <li>• User channel - the configuration is effective only for the currently registered user on a device.</li> </ul>
Connection Type	Select <b>Cisco Legacy AnyConnect</b> .
Samsung Knox	When selecting this option, a Samsung Knox license is required. A VPN setting with this option selected cannot be successfully applied to a non-Samsung Android device. This setting is ignored on non-Android devices.
Deploy inside Knox Workspace	Select this option to deploy the VPN client app inside the Knox Workspace (container). Deploying the app inside the container means that the Knox security platform protects the app and its data. This option is available only if you select the <b>Samsung Knox</b> option. See: <ul style="list-style-type: none"> <li>• <a href="#">"Configuring VPN modes when VPN client is outside the Knox container" on page 294</a></li> <li>• <a href="#">"Configuring VPN modes when VPN client is inside the Knox container" on page 301</a></li> </ul>
Server	Enter the IP address, hostname, or URL for the VPN server.
Proxy Server	Enter the name for the proxy server.
Proxy Server Port	Enter the port number for the proxy server. Type - Select <b>Static</b> or <b>Variable</b> for the type of authentication to be used for the proxy server.
Proxy Server User Name	If the authentication type is <b>Static</b> , enter the user name for the proxy server. If the authentication type is <b>Variable</b> , the default variable selected is \$USERID\$.
Proxy Server Password	If the authentication type is <b>Static</b> , enter the password for the proxy server. Confirm the password in the field below.

TABLE 2. PROXY - MANUAL SETTINGS (CONT.)



Item	Description
	If the authentication type is <b>Variable</b> , the default variable selected is \$PASSWORD\$.
Proxy Domains (iOS only)	This setting applies to iOS and macOS devices only.
Username	<p>Specify the user name to use. The default value is \$USERID\$. Use this field to specify an alternate format, such as:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as the following:</p> <ul style="list-style-type: none"> <li>• \$USERID\$: \$EMAIL\$</li> <li>• \$USERID\$_\$EMAIL\$</li> </ul> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p> <hr/> <p> Some enterprises have a strong preference concerning which identifier is exposed.</p> <hr/>
User Authentication	<p>Select the user authentication to use:</p> <ul style="list-style-type: none"> <li>• Password - see next row for information.</li> <li>• Certificate - If you select Certificate, select the identity certificate to be used as the account credential.</li> </ul> <p>If you select Certificate, and extended authentication (EAP) is not used, this certificate will be sent out for IKE client authentication. If extended authentication is used, this certificate can be used for EAP-TLS.</p>
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
Group Name	Specify the name of the group to use.

TABLE 2. PROXY - MANUAL SETTINGS (CONT.)

Item	Description
VPN on Demand	If the Samsung Knox and per-App VPN fields are both selected, then select this option to use VPN On Demand.
Per-App VPN	<p>Select <b>Yes</b> to create a per-app VPN setting.</p> <p>You cannot delete a per-app VPN setting that is being used by an app. Remove the per-app VPN setting from the app before you delete the setting.</p> <p>You can enable per-app VPN for an app when you:</p> <ul style="list-style-type: none"> <li>• add the app in the App Catalog.</li> <li>• edit an in-house app or an App Store app in the App Catalog.</li> </ul> <hr/> <p> When multiple labels are assigned to associate the selected VPN configurations in the Per-App VPN section, then VPN prioritization will happen in the order of the selected list.</p> <hr/> <p>See the <i>Core Apps@Work Guide</i> for information about how to add or edit iOS apps.</p>
Provider Type	This setting applies to iOS and macOS devices only.

Continue to ["Custom Data" on page 248](#).

## Proxy - Automatic

If you selected an Automatic proxy, you must specify the proxy server URL and proxy domain(s).


TABLE 3. PROXY - AUTOMATIC SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.
Description	Provide a description that clarifies the purpose of these settings.
Channel	<p>For macOS only. Select one of the following distribution options:</p> <ul style="list-style-type: none"> <li>• Device channel - the configuration is effective for all users on a device. This is the typical option.</li> <li>• User channel - the configuration is effective only for the currently registered user on a device.</li> </ul>
Connection Type	Select <b>Cisco Legacy AnyConnect</b> .
Samsung Knox	When selecting this option, a Samsung Knox license is required.

TABLE 3. PROXY - AUTOMATIC SETTINGS (CONT.)

Item	Description
	<p>A VPN setting with this option selected cannot be successfully applied to a non-Samsung Android device.</p> <p>This setting is ignored on non-Android devices.</p>
Deploy inside Knox Workspace	<p>Select this option to deploy the VPN client app inside the Knox Workspace (container). Deploying the app inside the container means that the Knox security platform protects the app and its data.</p> <p>This option is available only if you select the <b>Samsung Knox</b> option.</p> <p>See:</p> <ul style="list-style-type: none"> <li>• <a href="#">"Configuring VPN modes when VPN client is outside the Knox container" on page 294</a></li> <li>• <a href="#">"Configuring VPN modes when VPN client is inside the Knox container" on page 301</a></li> </ul>
Server	Enter the IP address, hostname, or URL for the VPN server.
Proxy Server URL	<p>Enter the URL for the proxy server.</p> <p>Enter the URL of the location of the proxy auto-configuration file.</p>
Proxy Domains (iOS only)	This setting applies to iOS and macOS devices only.
Username	<p>Specify the user name to use (required.) The default value is \$USERID\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as the following:</p> <ul style="list-style-type: none"> <li>• \$USERID\$: \$EMAIL\$</li> <li>• \$USERID_\$EMAIL\$</li> </ul> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p>
User Authentication	<p>Select the user authentication to use:</p> <ul style="list-style-type: none"> <li>• Password - see next row for information.</li> <li>• Certificate - If you select Certificate, select the identity certificate to be used as the account credential.</li> </ul>

TABLE 3. PROXY - AUTOMATIC SETTINGS (CONT.)

Item	Description
	If you select Certificate, and extended authentication (EAP) is not used, this certificate will be sent out for IKE client authentication. If extended authentication is used, this certificate can be used for EAP-TLS.
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
Group Name	Specify the name of the group to use.
VPN On Demand	If the Samsung Knox and per-App VPN fields are both selected, then select this option to use VPN On Demand.
Per-App VPN	<p><b>Select <b>Yes</b> to create a per-app VPN setting.</b></p> <p>You cannot delete a per-app VPN setting that is being used by an app. Remove the per-app VPN setting from the app before you delete the setting.</p> <p>You can enable per-app VPN for an app when you:</p> <ul style="list-style-type: none"> <li>• add the app in the App Catalog.</li> <li>• edit an in-house app or an App Store app in the App Catalog.</li> </ul> <hr/> <p> When multiple labels are assigned to associate the selected VPN configurations in the Per-App VPN section, then VPN prioritization will happen in the order of the selected list.</p> <hr/> <p>See the <i>Core Apps@Work Guide</i> for information about how to add or edit iOS apps.</p>
Provider Type	This setting applies to iOS and macOS devices only.

Continue to "[Custom Data](#)" below.

## Custom Data

Custom Data does not apply to Android devices.



- **Add+** - Click to add a new key / value pair.
- **Key / Value** - Enter the Key / value pairs necessary to configure the VPN setting. The app creator should provide the necessary key / value pairs.

## F5 SSL

This VPN connection type is supported on iOS, macOS, Windows devices. F5 SSL supports Android devices that have Samsung Knox enabled and on Android devices without Samsung Knox.

Use the following guidelines to configure the F5 SSL VPN connection type:

- ["Proxy - None \(default\)" below](#)
- ["Proxy - Manual " on page 251](#)
- ["Proxy - Automatic" on page 253](#)

Within these selections, you may make settings for:

- ["Custom Data" on page 255](#)

### Proxy - None (default)

Use the following guidelines to configure a F5 SSL VPN without a proxy.

TABLE 1. PROXY - NONE SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.
Description	Provide a description that clarifies the purpose of these settings.
Channel	For macOS only. Select one of the following distribution options: <ul style="list-style-type: none"> <li>• Device channel - the configuration is effective for all users on a device. This is the typical option.</li> <li>• User channel - the configuration is effective only for the currently registered user on a device.</li> </ul>
Connection Type	Select <b>F5 SSL</b> .
Samsung Knox	When selecting this option, a Samsung Knox license is required. A VPN setting with this option selected cannot be successfully applied to a non-Samsung Android device. This setting is ignored on non-Android devices.

TABLE 1. PROXY - NONE SETTINGS (CONT.)


Item	Description
Deploy inside Knox Workspace	<p>Select this option to deploy the VPN client app inside the Knox Workspace (container). Deploying the app inside the container means that the Knox security platform protects the app and its data.</p> <p>This option is available only if you select the <b>Samsung Knox</b> option.</p> <p>See:</p> <ul style="list-style-type: none"> <li>• <a href="#">"Configuring VPN modes when VPN client is outside the Knox container" on page 294</a></li> <li>• <a href="#">"Configuring VPN modes when VPN client is inside the Knox container" on page 301</a></li> </ul>
Server	Enter the IP address, hostname, or URL for the VPN server.
Proxy	<b>None</b> is the default setting. To configure a <b>Manual</b> or <b>Automatic</b> proxy, go to <a href="#">"Proxy - Manual " on the next page</a> or <a href="#">"Proxy - Automatic" on page 253</a> .
Username	<p>Specify the user name to use. The default value is \$USERID\$. Use this field to specify an alternate format, such as:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as the following:</p> <ul style="list-style-type: none"> <li>• \$USERID\$: \$EMAIL\$</li> <li>• \$USERID\$_\$EMAIL\$</li> </ul> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p> <hr/> <p> Some enterprises have a strong preference concerning which identifier is exposed.</p> <hr/>
User Authentication	<p>Select the user authentication to use:</p> <ul style="list-style-type: none"> <li>• Password - see next row for information.</li> <li>• Certificate - If you select Certificate, select the identity certificate to be used as the account credential.</li> </ul> <p>If you select Certificate, and extended authentication (EAP) is not used, this certificate will be sent out for IKE client authentication. If extended authentication is used, this certificate can be used for EAP-TLS.</p>

TABLE 1. PROXY - NONE SETTINGS (CONT.)

Item	Description
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL:\$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
VPN On Demand	If the Samsung Knox and per-App VPN fields are both selected, then select this option to use VPN On Demand.
Per-App VPN	When selecting this option, a Samsung Knox license is required.
Provider Type	This setting applies to iOS and macOS devices only.

Continue to ["Custom Data" on page 255](#).

## Proxy - Manual

If you select **Manual**, you must specify the proxy server, port number, and proxy domain information.


TABLE 2. PROXY - MANUAL SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.
Description	Provide a description that clarifies the purpose of these settings.
Channel	<p>For macOS only. Select one of the following distribution options:</p> <ul style="list-style-type: none"> <li>• Device channel - the configuration is effective for all users on a device. This is the typical option.</li> <li>• User channel - the configuration is effective only for the currently registered user on a device.</li> </ul>
Connection Type	Select <b>F5 SSL</b> .
Samsung Knox	<p>When selecting this option, a Samsung Knox license is required.</p> <p>A VPN setting with this option selected cannot be successfully applied to a non-Samsung Android device.</p> <p>This setting is ignored on non-Android devices.</p>

TABLE 2. PROXY - MANUAL SETTINGS (CONT.)

Item	Description
Deploy inside Knox Workspace	<p>Select this option to deploy the VPN client app inside the Knox Workspace (container). Deploying the app inside the container means that the Knox security platform protects the app and its data.</p> <p>This option is available only if you select the <b>Samsung Knox</b> option.</p> <p>See:</p> <ul style="list-style-type: none"> <li>• <a href="#">"Configuring VPN modes when VPN client is outside the Knox container" on page 294</a></li> <li>• <a href="#">"Configuring VPN modes when VPN client is inside the Knox container" on page 301</a></li> </ul>
Server	Enter the IP address, hostname, or URL for the VPN server.
Proxy	Select <b>Manual</b> . For an Automatic proxy, see <a href="#">"Proxy - Automatic" on the next page</a> .
Proxy Server	Enter the name for the proxy server.
Proxy Server Port	<p>Enter the port number for the proxy server.</p> <p>Type - Select <b>Static</b> or <b>Variable</b> for the type of authentication to be used for the proxy server.</p>
Proxy Server User Name	<p>If the authentication type is <b>Static</b>, enter the user name for the proxy server.</p> <p>If the authentication type is <b>Variable</b>, the default variable selected is \$USERID\$.</p>
Proxy Server Password	<p>If the authentication type is <b>Static</b>, enter the password for the proxy server. Confirm the password in the field below.</p> <p>If the authentication type is <b>Variable</b>, the default variable selected is \$PASSWORD\$.</p>
Proxy Domains (iOS only)	This setting applies to iOS and macOS devices only.
Username	<p>Specify the user name to use. The default value is \$USERID\$. Use this field to specify an alternate format, such as:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as the following:</p> <ul style="list-style-type: none"> <li>• \$USERID\$: \$EMAIL\$</li> <li>• \$USERID\$_\$EMAIL\$</li> </ul>

TABLE 2. PROXY - MANUAL SETTINGS (CONT.)

Item	Description
	<p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p> <hr/> <p> Some enterprises have a strong preference concerning which identifier is exposed.</p> <hr/>
User Authentication	<p>Select the user authentication to use:</p> <ul style="list-style-type: none"> <li>• Password - see next row for information.</li> <li>• Certificate - If you select Certificate, select the identity certificate to be used as the account credential.</li> </ul> <p>If you select Certificate, and extended authentication (EAP) is not used, this certificate will be sent out for IKE client authentication. If extended authentication is used, this certificate can be used for EAP-TLS.</p>
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
Per-App VPN	When selecting this option, a Samsung Knox license is required.
Provider Type	This setting applies to iOS and macOS devices only.

Continue to ["Custom Data" on page 255](#).

## Proxy - Automatic

If you selected an Automatic proxy, you must specify the proxy server URL and proxy domain(s).

TABLE 3. PROXY - AUTOMATIC SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.
Description	Provide a description that clarifies the purpose of these settings.
Channel	For macOS only. Select one of the following distribution options:

TABLE 3. PROXY - AUTOMATIC SETTINGS (CONT.)

Item	Description
	<ul style="list-style-type: none"> <li>• Device channel - the configuration is effective for all users on a device. This is the typical option.</li> <li>• User channel - the configuration is effective only for the currently registered user on a device.</li> </ul>
Connection Type	Select <b>F5 SSL</b> .
Samsung Knox	<p>When selecting this option, a Samsung Knox license is required.</p> <p>A VPN setting with this option selected cannot be successfully applied to a non-Samsung Android device.</p> <p>This setting is ignored on non-Android devices.</p>
Deploy inside Knox Workspace	<p>Select this option to deploy the VPN client app inside the Knox Workspace (container). Deploying the app inside the container means that the Knox security platform protects the app and its data.</p> <p>This option is available only if you select the <b>Samsung Knox</b> option.</p> <p>See:</p> <ul style="list-style-type: none"> <li>• <a href="#">"Configuring VPN modes when VPN client is outside the Knox container" on page 294</a></li> <li>• <a href="#">"Configuring VPN modes when VPN client is inside the Knox container" on page 301</a></li> </ul>
Server	Enter the IP address, hostname, or URL for the VPN server.
Proxy	Select <b>Automatic</b> . For a manual proxy, see <a href="#">"Proxy - Manual " on page 251</a>
Proxy Server URL	<p>Enter the URL for the proxy server.</p> <p>Enter the URL of the location of the proxy auto-configuration file.</p>
Proxy Domains (iOS only)	This setting applies to iOS and macOS devices only.
Username	<p>Specify the user name to use (required.) The default value is \$USERID\$.</p> <p>Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as the following:</p> <ul style="list-style-type: none"> <li>• \$USERID\$: \$EMAIL\$</li> <li>• \$USERID\$_\$EMAIL\$</li> </ul>

TABLE 3. PROXY - AUTOMATIC SETTINGS (CONT.)

Item	Description
	Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.
User Authentication	<p>Select the user authentication to use:</p> <ul style="list-style-type: none"> <li>• Password - see next row for information.</li> <li>• Certificate - If you select Certificate, select the identity certificate to be used as the account credential.</li> </ul> <p>If you select Certificate, and extended authentication (EAP) is not used, this certificate will be sent out for IKE client authentication. If extended authentication is used, this certificate can be used for EAP-TLS.</p>
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
VPN On Demand	If the Samsung Knox and per-App VPN fields are both selected, then select this option to use VPN On Demand.
Per-App VPN	When selecting this option, a Samsung Knox license is required.
Provider Type	This setting applies to iOS and macOS devices only.

Continue to "[Custom Data](#)" below.

## Custom Data

- **Add+** - Click to add a new key / value pair.
- **Key / Value** - Enter the Key / value pairs necessary to configure the VPN setting. The app creator should provide the necessary key / value pairs.

## IKEv2 (iOS Only)

This VPN connection type is supported on iOS devices. It is not supported on Android, macOS, and Windows devices.



---

iOS VPN configurations using IKEv2 need to include a selected value from the following list of certificate types:

---

- RSA
- ECDSA256
- ECDSA384
- ECDSA512

## IKEv2 (Windows)

This VPN connection type is supported on Windows devices. It is not supported on Android, iOS, and macOS devices.

## IPSec (Blue Coat)

This VPN connection type is supported on iOS devices. It is not supported on Android, macOS, and Windows devices.

## IPSec (Cisco)

This VPN connection type is supported on iOS and macOS devices. It is not supported on Android and Windows devices.

## Juniper SSL

This VPN connection type is supported on iOS, macOS, Android and Windows devices.



---

Ivanti recommends that you use Pulse Secure SSL instead of Juniper SSL.

---

The Juniper SSL VPN type supports Juniper SSL VPN definitions created in previous versions of Core. Juniper SSL VPN definitions are routed to the Pulse Secure VPN client. Use the type for new VPN definitions.

Use the following guidelines to configure Juniper SSL VPN.

- ["Proxy - None \(default\)" below](#)
- ["Proxy - Manual " on page 259](#)
- ["Proxy - Automatic" on page 261](#)

Within these selections, you may make settings for:

- ["Custom Data" on page 264](#)

### Proxy - None (default)

Use the following guidelines to configure a Juniper SSL VPN without a proxy.



TABLE 1. PROXY - NONE SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.
Description	Provide a description that clarifies the purpose of these settings.
Channel	<p>For macOS only. Select one of the following distribution options:</p> <ul style="list-style-type: none"> <li>• Device channel - the configuration is effective for all users on a device. This is the typical option.</li> <li>• User channel - the configuration is effective only for the currently registered user on a device.</li> </ul>
Connection Type	Select <b>Juniper SSL</b> .
Samsung Knox	<p>Select this option to use per-app VPN (either inside or outside the Knox Workspace) or per-container VPN. A Samsung Knox license is required.</p> <p>A VPN setting with this option selected cannot be successfully applied to a non-Samsung Android device.</p> <p>This setting is ignored on non-Android devices.</p>
Deploy inside Knox Workspace	<p>Select this option to deploy the VPN client app inside the Knox Workspace (container). Deploying the app inside the container means that the Knox security platform protects the app and its data.</p> <p>This option is available only if you select the <b>Samsung Knox</b> option.</p> <p>See:</p> <ul style="list-style-type: none"> <li>• <a href="#">"Configuring VPN modes when VPN client is outside the Knox container" on page 294</a></li> <li>• <a href="#">"KNOX VPN Support" on page 291</a></li> </ul>
Server	Enter the IP address, hostname, or URL for the VPN server.
Proxy	<b>None</b> is the default setting. Proxy is not supported on Android devices.
Username	<p>Specify the user name to use (required.) The default value is \$USERID\$. Use this field to specify an alternate format, such as:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as the following:</p> <ul style="list-style-type: none"> <li>• \$USERID\$: \$EMAIL\$</li> <li>• \$USERID\$ \$EMAIL\$</li> </ul>

TABLE 1. PROXY - NONE SETTINGS (CONT.)



Item	Description
	<p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p> <hr/> <p> Some enterprises have a strong preference concerning which identifier is exposed.</p> <hr/>
User Authentication	<p>Select the user authentication to use:</p> <ul style="list-style-type: none"> <li>• Password - see next row for information.</li> <li>• Certificate - If you select Certificate, select the identity certificate to be used as the account credential.</li> </ul>
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
Role	Specify the Juniper user role to use as a restriction.
Realm	Specify the Juniper realm to use as a restriction.
VPN On Demand	<p>On-Demand VPN is supported for Android only if the Samsung Knox and Per-app VPN checkboxes are selected. On Demand VPN for Android means that the Juniper SSL VPN connection is activated only when an app associated with it is launched. When all apps associated with this VPN connection type are stopped, VPN is disconnected.</p> <p>Select to enable VPN On Demand.</p>
Per-app VPN	<p>Select <b>Yes</b> to create a per-app VPN setting. An additional license may be required for this feature.</p> <p>The Provider Type field displays.</p> <p>You cannot delete a per-app VPN setting that is being used by an app. Remove the per-app VPN setting from the app before you delete the setting.</p> <p>You can enable per-app VPN for an app when you:</p> <ul style="list-style-type: none"> <li>• add the app in the App Catalog.</li> <li>• edit an in-house app or an App Store app in the App Catalog.</li> </ul>

TABLE 1. PROXY - NONE SETTINGS (CONT.)

Item	Description
	<div>  <p>When multiple labels are assigned to associate the selected VPN configurations in the Per-App VPN section, then VPN prioritization will happen in the order of the selected list.</p> </div> <hr/> <p>See the <i>Core Apps@Work Guide</i> for information about how to add or edit apps.</p>
Provider Type	This setting applies to iOS and macOS devices only.

Continue to ["Custom Data" on page 264](#).

## Proxy - Manual

Use the following guidelines to configure a Juniper SSL VPN with a manual proxy.

TABLE 2. PROXY - MANUAL SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.
Description	Provide a description that clarifies the purpose of these settings.
Channel	<p>For macOS only. Select one of the following distribution options:</p> <ul style="list-style-type: none"> <li>Device channel - the configuration is effective for all users on a device. This is the typical option.</li> <li>User channel - the configuration is effective only for the currently registered user on a device.</li> </ul>
Connection Type	Select <b>Juniper SSL</b> .
Samsung Knox	<p>Select this option to use per-app VPN (either inside or outside the Knox Workspace) or per-container VPN. A Samsung Knox license is required.</p> <p>A VPN setting with this option selected cannot be successfully applied to a non-Samsung Android device.</p> <p>This setting is ignored on non-Android devices.</p>
Deploy inside Knox Workspace	<p>Select this option to deploy the VPN client app inside the Knox Workspace (container). Deploying the app inside the container means that the Knox security platform protects the app and its data.</p> <p>This option is available only if you select the <b>Samsung Knox</b> option.</p> <p>See:</p>

TABLE 2. PROXY - MANUAL SETTINGS (CONT.)



Item	Description
	<ul style="list-style-type: none"> <li>"Configuring VPN modes when VPN client is outside the Knox container" on page 294</li> <li>"KNOX VPN Support" on page 291</li> </ul>
Server	Enter the IP address, hostname, or URL for the VPN server.
Proxy	Proxy is not supported on Android devices.
Proxy Server	This setting is not supported on Android devices.
Proxy Server Port	This setting is not supported on Android devices.
Type	This setting is not supported on Android devices.
Proxy Server User Name	This setting is not supported on Android devices.
Proxy Server Password	This setting is not supported on Android devices.
Proxy Domains (iOS only)	This setting applies to iOS and macOS devices only.
Username	<p>Specify the user name to use (required.) The default value is \$USERID\$. Use this field to specify an alternate format, such as:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as the following:</p> <ul style="list-style-type: none"> <li>\$USERID\$: \$EMAIL\$</li> <li>\$USERID\$_ \$EMAIL\$</li> </ul> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p> <hr/> <p> Some enterprises have a strong preference concerning which identifier is exposed.</p> <hr/>
User Authentication	<p>Select the user authentication to use:</p> <ul style="list-style-type: none"> <li>Password - see next row for information.</li> <li>Certificate - If you select Certificate, select the identity certificate to be used as the account credential.</li> </ul>
Password	Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:

TABLE 2. PROXY - MANUAL SETTINGS (CONT.)

Item	Description
	<p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
Role	Specify the Juniper user role to use as a restriction.
Realm	Specify the Juniper realm to use as a restriction.
VPN On Demand	<p>On-Demand VPN is supported for Android only if the Samsung Knox and Per-app VPN checkboxes are selected. On Demand VPN for Android means that the Juniper SSL VPN connection is activated only when an app associated with it is launched. When all apps associated with this VPN connection type are stopped, VPN is disconnected.</p> <p>Select to enable VPN On Demand.</p>
Per-app VPN	<p>Select <b>Yes</b> to create a per-app VPN setting. An additional license may be required for this feature.</p> <p>The Provider Type field displays.</p> <p>You cannot delete a per-app VPN setting that is being used by an app. Remove the per-app VPN setting from the app before you delete the setting.</p> <p>You can enable per-app VPN for an app when you:</p> <ul style="list-style-type: none"> <li>• add the app in the App Catalog.</li> <li>• edit an in-house app or an App Store app in the App Catalog.</li> </ul> <hr/> <p> When multiple labels are assigned to associate the selected VPN configurations in the Per-App VPN section, then VPN prioritization will happen in the order of the selected list.</p> <hr/> <p>See the <i>Core Apps@Work Guide</i> for information about how to add or edit apps.</p>
Provider Type	This setting applies to iOS and macOS devices only.

Continue to ["Custom Data" on page 264](#).

## Proxy - Automatic

Use the following guidelines to configure a Juniper SSL VPN with an automatic proxy.

TABLE 3. PROXY - AUTOMATIC SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.
Description	Provide a description that clarifies the purpose of these settings.
Channel	<p>For macOS only. Select one of the following distribution options:</p> <ul style="list-style-type: none"> <li>• Device channel - the configuration is effective for all users on a device. This is the typical option.</li> <li>• User channel - the configuration is effective only for the currently registered user on a device.</li> </ul>
Connection Type	Select <b>Juniper SSL</b> .
Samsung Knox	<p>Select this option to use per-app VPN (either inside or outside the Knox Workspace) or per-container VPN. A Samsung Knox license is required.</p> <p>A VPN setting with this option selected cannot be successfully applied to a non-Samsung Android device.</p> <p>This setting is ignored on non-Android devices.</p>
Deploy inside Knox Workspace	<p>Select this option to deploy the VPN client app inside the Knox Workspace (container). Deploying the app inside the container means that the Knox security platform protects the app and its data.</p> <p>This option is available only if you select the <b>Samsung Knox</b> option.</p> <p>See:</p> <ul style="list-style-type: none"> <li>• <a href="#">"Configuring VPN modes when VPN client is outside the Knox container" on page 294</a></li> <li>• <a href="#">"KNOX VPN Support" on page 291</a></li> </ul>
Server	Enter the IP address, hostname, or URL for the VPN server.
Proxy	Proxy is not supported on Android devices.
Proxy Server URL	This setting is not supported on Android devices.
Proxy Domains (iOS only)	This setting applies to iOS and macOS devices only.
Username	<p>Specify the user name to use (required.) The default value is \$USERID\$. Use this field to specify an alternate format, such as:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as the following:</p>

TABLE 3. PROXY - AUTOMATIC SETTINGS (CONT.)



Item	Description
	<ul style="list-style-type: none"> <li>• \$USERID\$:EMAIL\$</li> <li>• \$USERID\$_EMAIL\$</li> </ul> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p> <hr/> <p> Some enterprises have a strong preference concerning which identifier is exposed.</p> <hr/>
User Authentication	<p>Select the user authentication to use:</p> <ul style="list-style-type: none"> <li>• Password - see next row for information.</li> <li>• Certificate - If you select Certificate, select the identity certificate to be used as the account credential.</li> </ul>
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
Role	Specify the Juniper user role to use as a restriction.
Realm	Specify the Juniper realm to use as a restriction.
VPN On Demand	<p>On-Demand VPN is supported for Android only if the Samsung Knox and Per-app VPN checkboxes are selected. On Demand VPN for Android means that the Juniper SSL VPN connection is activated only when an app associated with it is launched. When all apps associated with this VPN connection type are stopped, VPN is disconnected.</p> <p>Select to enable VPN On Demand.</p>
Per-app VPN	<p>Select <b>Yes</b> to create a per-app VPN setting. An additional license may be required for this feature.</p> <p>The Provider Type field displays.</p> <p>You cannot delete a per-app VPN setting that is being used by an app. Remove the per-app VPN setting from the app before you delete the setting.</p> <p>You can enable per-app VPN for an app when you:</p>

TABLE 3. PROXY - AUTOMATIC SETTINGS (CONT.)

Item	Description
	<ul style="list-style-type: none"> <li>• add the app in the App Catalog.</li> <li>• edit an in-house app or an App Store app in the App Catalog.</li> </ul> <hr/> <p> When multiple labels are assigned to associate the selected VPN configurations in the Per-App VPN section, then VPN prioritization will happen in the order of the selected list.</p> <hr/> <p>See the <i>Core Apps@Work Guide</i> for information about how to add or edit apps.</p>
Provider Type	This setting applies to iOS and macOS devices only.

Continue to "[Custom Data](#)" below.

## Custom Data

- **Add+** - Click to add a new key / value pair.
- **Key / Value** - Enter the Key / value pairs necessary to configure the VPN setting. The app creator should provide the necessary key / value pairs.

## L2TP

This VPN connection type is supported on iOS, macOS, and Windows devices. It is not supported on Android devices.

## Tunnel (iOS and macOS)

This VPN connection type is supported on iOS and macOS devices only. It is not supported on Windows or Android devices.

## Tunnel (Android)

This VPN connection type is supported on Android devices only. It is not supported on iOS, macOS and Windows devices.

Use this setting to configure Tunnel VPN for Android. For information on how to set up and configure Tunnel VPN for Tunnel for Android, see the *Tunnel for Android Guide* on the [Ivanti Product Documentation page](#). These instructions also include how to configure VPN chaining with Tunnel. VPN chaining is the nesting of a VPN tunnel in another VPN tunnel for added security.



## Tunnel (Samsung Knox Workspace)

This VPN connection type is supported on Android devices only. It is not supported on iOS, macOS and Windows devices.

Use this setting to configure Tunnel VPN for Samsung Knox Workspace. For information on how to set up and configure Tunnel VPN for Tunnel for Samsung Knox, see the *Tunnel for Android Guide* on the [Ivanti Product Documentation page](#). These instructions also include how to configure VPN chaining with Tunnel. VPN chaining is the nesting of a VPN tunnel in another VPN tunnel for added security.

## Tunnel (Windows)

This VPN connection type is supported on Windows devices only. It is not supported on iOS, macOS and Android devices.

## NetMotion Mobility VPN (iOS)

This VPN connection type is supported on iOS devices. It is not supported on macOS, Android and Windows devices.

## OpenVPN

This VPN connection type is supported on Android devices. It is not supported on iOS, macOS, and Windows devices.

Use the OpenVPN connection type to configure Samsung “OpenVPN net.openvpn.knox.connect” for Samsung Knox devices. This configuration is available only to limited customers as approved by Samsung. **Contact Samsung to get the correct OpenVPN package.** It is supported only on devices with the Samsung Knox option selected in the VPN setting.

Note The Following:

- Open VPN is NOT supported with a third-party Open VPN vendor that is not Samsung.
- Open VPN is supported with Samsung Knox without using VPN chaining.

Use the following guidelines to configure OpenVPN:

TABLE 1. OPENVPN SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.
Description	<b>Provide a description that clarifies the purpose of these settings.</b>
Channel	For macOS only. Select one of the following distribution options:

TABLE 1. OPENVPN SETTINGS (CONT.)


Item	Description
	<ul style="list-style-type: none"> <li>• Device channel - the configuration is effective for all users on a device. This is the typical option.</li> <li>• User channel - the configuration is effective only for the currently registered user on a device.</li> </ul>
Connection Type	<p>Select <b>OpenVPN</b>.</p> <p>Only fields relevant to OpenVPN are displayed.</p>
Samsung Knox	<p>Always select this option. A Samsung Knox license is required.</p> <p>A VPN setting with this option selected cannot be successfully applied to a non-Samsung Android device.</p> <p>This setting is ignored on non-Android devices.</p>
Deploy inside Knox Workspace	<p>Select this option to deploy the VPN client app inside the Knox Workspace (container). Deploying the app inside the container means that the Knox security platform protects the app and its data.</p> <p>This option is available only if you select the <b>Samsung Knox</b> option.</p> <p>See <a href="#">"Configuring VPN modes when VPN client is outside the Knox container" on page 294</a></p>
Package Name	<p>Provide the Android package name of the OpenVPN client app: net.openvpn.knox.connect</p>
Server	<p>Enter the IP address, hostname or URL for the VPN server.</p>
Username	<p>Specify the user name to use. The default value is \$USERID\$. Use this field to specify an alternate format, such as:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as the following:</p> <ul style="list-style-type: none"> <li>• \$USERID\$: \$EMAIL\$</li> <li>• \$USERID\$_\$EMAIL\$</li> </ul> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p> <hr/> <p> Some enterprises have a strong preference concerning which identifier is exposed.</p>

TABLE 1. OPENVPN SETTINGS (CONT.)

Item	Description
User Authentication	<p>Click the radio button for <b>Password</b> or <b>Certificate</b> to specify user authentication type.</p> <p>If you select <b>Password</b>, specify the password to use. The default value is \$PASSWORD\$. You can specify a custom format, for example, \$PASSWORD\$_\$USERID\$. Other password formats available are:</p> <p>If you select <b>Certificate</b>, specify Password, and then provide the two other settings added to the page:</p> <ul style="list-style-type: none"> <li>Identity Certificate (required): Enter the identity certificate number.</li> <li>CA Certificate (optional): Select the CA Certificate from the list of available certificates.</li> </ul>
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
VPN Chaining	Select <b>Enable</b> to set up VPN chaining with Tunnel VPN. See "Configuring VPN chaining" in <i>Tunnel for Android Guide</i> .
Per-app VPN	When selecting this option, a Samsung Knox license is required.
Proxy Server Port	Enter the port number for the connection. (Required)
Protocol	Select from drop-down.
Cipher	Select from drop-down.
Packet Auth Digest	Select from drop-down.

## Palo Alto Networks GlobalProtect

This VPN connection type is supported on iOS, macOS, and Android devices. It is not supported on Windows devices.

Use the following guidelines to configure the Palo Alto Networks GlobalProtect VPN connection type.

- ["Proxy - None \(default\)" below](#)
- ["Proxy - Manual " on page 270](#)
- ["Proxy - Automatic" on page 273](#)

Within these selections, you may make settings for:

- ["On Demand Rules" on page 275](#)

## Proxy - None (default)


TABLE 1. PROXY - NONE SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.
Description	Provide a description that clarifies the purpose of these settings.
Channel	For macOS only. Select one of the following distribution options: <ul style="list-style-type: none"> <li>• Device channel - the configuration is effective for all users on a device. This is the typical option.</li> <li>• User channel - the configuration is effective only for the currently registered user on a device.</li> </ul>
Connection Type	Select <b>Palo Alto Networks GlobalProtect</b> .
Server	Enter the IP address, hostname, or URL for the VPN server.
Proxy	<b>None</b> is the default setting. To configure a <b>Manual</b> or <b>Automatic</b> proxy, go to <a href="#">"Proxy - Manual " on page 270</a> or <a href="#">"Proxy - Automatic" on page 273</a> .
Username	Specify the user name to use (required.) The default value is \$USERID\$. Include at least one of the following variables: \$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$ You can use combinations such as the following: <ul style="list-style-type: none"> <li>• \$USERID\$: \$EMAIL\$</li> <li>• \$USERID_\$EMAIL\$</li> </ul> Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.
User Authentication	Select the user authentication to use:

TABLE 1. PROXY - NONE SETTINGS (CONT.)

Item	Description
	<ul style="list-style-type: none"> <li>• Password - see next row for information.</li> <li>• Certificate - If you select Certificate, select the identity certificate to be used as the account credential.</li> </ul> <p>If you select Certificate, and extended authentication (EAP) is not used, this certificate will be sent out for IKE client authentication. If extended authentication is used, this certificate can be used for EAP-TLS.</p>
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
VPN On Demand	<p>This setting applies to iOS and macOS devices only. Select to enable VPN On Demand.</p> <p>The <a href="#">"On Demand Rules" on page 275</a> field displays.</p> <p>On Demand rules are associated with an array of dictionaries that define the network match criteria identifying a particular network location.</p> <p>VPN On Demand matches the dictionaries in the On Demand Rules against properties of your current network connection to determine whether domain-based rules should be used in determining whether to connect, then handles the connection as follows:</p> <ul style="list-style-type: none"> <li>• If domain-based matching is enabled for a matching On Demand Rule dictionary, then for each dictionary in that dictionary's connection evaluation array, VPN On Demand compares the requested domain against the domains listed in the Domains array.</li> <li>• If domain-based matching is not enabled, the specified behavior (Connect, Disconnect, Allow, or Ignore) is used if the dictionary otherwise matches.</li> </ul> <p>VPN On Demand rules are applied when the device's primary network interface changes, for example when the device switches to a different Wi-Fi network.</p> <p>Note the following:</p>

TABLE 1. PROXY - NONE SETTINGS (CONT.)

Item	Description
	<ul style="list-style-type: none"> <li>A matching rule is not required. The Default Rule is applied if a matching rule is not defined.</li> <li>If you select Evaluate Connection, a matching rule is not required.</li> <li>You can create up to 10 On Demand matching rules.</li> <li>For each matching rule you can create up to 50 Type and Value pairs.</li> <li>For instructions, see <a href="#">"On Demand Rules" on page 275</a>.</li> </ul>
Per-App VPN	<p>This setting applies to iOS and macOS devices only.</p> <p>Per-app VPN is supported on iOS devices version 9.0 or supported newer versions.</p> <p>Select <b>Yes</b> to create a per-app VPN setting. An additional license may be required for this setting.</p> <p>The Provider Type field displays.</p> <p>You cannot delete a per-app VPN setting that is being used by an app. Remove the per-app VPN setting from the app before you delete the setting.</p> <p>You can enable per-app VPN for an app when you:</p> <ul style="list-style-type: none"> <li>add the app in the App Catalog.</li> <li>edit an in-house app or an App Store app in the App Catalog.</li> </ul> <hr/> <p> When multiple labels are assigned to associate the selected VPN configurations in the Per-App VPN section, then VPN prioritization will happen in the order of the selected list.</p> <hr/> <p>See the <i>Core Apps@Work Guide</i> for information about how to add or edit apps.</p>
Provider Type	<p>If Per-App VPN is set to Yes, define whether the per-app VPN service will tunnel traffic at the application layer (<b>app-proxy</b>) or the IP layer (<b>packet-tunnel</b>).</p> <p>Select <b>app-proxy</b> (default) or <b>packet-tunnel</b>.</p>

## Proxy - Manual

If you select **Manual**, you must specify the proxy server, port number. and proxy domain information.

TABLE 2. PROXY - MANUAL SETTINGS


Item	Description
Proxy Server	Enter the name for the proxy server.
Proxy Server Port	Enter the port number for the proxy server. Type - Select <b>Static</b> or <b>Variable</b> for the type of authentication to be used for the proxy server.
Proxy Server User Name	If the authentication type is <b>Static</b> , enter the username for the proxy server. If the authentication type is <b>Variable</b> , the default variable selected is \$USERID\$.
Proxy Server Password	If the authentication type is <b>Static</b> , enter the password for the proxy server. Confirm the password in the field below. If the authentication type is <b>Variable</b> , the default variable selected is \$PASSWORD\$.
Proxy Domains (iOS only)	This setting applies to iOS and macOS devices only. The VPN will only proxy for the domain and domain suffixes specified here (.com and .org are examples of top-level domain suffixes). Domain suffixes can be used to match multiple domains. For example, .com would include all .com domains, and example.com would include all domains ending in example.com, such as pages.example.com and mysite.example.com. Wildcards are not supported. Click <b>Add+</b> to add a domain.
Username	Specify the user name to use (required.) The default value is \$USERID\$. Include at least one of the following variables: \$USERID\$, \$EMAIL\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$NULL\$ You can use combinations such as the following: <ul style="list-style-type: none"> <li>• \$USERID\$: \$EMAIL\$</li> <li>• \$USERID\$_ \$EMAIL\$</li> </ul> Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.
User Authentication	Select the user authentication to use: <ul style="list-style-type: none"> <li>• Password - see next row for information.</li> <li>• Certificate - If you select Certificate, select the identity certificate to be used as the account credential.</li> </ul>

TABLE 2. PROXY - MANUAL SETTINGS (CONT.)

Item	Description
	<p>If you select Certificate, and extended authentication (EAP) is not used, this certificate will be sent out for IKE client authentication. If extended authentication is used, this certificate can be used for EAP-TLS.</p>
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL:\$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
VPN On Demand	<p>This setting is not available on Android devices. Select to enable VPN On Demand.</p> <p>The <a href="#">"On Demand Rules" on page 275</a> field displays.</p> <p>On Demand rules are associated with an array of dictionaries that define the network match criteria identifying a particular network location.</p> <p>VPN On Demand matches the dictionaries in the On Demand Rules against properties of your current network connection to determine whether domain-based rules should be used in determining whether to connect, then handles the connection as follows:</p> <ul style="list-style-type: none"> <li>• If domain-based matching is enabled for a matching On Demand Rule dictionary, then for each dictionary in that dictionary's connection evaluation array, VPN On Demand compares the requested domain against the domains listed in the Domains array.</li> <li>• If domain-based matching is not enabled, the specified behavior (Connect, Disconnect, Allow, or Ignore) is used if the dictionary otherwise matches.</li> </ul> <p>VPN On Demand rules are applied when the device's primary network interface changes, for example when the device switches to a different Wi-Fi network.</p> <p>Note the following:</p> <ul style="list-style-type: none"> <li>• A matching rule is not required. The Default Rule is applied if a matching rule is not defined.</li> <li>• If you select Evaluate Connection, a matching rule is not required.</li> </ul>



TABLE 2. PROXY - MANUAL SETTINGS (CONT.)

Item	Description
	<ul style="list-style-type: none"> <li>You can create up to 10 On Demand matching rules.</li> <li>For each matching rule you can create up to 50 Type and Value pairs.</li> <li>For instructions, see <a href="#">"On Demand Rules" on page 275</a>.</li> </ul>
Per-App VPN	<p>This setting applies to iOS and macOS devices only.</p> <p>Per-app VPN is supported on iOS devices version 9.0 or supported newer versions.</p> <p>The Provider Type field displays.</p> <hr/> <div>  <p>When multiple labels are assigned to associate the selected VPN configurations in the Per-App VPN section, then VPN prioritization will happen in the order of the selected list.</p> </div> <hr/>
Provider Type	

## Proxy - Automatic

If you selected an Automatic proxy, you must specify the proxy server URL and proxy domain(s).


TABLE 3. PROXY - AUTOMATIC SETTINGS

Item	Description
Proxy Server URL	<p>Enter the URL for the proxy server.</p> <p>Enter the URL of the location of the proxy auto-configuration file.</p>
Proxy Domains (iOS only)	<p>This setting applies to iOS and macOS devices only. The VPN will only proxy for the domain and domain suffixes specified here (.com and .org are examples of top-level domain suffixes). Domain suffixes can be used to match multiple domains. For example, .com would include all .com domains, and example.com would include all domains ending in example.com, such as pages.example.com and mysite.example.com. Wildcards are not supported.</p> <p>Click <b>Add+</b> to add a domain.</p>
Username	<p>Specify the user name to use (required.) The default value is \$USERID\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$NULL\$</p> <p>You can use combinations such as the following:</p>

TABLE 3. PROXY - AUTOMATIC SETTINGS (CONT.)

Item	Description
	<ul style="list-style-type: none"> <li>• \$USERID\$: \$EMAIL\$</li> <li>• \$USERID\$_\$EMAIL\$</li> </ul> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p>
User Authentication	<p>Select the user authentication to use:</p> <ul style="list-style-type: none"> <li>• Password - see next row for information.</li> <li>• Certificate - If you select Certificate, select the identity certificate to be used as the account credential.</li> </ul> <p>If you select Certificate, and extended authentication (EAP) is not used, this certificate will be sent out for IKE client authentication. If extended authentication is used, this certificate can be used for EAP-TLS.</p>
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
VPN On Demand	<p>This setting is not available on Android devices. Select to enable VPN On Demand.</p> <p>The <a href="#">"On Demand Rules" on the next page</a> field displays.</p> <p>On Demand rules are associated with an array of dictionaries that define the network match criteria identifying a particular network location.</p> <p>VPN On Demand matches the dictionaries in the On Demand Rules against properties of your current network connection to determine whether domain-based rules should be used in determining whether to connect, then handles the connection as follows:</p> <ul style="list-style-type: none"> <li>• If domain-based matching is enabled for a matching On Demand Rule dictionary, then for each dictionary in that dictionary's connection evaluation array, VPN On Demand compares the requested domain against the domains listed in the Domains array.</li> </ul>

TABLE 3. PROXY - AUTOMATIC SETTINGS (CONT.)

Item	Description
	<ul style="list-style-type: none"> <li>If domain-based matching is not enabled, the specified behavior (Connect, Disconnect, Allow, or Ignore) is used if the dictionary otherwise matches.</li> </ul> <p>VPN On Demand rules are applied when the device's primary network interface changes, for example when the device switches to a different Wi-Fi network.</p> <p>Note the following:</p> <ul style="list-style-type: none"> <li>A matching rule is not required. The Default Rule is applied if a matching rule is not defined.</li> <li>If you select Evaluate Connection, a matching rule is not required.</li> <li>You can create up to 10 On Demand matching rules.</li> <li>For each matching rule you can create up to 50 Type and Value pairs.</li> <li>For instructions, see <a href="#">"On Demand Rules" below</a>.</li> </ul>
Per-App VPN	<p>This setting applies to iOS and macOS devices only.</p> <p>Per-app VPN is supported on iOS devices version 9.0 or supported newer versions.</p> <hr/> <p> When multiple labels are assigned to associate the selected VPN configurations in the Per-App VPN section, then VPN prioritization will happen in the order of the selected list.</p> <hr/>
Provider Type	

## On Demand Rules

Applicable to: iOS 7 and later

Whenever a network change is detected, the VPN On Demand service compares the newly connected network against the match network criteria specified in each set of rules (in order) to determine whether VPN On Demand should be allowed or not on the newly-joined network.

Rule sets are checked sequentially, beginning with the first. A rule set matches the current network only if all of the specified policies in that rule set match.

If a rule set matches the current network, a server probe is sent if a URL is specified in the profile. VPN then acts according to the policy defined in the dictionary (for example, Allow, Ignore, Evaluate Connection, Connect, or Disconnect).

Define sets of evaluation rules for each action that can be taken by VPN On Demand: **Allow**, **Connect**, **Disconnect**, **Evaluate Connection**, and **Ignore**. You can define more than one set of rules for each type of action that can be taken. For each set of evaluation rules, the number of rules defined for that set is indicated in the No. of Rules column.

▼ On Demand Rules (iOS7 and later)

ACTION	NO. OF RULES		
Connect	1		
Disconnect	1		
Ignore	1		

Add+

Procedure

- 1. Click **Add+** to add a new set of On Demand evaluation rules.

A rule creation dialog box opens.

On Demand Action: Connect ▼

▼ Matching Rules

TYPE	VALUE	DESCRIPTION	
DNS Domain	mydomain.example.com		
Interface Type	Cellular		

Add+

Cancel OK

2. From the **On Demand Action** drop-down list, select the action you want to be taken when the rules you create below are matched.

The following actions are available:

- **Allow:** (Deprecated by iOS.) Allow VPN On Demand to connect if triggered.
- **Connect:** Unconditionally initiate a VPN connection on the next network attempt.
- **Disconnect:** Tear down the VPN connection and do not reconnect on demand as long as this dictionary matches.
- **Evaluate Connection:** Evaluate the action parameters for each connection attempt.
- **Ignore:** Leave any existing VPN connection up, but do not reconnect on demand as long as this dictionary matches.

3. Matching Rules - For each rule you create, enter one of the following types:

- **DNS domain:** This rule matches if any of the domain names in the specified list matches any domain in the device's search domains list. A wildcard '\*' prefix is supported. For example, \*.example.com matches against either mydomain.example.com or yourdomain.example.com.
- **DNS Server Address:** This rule matches if any of the network's specified DNS servers match any entry in the list. Matching with a single wildcard is supported. For example, 17.\* matches any DNS server in the class A 17 subnet.
- **SSID:** A list of SSIDs to match against the current network. If the network is not a Wi-Fi network, or if the SSID does not appear in this list, the match fails. Omit this rule and the corresponding list to match against any SSID.
- **Interface Type:** If specified, this rule matches only if the primary network interface hardware matches the specified interface type. Choose **Ethernet**, **Wifi**, or **Cellular**.
- **URL String Probe:** A URL to probe. If this URL is successfully fetched without redirection (returning a 200 HTTP status code), this rule matches.

4. Enter a value for each rule type and an optional description.

5. After adding your rules, click **OK**.

### Default Rules

Define a default rule that simply specifies a default VPN On Demand action in case none of the On Demand rules match, or if no On Demand rules have been defined.

### Procedure

1. From the **On Demand Action** drop-down list, select the action you want to be taken by default, if none of the rules match or none are defined.

2. Click Add+ to add a default rule.

The following actions are available:

- **Allow:** (Deprecated by iOS.) Allow VPN On Demand to connect if triggered.
- **Connect:** Unconditionally initiate a VPN connection on the next network attempt.
- **Disconnect:** Tear down the VPN connection and do not reconnect on demand as long as this dictionary matches.
- **Evaluate Connection:** Evaluate the action parameters for each connection attempt.
- **Ignore:** Leave any existing VPN connection up, but do not reconnect on demand as long as this dictionary matches.

If you select **Evaluate Connection**, a domain actions table displays:

The screenshot shows a window titled "Default Rule". At the top, "On Demand Action:" is set to "Evaluate Connection" with a dropdown arrow and an information icon. Below this is a table with two columns: "DOMAIN ACTION" and "PARAMETERS". The table is currently empty, displaying "No records to display". At the bottom left of the table area is a blue "Add+" button.

3. Click **Add+** to add a domain action.

The **Action Parameters** dialog box opens.

The screenshot shows a dialog box titled "Action Parameters" with a close button (X) in the top right corner. At the top, "Domain Action" is set to "Connect if needed" with a dropdown arrow. Below this is a table with three columns: "EVALUATION TYPE", "VALUE", and "DESCRIPTION". The table contains three rows: "Domain" with value "mydomain.example.com", "Required DNS Server", and "Required URL Probe". Each row has a small "X" icon in the rightmost column. At the bottom left is a blue "Add+" button. At the bottom right are "Cancel" and "OK" buttons.

4. From the **Domain Action** drop-down list, select one of the following actions to be taken for the domains listed in the table:
  - **Connect if needed:** The specified domains should trigger a VPN connection attempt if domain name resolution fails, such as when the DNS server indicates that it cannot resolve the domain, responds with a redirection to a different server, or fails to respond (timeout).
  - **Never connect:** The specified domains should never trigger a VPN connection attempt.
5. Click **Add+** to include any of the following evaluation types:
  - **Domain:** The domains for which this evaluation applies.
  - **Required DNS Server:** IP addresses of DNS servers to be used for resolving the specified domains. These servers need not be part of the device's current network configuration. If these DNS servers are not reachable, a VPN connection is established in response. These DNS servers should be either internal DNS servers or trusted external DNS servers. *You can only configure required DNS server evaluation types for the **Connect if needed** domain action.*
  - **Required URL Probe:** An HTTP or HTTPS (preferred) URL to probe, using a GET request. If no HTTP response code is received from the server, a VPN connection is established in response. *You can only configure required URL probe evaluation types for the **Connect if needed** domain action.*
6. Add a value and optional description for each entry.
7. Click **OK** to save your domain action parameters.

## PPTP

This VPN connection type is supported on iOS, macOS, Android, and Windows devices.

Use the following guidelines to configure the PPTP VPN connection type.

- ["Proxy - None \(default\)" below](#)
- ["Proxy - Manual" on page 281](#)
- ["Proxy - Automatic" on page 283](#)

### Proxy - None (default)

Use the following guidelines to configure a PPTP VPN without a proxy.

TABLE 1. PROXY - NONE (DEFAULT) SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.

TABLE 1. PROXY - NONE (DEFAULT) SETTINGS (CONT.)


Item	Description
Description	Provide a description that clarifies the purpose of these settings.
Channel	<p>For macOS only. Select one of the following distribution options:</p> <ul style="list-style-type: none"> <li>• Device channel - the configuration is effective for all users on a device. This is the typical option.</li> <li>• User channel - the configuration is effective only for the currently registered user on a device.</li> </ul>
Connection Type	Select <b>PPTP</b> .
Server	Enter the IP address, hostname, or URL for the VPN server.
Proxy	<b>None</b> is the default setting. To configure a Manual or Automatic proxy, go to <a href="#">"Proxy - Manual" on the next page</a> or <a href="#">"Proxy - Automatic" on page 283</a>
Encryption Level	Select <b>None</b> , <b>Automatic</b> or <b>Maximum</b> (128 bit).
Domain	Specify the network domain.
Send all Traffic	Selecting this option protects data from being compromised, particularly on public networks.
User Name	<p>Specify the user name to use (required.) The default value is \$USERID\$. Use this field to specify an alternate format, such as:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as the following:</p> <ul style="list-style-type: none"> <li>• \$USERID\$: \$EMAIL\$</li> <li>• \$USERID_\$EMAIL\$</li> </ul> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p> <hr/> <p> Some enterprises have a strong preference concerning which identifier is exposed.</p> <hr/>
User Authentication	Select the authentication method to use: <b>Password</b> or <b>RSA SecureID</b> .
Password	Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:



TABLE 1. PROXY - NONE (DEFAULT) SETTINGS (CONT.)

Item	Description
	<p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank.</p> <p>Users will need to fill in the relevant password.</p>


## Proxy - Manual

Use the following guidelines to configure a PPTP VPN with a manual proxy.

TABLE 2. PROXY - MANUAL SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.
Description	Provide a description that clarifies the purpose of these settings.
Channel	<p>For macOS only. Select one of the following distribution options:</p> <ul style="list-style-type: none"> <li>• Device channel - the configuration is effective for all users on a device. This is the typical option.</li> <li>• User channel - the configuration is effective only for the currently registered user on a device.</li> </ul>
Connection Type	Select <b>PPTP</b> .
Server	Enter the IP address, hostname, or URL for the VPN server.
Proxy	Select <b>Manual</b> . To configure an automatic proxy, go to <a href="#">"Proxy - Automatic" on page 283</a>
Proxy Server	Enter the name for the proxy server.
Proxy Server Port	Enter the port number for the proxy server.
Type	Select <b>Static</b> or <b>Variable</b> for the type of authentication to be used for the proxy server.
Proxy Server User Name	<p>If the authentication type is <b>Static</b>, enter the username for the proxy server.</p> <p>If the authentication type is <b>Variable</b>, the default variable selected is \$USERID\$.</p>

TABLE 2. PROXY - MANUAL SETTINGS (CONT.)

Item	Description
Proxy Server Password	<p>If the authentication type is <b>Static</b>, enter the password for the proxy server. Confirm the password in the field below.</p> <p>If the authentication type is <b>Variable</b>, the default variable selected is \$PASSWORD\$.</p>
Proxy Domains (iOS only)	This setting does not apply to Android devices.
Encryption Level	Select <b>None</b> , <b>Automatic</b> or <b>Maximum</b> (128 bit).
Domain	Specify the network domain.
Send all Traffic	Selecting this option protects data from being compromised, particularly on public networks.
Username	<p>Specify the user name to use (required.) The default value is \$USERID\$. Use this field to specify an alternate format, such as:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as the following:</p> <ul style="list-style-type: none"> <li>• \$USERID\$: \$EMAIL\$</li> <li>• \$USERID\$_\$EMAIL\$</li> </ul> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p> <hr/> <p> Some enterprises have a strong preference concerning which identifier is exposed.</p> <hr/>
User Authentication	Select the authentication method to use: <b>Password</b> or <b>RSA SecureID</b> .
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>


## Proxy - Automatic

Use the following guidelines to configure a PPTP VPN with an automatic proxy.

TABLE 3. PROXY - AUTOMATIC SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.
Description	Provide a description that clarifies the purpose of these settings.
Channel	For macOS only. Select one of the following distribution options: <ul style="list-style-type: none"><li>• Device channel - the configuration is effective for all users on a device. This is the typical option.</li><li>• User channel - the configuration is effective only for the currently registered user on a device.</li></ul>
Connection Type	Select <b>PPTP</b> .
Server	Enter the IP address, hostname, or URL for the VPN server.
Proxy	Select <b>Automatic</b> . To configure a manual proxy, go to <a href="#">"Proxy - Manual" on page 281</a> .
Proxy Server URL	Enter the URL for the proxy server. Enter the URL of the location of the proxy auto-configuration file.
Proxy Domains (iOS only)	This setting does not apply to Android devices.
Encryption Level	Select <b>None</b> , <b>Automatic</b> or <b>Maximum</b> (128 bit).
Domain	Specify the network domain.
Send all Traffic	Selecting this option protects data from being compromised, particularly on public networks.
Username	<p>Specify the user name to use (required.) The default value is \$USERID\$. Use this field to specify an alternate format, such as:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as the following:</p> <ul style="list-style-type: none"><li>• \$USERID\$: \$EMAIL\$</li><li>• \$USERID\$_\$EMAIL\$</li></ul>

TABLE 3. PROXY - AUTOMATIC SETTINGS (CONT.)

Item	Description
	<p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p> <hr/> <p> Some enterprises have a strong preference concerning which identifier is exposed.</p> <hr/>
User Authentication	Select the authentication method to use: <b>Password</b> or <b>RSA SecureID</b> .
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>

## Pulse Secure SSL

This VPN connection type is supported on iOS, macOS, Android, and Windows devices.

 Ivanti recommends using the Pulse Secure SSL connection type instead of Juniper SSL.

Use the following guidelines to configure Pulse Secure SSL VPN.

- ["Proxy - None \(default\)" below](#)
- ["Proxy - Manual" on page 286](#)
- ["Proxy - Automatic" on page 289](#)

Within these selections, you may make settings for:

- ["Custom Data" on page 291](#)

### Proxy - None (default)

Use the following guidelines to configure a Pulse Secure SSL VPN without a proxy.

TABLE 1. PROXY - NONE (DEFAULT) SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.

TABLE 1. PROXY - NONE (DEFAULT) SETTINGS (CONT.)

Item	Description
Description	Provide a description that clarifies the purpose of these settings.
Channel	<p>For macOS only. Select one of the following distribution options:</p> <ul style="list-style-type: none"> <li>• Device channel - the configuration is effective for all users on a device. This is the typical option.</li> <li>• User channel - the configuration is effective only for the currently registered user on a device.</li> </ul>
Connection Type	Select <b>Pulse Secure SSL</b> .
Samsung Knox	<p>Select this option to use per-app VPN (either inside or outside the Knox Workspace) or per-container VPN. A Samsung Knox license is required.</p> <p>A VPN setting with this option selected cannot be successfully applied to a non-Samsung Android device.</p> <p>This setting is ignored on non-Android devices.</p>
Deploy inside Knox Workspace	<p>Select this option to deploy the VPN client app inside the Knox Workspace (container). Deploying the app inside the container means that the Knox security platform protects the app and its data.</p> <p>This option is available only if you select the <b>Samsung Knox</b> option.</p> <p>See:</p> <ul style="list-style-type: none"> <li>• <a href="#">"Configuring VPN modes when VPN client is outside the Knox container" on page 294</a></li> </ul>
Server	Enter the IP address, hostname, or URL for the VPN server.
Proxy	This setting is not supported on Android devices.
Username	<p>Enter a value for the username (required.) The default value is \$USERID\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as the following:</p> <ul style="list-style-type: none"> <li>• \$USERID\$: \$EMAIL\$</li> <li>• \$USERID_\$EMAIL\$</li> </ul> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p>

TABLE 1. PROXY - NONE (DEFAULT) SETTINGS (CONT.)

Item	Description
User Authentication	<p>Select the user authentication to use:</p> <ul style="list-style-type: none"> <li>Password - see next row for information.</li> <li>Certificate - If you select Certificate, select the identity certificate to be used as the account credential.</li> </ul> <p>If you select Certificate, and extended authentication (EAP) is not used, this certificate will be sent out for IKE client authentication. If extended authentication is used, this certificate can be used for EAP-TLS.</p>
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Use this field to specify a custom format, such as \$PASSWORD\$_\$USERID\$.</p> <p>Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
Role	Specify the Pulse user role to use as a restriction.
Realm	Specify the Pulse realm to use as a restriction.
VPN On Demand	If the Samsung Knox and per-App VPN fields are both selected, then select this option to use VPN On Demand.
Per-app VPN	When selecting this option, a Samsung Knox license is required.
Provider Type	This setting applies to iOS and macOS devices only.

Continue with ["Custom Data"](#) on page 291.

## Proxy - Manual

Use the following guidelines to configure a Pulse Secure SSL VPN with a manual proxy.

TABLE 2. PROXY - MANUAL SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.
Description	Provide a description that clarifies the purpose of these settings.

TABLE 2. PROXY - MANUAL SETTINGS (CONT.)


Item	Description
Channel	<p>For macOS only. Select one of the following distribution options:</p> <ul style="list-style-type: none"> <li>• Device channel - the configuration is effective for all users on a device. This is the typical option.</li> <li>• User channel - the configuration is effective only for the currently registered user on a device.</li> </ul>
Connection Type	Select <b>Pulse Secure SSL</b> .
Samsung Knox	<p>Select this option to use per-app VPN (either inside or outside the Knox Workspace) or per-container VPN. A Samsung Knox license is required.</p> <p>A VPN setting with this option selected cannot be successfully applied to a non-Samsung Android device.</p> <p>This setting is ignored on non-Android devices.</p>
Deploy inside Knox Workspace	<p>Select this option to deploy the VPN client app inside the Knox Workspace (container). Deploying the app inside the container means that the Knox security platform protects the app and its data.</p> <p>This option is available only if you select the <b>Samsung Knox</b> option.</p> <p>See:</p> <ul style="list-style-type: none"> <li>• <a href="#">"Configuring VPN modes when VPN client is outside the Knox container" on page 294</a></li> </ul>
Server	Enter the IP address, hostname, or URL for the VPN server.
Proxy	This setting is not supported on Android devices.
Proxy Server	This setting is not supported on Android devices.
Proxy Server Port	This setting is not supported on Android devices.
Type	This setting is not supported on Android devices.
Proxy Server User Name	This setting is not supported on Android devices.
Proxy Server Password	This setting is not supported on Android devices.
Proxy Domains (iOS only)	This field applies to iOS and macOS devices only.
Username	<p>Enter a value for the username (required.) The default value is \$USERID\$.</p> <p>Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p>

TABLE 2. PROXY - MANUAL SETTINGS (CONT.)

Item	Description
	<p>You can use combinations such as the following:</p> <ul style="list-style-type: none"> <li>• \$USERID\$: \$EMAIL\$</li> <li>• \$USERID\$_ \$EMAIL\$</li> </ul> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p>
User Authentication	<p>Select the user authentication to use:</p> <ul style="list-style-type: none"> <li>• Password - see next row for information.</li> <li>• Certificate - If you select Certificate, select the identity certificate to be used as the account credential.</li> </ul> <p>If you select Certificate, and extended authentication (EAP) is not used, this certificate will be sent out for IKE client authentication. If extended authentication is used, this certificate can be used for EAP-TLS.</p>
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Use this field to specify a custom format, such as \$PASSWORD\$_ \$USERID\$.</p> <p>Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
Role	Specify the Pulse user role to use as a restriction.
Realm	Specify the Pulse realm to use as a restriction.
VPN On Demand	If the Samsung Knox and per-App VPN fields are both selected, then select this option to use VPN On Demand.
Per-app VPN	<p>When selecting this option, a Samsung Knox license is required.</p> <p>Select <b>Yes</b> to create a per-app VPN setting.</p> <p>The "<a href="#">Pulse Secure SSL</a>" on page 284 section displays.</p> <p>An additional license may be required for this feature.</p>



TABLE 2. PROXY - MANUAL SETTINGS (CONT.)

Item	Description
	<p>You cannot delete a per-app VPN setting that is being used by an app. Remove the per-app VPN setting from the app before you delete the setting.</p> <p>You can enable per-app VPN for an app when you:</p> <ul style="list-style-type: none"> <li>• add the app in the App Catalog.</li> <li>• edit an in-house app or an App Store app in the App Catalog.</li> </ul> <hr/> <p> When multiple labels are assigned to associate the selected VPN configurations in the Per-App VPN section, then VPN prioritization will happen in the order of the selected list.</p> <hr/> <p>See the <i>Core Apps@Work Guide</i> for information about how to add or edit apps.</p>
Provider Type	This setting applies to iOS and macOS devices only.

Continue with "Custom Data" on page 291.

## Proxy - Automatic

Use the following guidelines to configure a Pulse Secure SSL VPN with an automatic proxy.

TABLE 3. PROXY - AUTOMATIC SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.
Description	Provide a description that clarifies the purpose of these settings.
Channel	<p>For macOS only. Select one of the following distribution options:</p> <ul style="list-style-type: none"> <li>• Device channel - the configuration is effective for all users on a device. This is the typical option.</li> <li>• User channel - the configuration is effective only for the currently registered user on a device.</li> </ul>
Connection Type	Select <b>Pulse Secure SSL</b> .
Samsung Knox	<p>Select this option to use per-app VPN (either inside or outside the Knox Workspace) or per-container VPN. A Samsung Knox license is required.</p> <p>A VPN setting with this option selected cannot be successfully applied to a non-Samsung Android device.</p>

TABLE 3. PROXY - AUTOMATIC SETTINGS (CONT.)

Item	Description
	This setting is ignored on non-Android devices.
Deploy inside Knox Workspace	<p>Select this option to deploy the VPN client app inside the Knox Workspace (container). Deploying the app inside the container means that the Knox security platform protects the app and its data.</p> <p>This option is available only if you select the <b>Samsung Knox</b> option.</p> <p>See:</p> <ul style="list-style-type: none"> <li>"Configuring VPN modes when VPN client is outside the Knox container" on page 294</li> </ul>
Server	Enter the IP address, hostname, or URL for the VPN server.
Proxy	This setting is not supported on Android devices.
Proxy Server URL	This setting is not supported on Android devices.
Proxy Domains (iOS only)	This setting applies to iOS and macOS devices only.
Username	<p>Enter a value for the username (required.) The default value is \$USERID\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as the following:</p> <ul style="list-style-type: none"> <li>\$USERID\$: \$EMAIL\$</li> <li>\$USERID\$_\$EMAIL\$</li> </ul> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p>
User Authentication	<p>Select the user authentication to use:</p> <ul style="list-style-type: none"> <li>Password - see next row for information.</li> <li>Certificate - If you select Certificate, select the identity certificate to be used as the account credential.</li> </ul> <p>If you select Certificate, and extended authentication (EAP) is not used, this certificate will be sent out for IKE client authentication. If extended authentication is used, this certificate can be used for EAP-TLS.</p>

TABLE 3. PROXY - AUTOMATIC SETTINGS (CONT.)

Item	Description
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Use this field to specify a custom format, such as \$PASSWORD\$_\$USERID\$.</p> <p>Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL\$: \$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
Role	Specify the Pulse user role to use as a restriction.
Realm	Specify the Pulse realm to use as a restriction.
VPN On Demand	If the Samsung Knox and per-App VPN fields are both selected, then select this option to use VPN On Demand.
Per-app VPN	When selecting this option, a Samsung Knox license is required.
Provider Type	This setting applies to iOS and macOS devices only.

Continue with "Custom Data" below.

## Custom Data

- **Add+** - Click to add a new key / value pair.
- **Key / Value** - Enter the Key / value pairs necessary to configure the VPN setting. The app creator should provide the necessary key / value pairs.

## KNOX VPN Support

As part of Ivanti's support of Samsung Knox, Mobile@Work for Android together with Core support the following Virtual Private Network (VPN) clients:

- Pulse Secure (previously called Junos Pulse) (SSL)
- F5 BIG-IP Edge Client (SSL)
- Cisco AnyConnect (SSL)
- OpenVPN (SSL)
- Tunnel for Samsung Knox

Mobile@Work 9.0.0.0 for Android or supported newer versions adds:

- Cisco AnyConnect (universal app for Android and for Samsung Knox)

Core supports all of these VPN clients on Samsung Knox 2.0 or supported newer versions.

The following VPN connection types are supported with other Android devices:

- Cisco AnyConnect
- Pulse Secure
- F5 SSL
- Tunnel
- Palo Alto Networks GlobalProtect

## Basic Requirements to use Samsung Knox Features

To use any Samsung Knox Premium features that Core supports, including VPN, the following are required:

- The user must have a Samsung Knox-capable mobile device.
- A Samsung General Policy with a Samsung Knox license key must be defined and applied to a label. To create this policy, in Core Admin Portal go to **Policies & Configs > Policies**. Select **Add New > Android > Samsung General**.
- The device must have the Samsung General Policy label applied.

## VPN clients deployed either inside or outside Knox Workspace

VPN client apps are deployed either inside or outside the Knox Workspace (container). When deployed inside the container, the VPN client and its data are protected by the Knox security platform.

Whether the VPN client is deployed inside or outside the container depends on:

- the version of Mobile@Work on the device
- an option you set in the VPN setting

### Mobile@Work 9.1 for Android

When a device is running Mobile@Work 9.1 for Android, you can set an option in the VPN setting to deploy the VPN client inside the container. The following VPN clients you can use with Samsung devices to deploy inside or outside the container are:

- Pulse Secure SSL (previously Junos Pulse)
- Cisco AnyConnect
- F5 SSL

- OpenVPN
- Tunnel for Samsung Knox

The option in the VPN setting is called **Deploy inside Knox workspace**. **When you choose this option, be sure to add the VPN client app to the Apps** section of the Samsung Knox Container setting. Tunnel for Samsung Knox is always deployed inside the container.

**See also:**

- ["Configuring VPN modes when VPN client is outside the Knox container" on the next page](#)

## VPN Modes

For Android devices using the Samsung Knox Workspace, there are four VPN modes you can configure in Core. They are:

### Per-Device VPN

- If a VPN client is installed outside the Knox container:
  - all apps outside the container use the same VPN connection.
  - a per-device VPN does not apply inside the Knox container for Samsung Knox 2.0 or supported newer versions.
- If a VPN client is installed inside the Knox container, per-device VPN provides similar functionality to per-container VPN:
  - all apps inside the Knox container use the same VPN connection.
  - a per-device VPN does not apply to apps outside the Knox container.
- Available for all Android devices.

### Per-Container VPN

- All apps inside the Knox container use the same VPN connection.
- Requires a Samsung Knox license.

### Per-App VPN for apps inside of Knox Container

- Applies to individual apps inside a Knox container.
- Each app can be individually assigned to a VPN connection. We recommend using a single VPN profile from a single provider. (The new feature allows you to cross providers.)
- Any number of apps can share a single VPN connection. (Check this is true for the cross provider

feature. It may only be one app.)


- Requires a Samsung Knox license. See ["Working with Samsung general policies" on page 154](#).

## Per-App VPN for apps outside of Knox Container

- Applies to apps outside of a Knox container (a Knox container may or may not be present.)
- Each app can be individually assigned to a VPN connection.
- Requires a Samsung Knox license.

All of these modes are supported by the following VPN clients on Samsung Knox devices:

TABLE 1. VPN CLIENTS

VPN Client Name	Appears in VPN Setting as Connection Type:
Pulse Secure (previously: Junos Pulse)	"Pulse Secure SSL" <hr/>  The connection type "Juniper SSL" is only for VPN settings created in previous versions of Core. <hr/>
F5 BIG-IP Edge Client	"F5 SSL"
OpenVPN	"OpenVPN"
Cisco AnyConnect	"Cisco AnyConnect"

The following VPN clients are supported for non-Samsung Android devices using per-device mode:

- Cisco AnyConnect
- F5 SSL
- Tunnel
- Pulse Secure
- Palo Alto Networks GlobalProtect

## Configuring VPN modes when VPN client is outside the Knox container

If the VPN client is installed outside the Knox container, you can configure the VPN client to be used in one of these modes:

- per-device
- per-container
- per-app

In addition, you can configure a per app Android Enterprise VPN within the Knox v3 workspace. See ["Creating per container and per app Android Enterprise VPNs within the Knox v3 workspace" on the next page.](#)

The following table provides an overview of what you need to configure for each mode.

	per-device mode	per-container mode	per-app mode
Description	The VPN client configured for per-device use can be used by appropriately labeled apps that are outside the Knox container.	The VPN client configured for per-container use can be used by any apps inside the Knox container.	The VPN client configured for per-app use can be used only by apps specifically configured to use it. The apps can be either inside or outside the Knox container.
VPN setting	Options in VPN setting: <ul style="list-style-type: none"> <li>• <b>per-app VPN:</b> No</li> <li>• <b>Samsung Knox:</b> Select ONLY if using OpenVPN.</li> <li>• <b>Deploy inside Knox Workspace:</b> Not selected</li> </ul> Apply label to VPN setting	Options in VPN setting <ul style="list-style-type: none"> <li>• <b>per-app VPN:</b> Yes</li> <li>• <b>Samsung Knox:</b> Selected</li> <li>• <b>Deploy inside Knox Workspace:</b> Not selected</li> </ul> Apply label to VPN setting	Options in VPN setting <ul style="list-style-type: none"> <li>• <b>per-app VPN:</b> Yes</li> <li>• <b>Samsung Knox:</b> Selected</li> <li>• <b>Deploy inside Knox Workspace:</b> Not selected</li> </ul> Apply label to VPN setting
App in App Catalog	<ul style="list-style-type: none"> <li>• Apply label to app</li> <li>• <b>Per App VPN Settings</b> in app: not applicable</li> </ul>	<ul style="list-style-type: none"> <li>• App label is not applicable to VPN usage</li> <li>• <b>Per App VPN Settings</b> in app: not applicable</li> </ul>	For apps outside the Knox container: <ul style="list-style-type: none"> <li>• Apply label to app</li> <li>• <b>Per App VPN Settings</b> in app: set to VPN setting</li> </ul>
Samsung Knox Container setting		<ul style="list-style-type: none"> <li>• In the <b>App Settings</b> section, in the <b>VPN</b> field, select the VPN setting from the drop-down list.</li> </ul>	For apps inside the Knox container: <ul style="list-style-type: none"> <li>• In the <b>Apps</b> section, for the specific app, select the VPN setting from the drop-down list.</li> </ul>

	per-device mode	per-container mode	per-app mode
		<ul style="list-style-type: none"> <li>In the <b>Apps</b> section, for a specific app, make no VPN selection.</li> <li>Apply label to Samsung Knox Container setting</li> </ul>	<ul style="list-style-type: none"> <li>In the <b>App Settings</b> section, in the VPN field, make no selection.</li> <li>Apply label to Samsung Knox Container setting</li> </ul>
Android enterprise	N/A	( Managed device with Work Profile mode)  <b>Enable Managed Device with Work Profile (on Android 10 and below)</b> Selected  <b>Enable Samsung Per-container VPN:</b> Selected	( Managed device with Work Profile mode)  In the App Catalog, <b>Per App VPN by Label Only:</b> Selected (applicable for in-house apps only)  <b>Install this app for Android enterprise:</b> Selected

## Creating per container and per app Android Enterprise VPNs within the Knox v3 workspace

In Work Profile mode, Managed Device with Work Profile mode, and Work Profile on Company Owned Device mode, administrators can configure Knox VPN settings for per container and per app deployment devices to communicate with services securely. Within the Knox workspace, administrators can create per-app VPNs that they can assign to apps in the Apps catalog. Additionally, a special case of a per app deployment ( Tunnel + OpenVPN) supports VPN chaining, see "Configuring VPN chaining" procedure in *Tunnel for Android Guide*.

Work Profile mode, Managed Device with Work Profile mode, and Work Profile on Company Owned Device mode works with the following VPN connection types:

- Cisco AnyConnect
- F5 SSL
- Pulse Secure SSL
- OpenVPN
- Tunnel (Samsung KNOX Workspace)

Note The Following:

These methods of configuring VPNs are not supported:



- Configuring VPNs via App restrictions and using Knox VPN APIs
- Support for device-wide VPN in Managed device with Work Profile mode

Android Enterprise VPN is configured using a password and certificate-based credentials. KLM licenses must be applied.

## Creating per container Android Enterprise VPN with Knox 3 workspace

This section covers configuring Knox VPN settings for per container Android Enterprise. The below procedure is applicable for Managed device with Work Profile mode for Android version 8.0.

### Procedure

1. Register the device, in Work Profile mode, to Core using the procedure described in ["Setting the registration PIN code length for device user registration" on page 70](#).
2. Create a Samsung General Policy. See ["Working with Samsung general policies" on page 154](#).
3. Create a Android Enterprise configuration.
  - a. Click **Add New > Android > Android enterprise**.

The New Android enterprise (all modes) Setting dialog box opens.
  - b. Enter the Name and Description of the configuration.
  - c. Select the **Enable Managed Device with Work Profile (on Android 10 and below)** check box.

This field applies to Android 8, 9, and 10 devices.
  - d. Click **Save**.
4. Apply the configuration to a device label.

5. Create a VPN configuration for Android Enterprise.
  - a. Click **Policies & Configurations > Configurations**.
  - b. Select **Add New > VPN**. The Add VPN Setting dialog box opens.
  - c. Select a Connection Type in the drop-down:
    - Cisco Legacy AnyConnect
    - OpenVPN
    - F5 SSL
    - Pulse Secure SSL
    - Tunnel (Samsung KNOX Workspace)
  - d. Select the **Samsung KNOX** check box.
  - e. Select the **Deploy inside Knox Workspace** check box.
  - f. Select the Per-app VPN **Yes** radio button.
  - g. Click **Save**.
6. Apply the VPN configuration to a device label.
7. Edit the Android Enterprise configuration.
  - a. In the For Samsung Knox v3 (Android 8.0) section, select the **Enable Samsung Per-container VPN** check box.
  - b. In the VPN Config Name field, select the VPN configuration you just created.
  - c. Click **Save**.

In Devices & Users > Devices > Device Details page, the Managed Device with Work Profile displays your setting, for example, Workspace > Tunnel.

## Creating per app Android Enterprise VPN with Knox 3 workspace

This section covers configuring Knox VPN settings for per app Android Enterprise. The below procedure is applicable for Managed device with Work Profile mode.



Before you begin this procedure, follow the "Configuring VPN chaining" procedure in *Tunnel for Android Guide* to populate the **VPN Config Name** field.

---

1. Register the device, in Work Profile mode, to Core using the procedure described in "[Setting the registration PIN code length for device user registration](#)" on page 70.
2. Create a Samsung General Policy. See "[Working with Samsung general policies](#)" on page 154.
3. Apply the policy to a device label.

4. Add a new Android Enterprise app in the App Catalog, for example, Google Chrome.
  - a. Click **Apps > App Catalog > Add**.
  - b. In the Android Enterprise section, select the **Install this app for Android enterprise** check box.
  - c. Click **Save**.
5. Apply the app to a device label.
6. Create a VPN configuration for Android Enterprise.
  - a. Click **Policies & Configurations > Configurations**.
  - b. Select **Add New > VPN**. The Add VPN Setting dialog box opens.
  - c. Select a Connection Type in the drop-down:
    - Cisco Legacy AnyConnect
    - OpenVPN
    - F5 SSL
    - Pulse Secure SSL
    - Tunnel (Samsung KNOX Workspace)
  - d. Select the **Samsung Knox** check box.
  - e. Select the **Deploy inside Knox Workspace** check box.
  - f. Select the Per-app VPN **Yes** radio button.
  - g. **Save** the new configuration.
7. Import another app and install this app for Android Enterprise. In the Per App VPN Settings section, select the new perApp VPN you created.

### Next steps

["Move Android Enterprise in-house apps to inside Knox Workspace" below](#)

## Move Android Enterprise in-house apps to inside Knox Workspace

Once you have set up VPN for Knox Workspaces, you can move in-house apps from outside of the workspace to inside the Knox workspace. This is applicable to:

- Managed Device with Work Profile mode on Android devices with an activated KNOX premium license.
- devices with Knox version 3.x and above only.

You cannot copy or move apps from the personal side of the device into Work Profile mode or Managed Device with Work Profile mode on Samsung devices. The in-house apps should be assigned to a device label so they can be installed in a personal (outside of the container) space. This Android Enterprise-only capability allows you to move previously-installed in-house apps into the container (Knox V3 workspace) using whitelisting of apps in the Android Enterprise configuration. The app being moved must be whitelisted prior to moving inside the Knox workspace, see ["Android Samsung Knox Container Settings" on page 499](#).

## Procedure

This procedure is applicable for Android OS version 8.0 or supported newer versions.

1. Complete the procedure in ["Creating per container Android Enterprise VPN with Knox 3 workspace" on page 297](#) or ["Creating per app Android Enterprise VPN with Knox 3 workspace" on page 298](#).
2. Add a new Android Enterprise app in the App Catalog.
3. Apply the app to a device label.
4. If needed, force device check in.
5. In **Policies & Configs > Configurations**, **Edit** the Android Enterprise configuration and select the **Move In- House app into workspace** check box.
6. In the Package Name field, select the name of the app or hold the Shift key down and select multiple apps.
7. Click **Save**.

On the device, the app is moved to the Knox Workspace. In the device's Settings > Workspace option, the Install apps option is disabled.

## Remove Android Enterprise apps from Knox Workspace

If the whitelist of apps is modified and an app is no longer listed inside the Knox workspace, that app will be moved back to the personal space. If the whitelist of apps is removed, all previously installed in-house apps will be moved back into the personal space.

## Procedure

1. In **Policies & Configs > Configurations**, **Edit** the Android Enterprise configuration.
2. In the Package Name field, de-select the name of the app or hold the Shift key down and de-select multiple apps.
3. Click **Save**.
4. Force device check in.

On the device, the app is moved out of Knox Workspace to the personal space.

## Configuring VPN modes when VPN client is inside the Knox container

If the VPN client is installed inside the Knox container, you can configure the VPN client to be used in one of these modes:

- per-device, but when the VPN client is installed inside the Knox container, per-device mode is really another way to configure per-container mode. Apps outside the container cannot use the VPN client.
- per-container
- per-app

The following table provides an overview of what you need to configure for each mode.

	per-device mode	per-container mode	per-app mode
Description	The VPN client configured for per-device use can be used by any apps inside the Knox container.  Therefore, per-device mode when the VPN client is inside the container <b><i>is really a way of configuring per-container mode.</i></b>	The VPN client configured for per-container use can be used by any apps inside the Knox container.	The VPN client configured for per-app use can be used only by apps specifically configured to use it. The apps can be either inside or outside the Knox container.
VPN setting	Options in VPN setting: <ul style="list-style-type: none"> <li>• <b>per-app VPN:</b> No</li> <li>• <b>Samsung Knox:</b> Selected</li> <li>• <b>Deploy inside Knox Workspace:</b> Selected</li> </ul> Apply label to VPN setting	Options in VPN setting <ul style="list-style-type: none"> <li>• <b>per-app VPN:</b> Yes</li> <li>• <b>Samsung Knox:</b> Selected</li> <li>• <b>Deploy inside Knox Workspace:</b> Selected</li> </ul> Apply label to VPN setting	Options in VPN setting <ul style="list-style-type: none"> <li>• <b>per-app VPN:</b> Yes</li> <li>• <b>Samsung Knox:</b> Selected</li> <li>• <b>Deploy inside Knox Workspace:</b> Selected</li> </ul> Apply label to VPN setting
App in App Catalog	<ul style="list-style-type: none"> <li>• App label is not applicable to VPN usage</li> <li>• <b>Per App VPN Settings</b> in app: not applicable</li> </ul>	<ul style="list-style-type: none"> <li>• App label is not applicable to VPN usage</li> <li>• <b>Per App VPN Settings</b> in app: not applicable</li> </ul>	For apps outside the Knox container: <ul style="list-style-type: none"> <li>• Apply label to app</li> <li>• <b>Per App VPN Settings</b> in app: set to VPN setting</li> </ul>

	per-device mode	per-container mode	per-app mode
Samsung Knox Container setting	<ul style="list-style-type: none"> <li>Include the VPN client in the <b>Apps</b> section.</li> </ul> <p><b>Note:</b> Do not apply a label to the VPN client app itself. This reference to the app will result in the app being deployed in the device's Knox container.</p> <ul style="list-style-type: none"> <li>Apply label to Samsung Knox Container setting</li> </ul>	<ul style="list-style-type: none"> <li>Include the VPN client in the <b>Apps</b> section.</li> </ul> <p><b>Note:</b> Do not apply a label to the VPN client app itself. This reference to the app will result in the app being deployed in the device's Knox container.</p> <ul style="list-style-type: none"> <li>In the <b>App Settings</b> section, in the <b>VPN</b> field, select the VPN setting from the drop-down list.</li> <li>In the <b>Apps</b> section, for a specific app, make no VPN selection.</li> <li>Apply label to Samsung Knox Container setting</li> </ul>	<ul style="list-style-type: none"> <li>Include the VPN client in the <b>Apps</b> section.</li> </ul> <p><b>Note:</b> Do not apply a label to the VPN client app itself. This reference to the app will result in the app being deployed in the device's Knox container.</p> <ul style="list-style-type: none"> <li>For apps inside the container, in the <b>Apps</b> section, for the specific app, select the VPN setting from the drop-down list.</li> <li>In the <b>App Settings</b> section, in the <b>VPN</b> field, make no selection.</li> <li>Apply label to Samsung Knox Container setting</li> </ul>

## VPN Behavior on the Device

When a VPN setting is installed on a device, the following behavior is observed:

- The VPN client displays its VPN connection status in the notifications bar.
- For per-app VPN configurations, the connection is automatically established when the user opens an app or accesses data that requires the connection.
- For per-device VPN, the user must manually establish the connection through the VPN client app.

Disconnecting or attempting to remove VPN behaves as follows:

- A user cannot disconnect a per-app or per-container VPN connection manually. The connection is automatically disconnected if:
  - Device is removed from the label that provides VPN.
  - Device is retired.
- A user can disconnect a per-device VPN connection manually.
- A user cannot uninstall a VPN client on Samsung devices if a VPN connection exists using the client.

## Usage Notes

### For all VPN clients:

- Knox 1.2 supports using per-app VPN outside of the Knox container, but not inside. Per-device VPN works inside Knox 1.2 container.
- Knox 2.0 or supported newer versions is required to use per-app VPN inside of the Knox container. Per-device VPN is not available inside these versions of the Knox container.

For the F5 BIG-IP Edge Client, Pulse Secure (previously Junos Pulse), OpenVPN, and Cisco AnyConnect:

- To use per-app VPN with Pulse Secure, F5 BIG-IP Edge Client, OpenVPN, or Cisco AnyConnect, you must select Samsung Knox in the VPN Settings. An invalid configuration can result if Samsung Knox is not selected.

### For Juniper (Pulse Secure, previously Junos Pulse):

- For the Pulse Secure client, the user must accept the app's EULA before Mobile@Work can install the VPN setting.
- To use Pulse Secure for per-app VPN, a license is required from Juniper Networks that is applied to the VPN gateway.
- Mobile@Work supports the PulseSecure client, not the "Junos for Samsung" client.

Regarding migrating to Pulse Secure from Junos Pulse:

Only Mobile@Work 9.0.0.0 and prior prompts the device user to install Pulse Secure if the device is using the Junos Pulse VPN app. Otherwise, device users are not prompted, but can uninstall the Junos Pulse app and then install Pulse Secure. When Junos Pulse is uninstalled, the Junos Pulse configurations will be removed only if the device is running Mobile@Work 9.0.0.0 or prior.

If you prefer device users to be prompted to migrate, Ivanti recommends users stay on Mobile@Work 8.5 (8.5.0.0 through 8.5.0.3) until after they have upgraded to Pulse Secure. See the migration instructions in the following documents.

- “Junos Pulse to Pulse Secure Migration: Configuring a Custom SSL VPN Config in Core”: <https://community.mobileiron.com/docs/DOC-1755>
- “Action Required by September 30, 2015 to Support Junos Pulse VPN on Newly Enrolled iOS and Android Devices”: <https://community.mobileiron.com/docs/DOC-3097>

## Limitations for VPN connections and settings

- Per-container VPN for the Knox container cannot be combined with per-app VPN for apps inside the container. You must choose to use one VPN mode or the other.

To do so, in the **New Samsung Knox Container Setting** dialog, you must either provide a VPN selection for individual apps in the **Apps** section, or provide a VPN selection in the **App Settings** section, but not both

- Mobile Iron recommends using a single VPN client and a single VPN connection per device.

## How to set up VPN for apps both outside and inside the Knox container

In Knox 2.0 or supported newer versions, when you install a VPN client outside of the Knox container, a per-device VPN does not provide VPN inside the Knox container. If you want VPN working for apps both inside and outside the Knox container when the VPN client is outside the Knox container, set up:

- a per-device VPN for apps outside of the container, and
- a per-container VPN for the apps inside of the container.

We recommend using the same VPN client for each. You will need to create a separate VPN setting for each, however. One VPN setting sets its per-app VPN option to yes, and the other sets it to no.

See “Configuring VPN modes when VPN client is outside the Knox container” on page 294.

## Using certificates with VPN

When using certificates with VPN settings, depending on the VPN client, you will need to add the certificate in the VPN setting, and in some cases also assign the certificate to a label.

The following tables indicate the rules for each VPN client and certificate type.

VPN Client	Rules for User Authentication Certificates
Pulse Secure (previously: Junos Pulse), OpenVPN	Provide user authentication certificate in the VPN setting. Apply certificate to a label.
Mocana KeyVPN, F5 Big-IP Edge Client	Provide user authentication certificate in the VPN setting only. Do not apply certificate to a label.



VPN Client	Rules for CA (Root) Certificates
Pulse Secure (previously: Junos Pulse), F5 Big-IP Edge Client	Apply CA certificate to a label.
Mocana KeyVPN, OpenVPN	Provide CA certificate in the VPN setting only. Do not apply certificate to a label.

## Samsung Knox IPsec

This VPN connection type is supported on Android devices. It is not supported on iOS, macOS, and Windows devices.

This section applies to Android devices with Samsung Knox only. Samsung Knox IPsec is used for VPN access in the Samsung Knox container - see ["Android Samsung Knox Container Settings" on page 499](#).

Use the following guidelines to configure Samsung Knox IPsec.

TABLE 1. SAMSUNG KNOX IPSEC SETTINGS

Item	Description
Name	Enter a short phrase that identifies this VPN setting.
Description	Provide a description that clarifies the purpose of these settings.
Channel	For macOS only. Select one of the following distribution options: <ul style="list-style-type: none"> <li>Device channel - the configuration is effective for all users on a device. This is the typical option.</li> <li>User channel - the configuration is effective only for the currently registered user on a device.</li> </ul>
Connection Type	Select <b>Samsung Knox IPsec</b> .
Server	Enter the IP address, hostname, or URL for the VPN server.
Backup Server	Enter the IP address, hostname, or URL for the fallback server to use in the event that the primary server is not available.
Authentication Type	Select the authentication method to use: <ul style="list-style-type: none"> <li><b>Pre-Shared Key</b> - When selected, the Shared Secret and Group Name fields display.</li> <li><b>Certificate</b> - When selected, the Identity Certificate and CA Certificate fields display.</li> </ul>

TABLE 1. SAMSUNG KNOX IPSEC SETTINGS (CONT.)



Item	Description
Shared Secret	<p>This field displays when Pre-Shared Key is selected as the Authentication Type.</p> <p>Enter the shared secret passcode. This is not the user's password; the shared secret must be specified to initiate a connection.</p>
Confirm Shared Secret	Re-enter the Shared Secret passcode to confirm.
Group ID Type	<p>This field displays when Certificate is selected as the Authentication Type.</p> <p>Select the Group ID type your IPsec VPN server uses to authenticate to IKE peers.</p>
User Authentication	<p>This field displays when Certificate is selected as the Authentication Type.</p> <p>Select to enable user authentication as an additional factor.</p>
Group Name	<p>This field displays when Pre-Shared Key is selected as the Authentication Type. Enter the group name for your Samsung Knox IPsec VPN server. This name corresponds to the value selected in Group ID Type.</p>
Identity Certificate	<p>This field displays when Certificate is selected as the Authentication Type.</p> <p>Select the entry you created for supporting VPN, if you are implementing certificate-based authentication.</p>
CA Certificate	<p>This field displays when Certificate is selected as the Authentication Type.</p> <p>Select the entry you created for supporting VPN, if you are implementing certificate-based authentication.</p>
Username	<p>Specify the user name to use. The default value is \$USERID\$. Use this field to specify an alternate format, such as:</p> <p>\$USERID\$, \$EMAIL\$, \$SAM_ACCOUNT_NAME\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as the following:</p> <ul style="list-style-type: none"> <li>• \$USERID\$: \$EMAIL\$</li> <li>• \$USERID\$_\$EMAIL\$</li> </ul> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant username.</p> <hr/> <p> Some enterprises have a strong preference concerning which identifier is exposed.</p>

TABLE 1. SAMSUNG KNOX IPSEC SETTINGS (CONT.)

Item	Description
Password	<p>Specify the password to use (required.) The default value is \$PASSWORD\$. Include at least one of the following variables:</p> <p>\$USERID\$, \$EMAIL\$, \$PASSWORD\$, \$USER_CUSTOM1\$, \$USER_CUSTOM2\$, \$USER_CUSTOM3\$, \$USER_CUSTOM4\$, \$CUSTOM_DEVICE_Attributename\$, \$CUSTOM_USER_Attributename\$, \$NULL\$</p> <p>You can use combinations such as \$EMAIL:\$PASSWORD\$</p> <p>Enter \$NULL\$ if you want the field presented to the user to be blank. Users will need to fill in the relevant password.</p>
IKE Version	<p>The IPsec VPN server uses the IKE to negotiate the protocols and algorithms used for the connection, and to generate the encryption and authentication keys. Select one:</p> <ul style="list-style-type: none"> <li>• <b>Phase 1</b> - When Phase 1 is selected, the Phase 1 Mode field displays.</li> <li>• <b>Phase 2</b></li> </ul>
Phase 1 Mode	<p>If you selected IKE Phase 1, select the mode of operation in use by your IPsec VPN server:</p> <ul style="list-style-type: none"> <li>• <b>Main</b> - Has three two-way exchanges between the initiator and the receiver.</li> <li>• <b>Aggressive</b> - Fewer exchanges are made, and with fewer packets.</li> </ul>
Per-app VPN	<p>Select <b>Yes</b> to create a per-app VPN setting. A Samsung Knox key / license is required for this feature.</p> <p>You cannot delete a per-app VPN setting that is being used by an app. Remove the per-app VPN setting from the app before you delete the setting.</p> <p>You can enable per-app VPN for an app when you:</p> <ul style="list-style-type: none"> <li>• add the app in the App Catalog.</li> <li>• edit an in-house app or an App Store app in the App Catalog.</li> </ul> <hr/> <p> When multiple labels are assigned to associate the selected VPN configurations in the Per-App VPN section, then VPN prioritization will happen in the order of the selected list.</p> <hr/> <p>See the <i>Core Apps@Work Guide</i> for information about how to add or edit apps.</p>

## **SonicWall Mobile Connect**

This VPN connection type is supported on iOS, macOS, and Windows devices. It is not supported on Android devices.

## **Custom SSL**

This VPN connection type is supported on iOS devices. It is not supported on macOS, Android, and Windows devices.

# Managing Certificates and Configuring Certificate Authorities

This section addresses components related to managing certificates and certificate authorities.

Certificates overview .....	309
Managing certificates issued by certificate enrollment configurations .....	311
Supported certificate scenarios .....	312
Core as a certificate authority .....	314
Configuring Core as an independent root CA (Self-Signed) .....	314
Configuring Core as an intermediate CA .....	318
Mutual authentication between devices and Core .....	319
Certificates settings .....	332
Certificate Enrollment settings .....	333
Configuring a client-provided certificate enrollment setting .....	336
Configuring an Entrust CA .....	339
Configuring a GlobalSign CA .....	341
Configuring Core as the CA .....	344
Configuring OpenTrust CA .....	346
Configuring a single file identity certificate enrollment setting .....	348
Configuring SCEP .....	349
Configuring Symantec Managed PKI .....	354
Configuring Symantec Web Services Managed PKI .....	356
Configuring a user-provided certificate enrollment setting .....	359

## Certificates overview

Core is capable of distributing and managing certificates.

Certificates are mainly used for the following purposes:

- Establishing secure communications
- Encrypting payloads
- Authenticating users and devices

Certificates establish user identity while eliminating the need for users to enter user names and passwords on their mobile devices. Certificates streamline authentication to key enterprise resources, such as email, Wi-Fi, and VPN. Some applications require the use of certificates for authentication.

The following diagram compares a certificate to a passport:

FIGURE 1. COMPARING CERTIFICATES TO A PASSPORT



The certificate includes information that identifies the following information:

- the issuing certificate authority
- acceptable uses for the certificate
- information that enables the certificate to be validated.

This solution provides the flexibility to use Core as a local certificate authority, an intermediate certificate authority, or as a proxy for a trusted certificate authority.

## Types of certificates

Core uses the following types of certificates:

TABLE 1. CERTIFICATE TYPES


Certificate type	Description
Portal HTTPS	<p>The identify certificate and its certificate chain, including the private key, that identifies Core, allowing a client (such as a browser or app) to trust Core. Typically, this certificate is the same certificate as the Client TLS and iOS Enrollment certificates.</p> <p>Core sends this certificate to the client as part of the TLS handshake over port 443 or 8443 when the client initiates a request to Core.</p> <hr/> <p> This certificate must be a publicly trusted certificate from a well-known Certificate Authority if you are using mutual authentication.</p> <hr/> <p><b>Related topics</b></p>

TABLE 1. CERTIFICATE TYPES (CONT.)

Certificate type	Description
	"Certificates you configure on the System Manager" in the Core System Manager Guide
Client TLS	<p>The identify certificate and its certificate chain, including the private key, that identifies Core, allowing Mobile@Work for iOS and Android to trust Core. Typically, this certificate is the same certificate as the Portal HTTPS and iOS Enrollment certificates.</p> <p>Core sends this certificate to Mobile@Work for iOS or Android as part of the TLS handshake over port 9997 when Mobile@Work initiates a request to Core.</p> <p><b>Related topics</b></p> <p>"Certificates you configure on the System Manager" in the Core System Manager Guide</p>
MobileIron Core server SSL	Can be either self-signed or third-party certificates. By default, Core generates self-signed certificates. You can use trusted certificates from third-party certificate providers such as Verisign, Thawte, or Go Daddy. Kerberos and Entrust certificates are also supported.
Sentry server SSL	Identifies the Sentry to the client and secures communication, over port 443, between devices and the Sentry.
Client identity	Verifies the identity of users and devices and can be distributed through Certificate Enrollment.

## Samsung Knox devices and certificates managed by Core

Certificates managed by Core are automatically removed from a Samsung Knox device when the device is retired, or when the label that applied the certificate to the device is removed from the certificate.

## Managing certificates issued by certificate enrollment configurations

Core runs a process each day at 3:45 am that manages all certificates issued using certificate enrollment configurations.

Certificates have a limited lifetime that is defined when certificates are issued. When the certificate lifetime is within the expiry window (60 days, by default), Core does not automatically renew the certificates. Only a forced manual renewal/creation is possible.

Re-issued certificates are sent to the managed device configuration and the expiring certificates become inactive. The inactive certificates are purged from the system once the certificates are expired or confirmed to be revoked.

## Supported certificate scenarios

Core supports the following certificate scenarios:

- ["Core as a certificate authority" below](#)
- ["Using Core as a certificate proxy" below](#)
- ["Using Core as a certificate enrollment reverse proxy" on the next page](#)
- ["Kerberos constrained delegation" on page 314](#)

### Core as a certificate authority

You can configure Core as a local certificate authority (CA) for the following scenarios:

- Core as an Independent Root CA (self-signed)—Configure Core as an independent root certificate authority if you are using a self-signed certificate. Use this option if your company does not have its own certificate authority and you are using Core as the certificate authority.
- Core as an Intermediate CA—Use this option when your company already has its own certificate authority. Using Core as an Intermediate CA gives your mobile device users the advantage of being able to authenticate to servers within your company intranet.

### Using Core as a certificate proxy

Core can act as a proxy to a 3rd party CA by using APIs exposed by the 3rd party CA or the SCEP protocol to obtain certificates required by a Certificate Enrollment. This enables you to configure certificate-based authentication for devices.

Using Core as a certificate proxy has the following benefits:

- Certificate verifies Exchange ActiveSync, Wi-Fi and/or VPN connections, eliminating the need for passwords that are complex to manage
- Core can manage certificates by checking status against a CA's CRL, deactivating revoked certificates and requesting replacement when certificates are about to expire
- Core can detect and address certificate renewal and ensure that devices cannot reconnect to enterprise resources if they are out of compliance with company policies.



- Simplified enrollment with the following:
  - MS Certificate Enrollment
  - Entrust
  - Local CA
  - Symantec Managed PKI
  - User provided certificates
  - Open Trust
  - Symantec Web Services Managed PKI

The following applications are supported.

- ActiveSync is supported with Email+ and TouchDown
- VPN is supported on Android with Cisco AnyConnect .
- Wi-Fi.

The following certificates are supported for Android devices:

- Microsoft NDES Certificate Enrollment
- Entrust
- Local CA
- Symantec Managed PKI
- User provided certificates
- Open Trust
- Symantec Web Services Managed PKI
- Client-Provided certificates
- Client-provided certificates using the native SCEP client on iOS

For information about how to create certificate enrollment settings in Core, see ["Certificate Enrollment settings" on page 333](#).

## Using Core as a certificate enrollment reverse proxy

Identity certificates with Microsoft Certificate Enrollment are supported. A root or intermediate certificate from a trusted certificate authority (CA) is required, and you must set up Core to act as a SCEP reverse proxy.

Windows devices originate the certificate request. When the Windows device requests a certificate, the Core acts as a Certificate Enrollment reverse proxy and communicates with the Certificate Enrollment server to deliver the certificate to the device.

## Kerberos constrained delegation

You can use Kerberos constrained delegation (KCD) for authenticating the device to the ActiveSync server, the app server, and to Sentry.

For detailed information about how to configure Core to use Kerberos authentication, see, "Device and server authentication support for Standalone Sentry" in the *Sentry Guide for Core*.

## Core as a certificate authority

You can configure Core as a local certificate authority for the following scenarios:

- **Core as an Independent Root CA (self-signed)**— Configure Core as an independent root certificate authority if you are using a self-signed certificate. Use this option if your company does not have its own certificate authority and you are using Core as the certificate authority.

See ["Configuring Core as an independent root CA \(Self-Signed\)"](#) below.

- **Core as an Intermediate CA**—Use this option when your company already has its own certificate authority. Using Core as an Intermediate CA gives your mobile device users the advantage of being able to authenticate to servers within your company intranet.

See ["Configuring Core as an intermediate CA" on page 318](#).

## Configuring Core as an independent root CA (Self-Signed)

Configuring Core as an independent root CA requires configuring your infrastructure to trust Core as an independent root CA.

To configure Core as an independent root CA, you must follow these basic steps:

1. Generate a self-signed certificate

See ["Generating a self-signed certificate"](#) below.

2. Create a local CA certificate enrollment setting for the self-signed certificate


See ["Creating a local certificate enrollment setting" on page 317](#).

## Generating a self-signed certificate

To generate the self-signed certificate:

1. Log into the Admin Portal.
2. Go to **Services > Local CA**.

3. Select **Add > Generate Self-Signed Cert.**



The image shows a 'Generate Self-Signed Certificate' dialog box with the following fields and values:

Field	Value
Local CA Name	Local CA Name
Key Type	RSA
Key Length	3072
CSR Signature Algorithm	SHA384
Key Lifetime (in days)	10950
Issuer Name	CN=Secure Certification Authority

At the bottom right, there are two buttons: 'Cancel' and 'Generate'.

4. Enter the following information.

- **Local CA Name:** Enter a recognizable name to identify the self-signed certificate. This name will appear in the list of local certificate authorities in **Services > Local CA**.
- **Key Type:** Specify the key type. The options are RSA (default) or Elliptical Curve.
- **Key Length:** Specify the key length. The values are 2048, 3072 (the default), and 4096. The longer the key length, the more secure the certificate.
- **CSR Signature Algorithm:** The values are SHA1, SHA256, SHA384 (default), and SHA512.
  - **Key Lifetime (in days):** Enter number of days. The key will expire after the entered number of days. The default is 10,950 days. Ivanti recommends 5 years or longer; 61 days is the minimum.
  - **Issuer Name:** Requires an X.509 name. For example, CN=www.yourcompany.com, DC=yourcompany, DC=com.

The **Issuer Name** field uses an X.509 distinguished name. You can use one or more X.509 codes, separated by commas. The following table describes the valid codes for the Issuer Name field:

Code	Name	Type	Max Size	Example
C	Country/Region	ASCII	2	C=US
DC	Domain Component	ASCII	255	DC=company, DC=com
S	State or Province	Unicode	128	S=California
L	Locality	Unicode	128	L=Mountain View
O	Organization	Unicode	64	O=Company Name, Inc.
OU	Organizational Unit	Unicode	64	OU=Support
CN	Common Name	Unicode	64	CN=www.company.com

If you have a registered DNS name that you use to send SMTP mail, a best practice is to use the domain component convention and the DNS name for the certificate name.

5. Click **Generate**.

Certificate Template

▶ CA Certificate

▼ Client Certificate Template

Hash Algorithm: SHA384

Minimum Key Size Allowed: 2048

Key Lifetime (days): 365

Key Lifetime Limited by CA: ☒

Enhanced Key Usage: ☒ Client Authentication, ☐ IPSEC, ☐ Smart Card Logon

Custom OIDs:

Cancel Save

6. Configure the **Client Certificate Template**.

Values depend on the purpose for the certificate and the requirements of your environment.

- **Hash Algorithm:** The larger the hash number, the more secure. The options are SHA256, SHA384 (default), SHA512—part of the SHA2 secure hash algorithm family required for U.S. government applications. The number signifies the output bits.
- **Minimum Key Size Allowed:** The longer the key length is, the more secure the certificate.
- **Key Lifetime (days):** 365 days or longer is recommended; 61 days is the minimum.
- **Key Lifetime limited by CA:** Select to use the key lifetime specified for the self-signed CA.

Ivanti recommends enabling this option. Enabling this option ensures that client certificate validity periods do not exceed the life time of the issuing CA certificate.

- **Enhanced Key Usage:** When a certificate is presented to an application, the application can require the presence of an Enhanced Key Usage OID specific to that application. Leave these deselected if you do not have any applications that require additional OIDs.
- **Custom OIDs:** If you are using this certificate for SSL authentication, enter the OID in this field.

7. Click **Save**.

The newly created self-signed certificate will be listed in **Services > Local CA**.

## Creating a local certificate enrollment setting

After you have generated the self-signed certificate, you need to create a local CA certificate enrollment setting for the self-signed certificate. Creating a local CA certificate enrollment setting enables proxy functionality so that Core generates the certificates and caches the generated keys.

1. Log into the Admin Portal.
2. Go to **Policies & Configs > Configurations**.
3. Click **Add New > Certificate Enrollment > Local**.

For more information on configuring the settings, see ["Certificate Enrollment settings" on page 333](#).


## Configuring Core as an intermediate CA

When you configure Core as an intermediate certificate authority, the managed device users can authenticate to servers within your company intranet; not just the Core system.

After you get the certificate from your certificate vendor, you can add the certificates to Core to create the intermediate certificate authority (CA).

### Procedure

1. In the Core Admin Portal go to **Services > Local CA**.
2. Click on **Add > Intermediate Enterprise CA**.



3. Click **Browse** and navigate to the combined file.
4. Click **Open**.
5. Enter a recognizable name in the **Local CA Name** field.
6. Click **Upload Certificate**.

Your local certificate authority is now available to use. The local CA will be listed in **Services > Local CA**.

## Mutual authentication between devices and Core

Core supports mutual authentication, which means that not only must the device trust Core, but Core must trust the device. Therefore, with mutual authentication, a registered device can continue to communicate with Core only if the device provides the right certificate to Core. Mutually authenticated communication between the device and Core enhances security.



A device authenticating to Core with a certificate is also known as certificate-based authentication to Core.

---

- ["Scenarios that can use mutual authentication" below](#)
- ["Core port usage with devices, with and without mutual authentication" on the next page](#)
- ["The mutual authentication setting on Core" on page 321](#)
- ["When devices use mutual authentication" on page 322](#)
- ["Mutual authentication identity certificate for Core" on page 324](#)
- ["Mutual authentication client identity certificate" on page 324](#)
- ["Supported custom attributes for mutual authentication certificates" on page 325](#)
- ["New endpoint for mutual certification authentication" on page 325](#)
- ["Handling client identity certificate expiration for Android devices" on page 327](#)
- ["Handling client identity certificate expiration for iOS devices" on page 328](#)
- ["Mutual authentication and Apps@Work" on page 329](#)
- ["Enabling mutual authentication for Apple and Android devices" on page 329](#)
- ["Enabling TLS inspecting proxy support when using mutual authentication" on page 330](#)
- ["Enabling mutual authentication for Apple and Android devices" on page 329](#)
- ["Enabling mutual authentication for Apple and Android devices" on page 329](#)

### Scenarios that can use mutual authentication

The device can present a client identity certificate to Core in the following cases:

TABLE 1. MUTUAL AUTHENTICATION USAGE BY PLATFORM

Platform	Mutual Authentication usage
iOS	<ul style="list-style-type: none"> <li>• Mobile@Work for iOS device check-in</li> <li>• AppConnect for iOS check-in</li> <li>• iOS MDM device check-in</li> <li>• Apps@Work for iOS communication</li> </ul>
macOS	<ul style="list-style-type: none"> <li>• Mobile@Work for macOS device check-in</li> <li>• macOS MDM device check-in</li> </ul>
Android	<ul style="list-style-type: none"> <li>• Mobile@Work for Android device check-in, which includes AppConnect check-in</li> <li>• Apps@Work for Android communication</li> </ul>
Windows 10	<ul style="list-style-type: none"> <li>• Device check-in</li> </ul>



Mutual authentication is not possible at the time Mobile@Work registers with Core, because the device receives its identity certificate during the registration process.

## Core port usage with devices, with and without mutual authentication

The following table summarizes Core port usage for registration and further communication with devices. The port usage for some cases is different depending on whether mutual authentication is enabled.

TABLE 2. CORE PORT USAGE WITH DEVICES WITH AND WITHOUT MUTUAL AUTHENTICATION

	Without mutual authentication	With mutual authentication
Mobile@Work for iOS	9997	443
Mobile@Work for Android	9997	443
Mobile@Work for macOS	Not applicable. Mobile@Work for macOS always uses mutual authentication with Core.	443



TABLE 2. CORE PORT USAGE WITH DEVICES WITH AND WITHOUT MUTUAL AUTHENTICATION (CONT.)

	Without mutual authentication	With mutual authentication
iOS and macOS MDM agent provisioning and agent check-in	443	443
Windows 10	Not applicable. Windows 10 always uses mutual authentication with Core.	443



Port 9997 is configurable in the System Manager in Settings > Port Settings > Sync TLS Port. However, changing the port is rare.

## The mutual authentication setting on Core

The setting on Core to enable mutual authentication is in the Admin Portal in **Settings > System Settings > Security > Certificate Authentication**. Whether the setting is automatically selected on new installations and upgrades is described by the following table.

TABLE 3. SETTING FOR MUTUAL AUTHENTICATION ON NEW INSTALLS AND UPGRADES

	Setting to enable mutual authentication
New installations	Not selected. Mutual authentication is <b>not</b> enabled.
Upgrade from a previous version of Core in which mutual authentication was <b>not</b> enabled. Or Upgrade from a version of Core prior to Core 9.7.0.0 in which the Android mutual authentication setting was <b>not</b> enabled.	Not selected. Mutual authentication is <b>not</b> enabled.
Upgrade from a previous version of Core in which mutual authentication <b>was</b> enabled. Or Upgrade from a version of Core prior to Core 9.7.0.0 in which the Android mutual authentication setting <b>was</b> enabled.	Selected. Mutual authentication <b>is</b> enabled.

**IMPORTANT:** Once mutual authentication is enabled on Core, it cannot be disabled.

**The mutual authentication setting impacts mutual authentication usage only on:**

- Mobile@Work for Android
- Apps@Work for Android
- However, to enable mutual authentication for Apps@Work for Android:
  - You must also select **Certificate Authentication** for Apps@Work at **Apps > Apps@Work Settings > App Storefront Authentication**.
  - The device must be using Mobile@Work 10.2.0.0 for Android or supported newer versions.
- Mobile@Work 9.8 or supported newer versions.
- iOS MDM
- macOS MDM

**The mutual authentication setting has no impact on mutual authentication usage on:**

- Versions of Mobile@Work for iOS prior to Mobile@Work 9.8  
These versions of Mobile@Work for iOS **never** use mutual authentication.
- Apps@Work for iOS  
Apps@Work for iOS uses mutual authentication if you select **Certificate Authentication** for Apps@Work at **Apps > Apps@Work Settings > App Storefront Authentication**.
- Mobile@Work for macOS  
Mobile@Work for macOS **always** uses mutual authentication.
- Windows 10 devices  
Windows 10 devices **always** uses mutual authentication.

## When devices use mutual authentication

Whether devices use mutual authentication depends on:

- The device platform
- Whether mutual authentication was enabled before upgrade
- Whether mutual authentication is enabled after upgrade
- Whether mutual authentication is enabled after a new installation
- For Mobile@Work for iOS, the version of Mobile@Work

The following table summarizes when devices use mutual authentication and the port they use in communication with Core.

TABLE 4. CORE MUTUAL AUTHENTICATION (MA) SETTING IMPACT TO DEVICE COMMUNICATION

	<b>New Core installation</b>  <b>or</b> <b>Core upgrade in which: MA setting was NOT enabled before upgrade</b>	<b>New Core installation in which you enable MA setting after installation.</b>  <b>or</b> <b>Core upgrade in which: MA setting was NOT enabled before upgrade but you enable it after the upgrade.</b>	<b>Core upgrade in which: MA setting WAS enabled before upgrade</b>
<b>Mutual authentication setting</b>	Not enabled	Enabled	Enabled
<b>Device client</b>			
<b>Android:</b> Mobile@Work  (all Mobile@Work versions that Core supports)	Port: 9997 MA: not used	Devices that register after enabling MA: <ul style="list-style-type: none"> <li>• Port: 443</li> <li>• MA: used</li> </ul> Devices that were already registered: <ul style="list-style-type: none"> <li>• Port: 9997</li> <li>• MA: not used.</li> </ul>	Port: 443 MA: used
<b>iOS:</b> Mobile@Work 9.8 or supported newer versions	Port: 9997 MA: not used	Devices that register after enabling MA: <ul style="list-style-type: none"> <li>• Port: 443</li> <li>• MA: used</li> </ul> Devices that were already registered: <ul style="list-style-type: none"> <li>• Port: 9997</li> <li>• MA: not used.</li> </ul>	Devices that register after enabling MA: <ul style="list-style-type: none"> <li>• Port: 443</li> <li>• MA: used</li> </ul> Devices that were already registered: <ul style="list-style-type: none"> <li>• Port: 9997</li> <li>• MA: not used.</li> </ul>
<b>iOS:</b> Mobile@Work versions prior to 9.8	Port: 9997 MA: not used	Port: 9997 MA: not used	Port: 9997 MA: not used

TABLE 4. CORE MUTUAL AUTHENTICATION (MA) SETTING IMPACT TO DEVICE COMMUNICATION (CONT.)

	New Core installation or Core upgrade in which: MA setting was NOT enabled before upgrade	New Core installation in which you enable MA setting after installation. or Core upgrade in which: MA setting was NOT enabled before upgrade but you enable it after the upgrade.	Core upgrade in which: MA setting WAS enabled before upgrade
<b>iOS:</b> iOS MDM check-in	Port: 443 MA: not used	Port: 443 MA: used	Port: 443 MA: used.
<b>macOS:</b> Mobile@Work	Port: 443 MA: used	Port: 443 MA: used	Port: 443 MA: used
<b>macOS</b> macOS MDM agent check-in	Port: 443 MA: not used	Port: 443 MA: used	Port: 443 MA: used
Windows 10	Port: 443 MA: used	Port: 443 MA: used	Port: 443 MA: used



On new Core installations (not upgrades), if you enable mutual authentication **before any devices register**, you can disable port 9997 (in the System Manager in Settings > Port Settings > Sync TLS Port) because it is not used. If devices were registered before enabling mutual authentication, disabling the port causes those devices to not be able to check-in.

## Mutual authentication identity certificate for Core

You provide an identity certificate for Core to use in mutual authentication in the Portal HTTPS certificate. You configure this certificate on the System Manager at **Security > Certificate Mgmt.** The certificate is the identify certificate and its certificate chain, including the private key, that identifies Core, allowing the devices to trust Core. This certificate must be a publicly trusted certificate from a well-known Certificate Authority when using mutual authentication.

## Mutual authentication client identity certificate

You enable mutual authentication for iOS and Android devices in the Admin Portal in **Settings > System Settings > Security > Certificate Authentication.** The certificate enrollment setting specifies how the identity certificate that the device will present to Core is generated.

By default, the certificate enrollment setting for mutual authentication is generated with Core as a local Certificate Authority (CA). Most customers use the default selection. However, if necessary due to your security requirements, you can instead specify a SCEP certificate enrollment setting that you create.

**IMPORTANT:**

- If you use a SCEP certificate enrollment setting for mutual authentication, you cannot use it for any other purpose. For example, you cannot use it in VPN or wi-fi configurations.
- If you use a SCEP certificate enrollment setting that uses an intermediate CA, make sure that all the intermediate CA certificates and the root CA certificate are included in Core's trusted root certificates. See "Managing trusted certificates" in the *Getting Started with Core*
- See:
  - ["Handling client identity certificate expiration for Android devices" on page 327](#)
  - ["Handling client identity certificate expiration for iOS devices" on page 328](#)

## Supported custom attributes for mutual authentication certificates

From Core release 10.8.0.0 through the latest release supported by Ivanti, Core supports only the following list of custom attributes in the **Subject** field for mutual authentication enrollment certificates:

- \$RANDOM\_16\$
- \$RANDOM\_32\$
- \$RANDOM\_64\$
- \$CONFIG\_UUID\$
- \$TIMESTAMP\_MS\$

If, after upgrading to release 10.8.0.0 or supported newer versions, the existing selected mutual authentication certificate includes unsupported attributes, Core will replace them with the value \$RANDOM\_32\$ for new device registrations and for existing device certificate renewals.

The **Admin portal > Settings > System Settings > Client Mutual Certificate Authentication > Certificate Enrollment setting** drop-down menu displays only the Simple Certificate Enrollment Protocol (SCEP) configurations with the five supported custom attributes in the **Subject** field. Configurations with other custom attributes do not display.

## New endpoint for mutual certification authentication

Once mutual authentication is enabled on Core by the administrator, new mutual authentication devices endpoints are available for use by iOS and Android clients. The existing (old) OAuth endpoint is not protected by 2FA or mutual certificate authentication and is vulnerable to password spraying and DOS attacks. There is an option for the administrator to disable the original OAuth endpoint and utilize the new endpoint.



If mutual authentication migration is not enabled, then older client installations will continue to lack mutual authentication functionality.

This feature is applicable on Mobile@Work for Android version 11.1.0.0 and Mobile@Work for iOS version 12.11.10 or supported newer versions.

Below is an example scenario of the old OAuth versus the new endpoint:

TABLE 5. OLD OAUTH VS NEW ENDPOINT

New endpoint	Old OAuth
Not configured	Enabled (old OAuth endpoint works)
Enabled	Enabled (new endpoint works)
Enabled	Disabled (new endpoint works)
Disabled	Disabled (Error)

Note The Following:

You can have mutual certificate authentication on Mobile@Work clients (both iOS and Android) and on the watchOS app, however, it will mean less security. Ivanti does not recommend putting mutual certificate authentication on the watchOS app.

To implement this setup, two endpoints are required:

1. A current OAuth endpoint that can be used by watchOS app, an old or updated Mobile@Work for iOS, OR an old or updated Mobile@Work for Android and cURL script.
2. A new endpoint that will always require mutual certificate authentication.

### Before you begin

- Administrators should have enabled mutual certificate authentication and have migrated all the devices. Check-ins will occur on port 443 and not sync the TLS port 9997.
- Clients need to be upgraded to the version that supports the new endpoint.


### Procedure

1. Go to **Settings > System Settings**.
2. In the left navigational pane, click **Security > Certificate Authentication**.

The Client Mutual Certification Authentication page displays in the right pane.

3. Use the below guidelines to complete this form.

TABLE 6. CLIENT MUTUAL CERTIFICATION AUTHENTICATION

Item	Description
Enable client mutual certificate authentication on Android client, iOS client, iOS and macOS MDM and AppConnect communications	Selecting the check box is a pre-requisite to enabling the new endpoint.
Certificate Enrollment Setting	Select <b>System-Mutual Auth CE</b> from the drop-down.
Enable new OAuth Endpoint with Mutual certificate Authentication	Select this to enable the new endpoint. If this field is greyed out, it means you did not meet the pre-requisite requirements of enabling mutual certificate authentication and migrating all client devices. See <i>Before you begin</i> .
Disable legacy OAuth Endpoint	<p>This should only be done after the client devices have been updated to Mobile@Work for Android version X and Mobile@Work for iOS version X.</p> <ol style="list-style-type: none"> <li>When selecting the Disable legacy OAuth Endpoint box, a confirmation displays. Click <b>Disable</b>.</li> <li>A second confirmation dialog box displays, click <b>Disable</b>.</li> </ol> <p>Once disabled, the WatchOS app will no longer work. This setting can be reversed by de-selecting it.</p> <hr/> <p> Before disabling the legacy OAuth endpoint, make sure that all devices are migrated to the new endpoint.</p> <hr/>

4. Click **Save**.

## Handling client identity certificate expiration for Android devices

Mobile@Work 10.1 for Android handles the expiration of the client identity certificate used for mutual authentication between Mobile@Work for Android and Core. In the Admin Portal, on the sync policy for the device, specify a renewal window for the certificate. The renewal window is a number of days prior to the certificate expiration. When Mobile@Work determines the renewal window has begun, it requests a new certificate from Core.

If Mobile@Work is out of contact with Core during the renewal window, but is in contact again within 30 days after the expiration, Mobile@Work requests a new certificate from Core.

If Mobile@Work is not in contact with Core either during the renewal window or within 30 days after the expiration, the device will be retired and will need to re-register with Core.

Mobile@Work versions prior to 10.1 do not support certificate expiration. When the certificate expires, the device user must re-register Mobile@Work.

### Procedure

1. In the Admin Portal, go to **Policies & Configs > Policies**.
2. Select the appropriate sync policy.
3. For **Mutual Certificate Authentication Renewal Window**, enter the number of days prior to the expiration date that you want to allow devices to renew their identity certificate. Enter a value between 1 and 60.



A blank value defaults to 60 days.

---

4. Click **Save**.
5. Click **OK**.

## Handling client identity certificate expiration for iOS devices

Mobile@Work 11.1.0 for iOS handles the expiration of the client identity certificate used for mutual authentication between Mobile@Work for iOS and Core version 10.3.0.0 or supported newer versions. In the Admin Portal, on the sync policy for the device, specify a renewal window for the certificate. The renewal window is a number of days prior to the certificate expiration. When Mobile@Work determines the renewal window has begun, it requests a new certificate from Core.

If Mobile@Work is out of contact with Core during the renewal window, but is in contact again within 30 days after the expiration, Mobile@Work requests a new certificate from Core.

If Mobile@Work is not in contact with Core either during the renewal window or within 30 days after the expiration, the device will be retired and will need to re-register with Core.

Mobile@Work versions prior to 11.1.0 do not support certificate expiration. When the certificate expires, the device user must re-register Mobile@Work.

### Procedure

1. In the Admin Portal, go to **Policies & Configs > Policies**.
2. Select the appropriate sync policy.



3. For **Mutual Certificate Authentication Renewal Window**, enter the number of days prior to the expiration date that you want to allow devices to renew their identity certificate. Enter a value between 1 and 60.



A blank value defaults to 60 days.

---

4. Click **Save**.
5. Click **OK**.

## Mutual authentication and Apps@Work

Both Apps@Work for Android and Apps@Work for iOS can use mutual authentication.

Apps@Work for iOS uses mutual authentication if you select **Certificate Authentication** at **Apps > Apps@Work Settings > App Storefront Authentication**. It does *not* depend on the mutual authentication setting at **Settings > System Settings > Security > Certificate Authentication**.

However, Apps@Work for Android uses mutual authentication only if you do both of the following:

- Select **Certificate Authentication** at **Apps > Apps@Work Settings > App Storefront Authentication**.
- Enable the mutual authentication setting at **Settings > System Settings > Security > Certificate Authentication**.

### Related topics

- "Setting up Apps@Work for iOS and macOS" in the *Core Apps@Work Guide*
- "Apps@Work in Mobile@Work for Android in the *Core Apps@Work Guide*

## Enabling mutual authentication for Apple and Android devices

The Core mutual authentication setting enables mutual authentication for:

- Mobile@Work for Android
- Apps@Work for Android
  - You must also select **Certificate Authentication** for Apps@Work at **Apps > Apps@Work Settings > App Storefront Authentication**.
  - The device must be using Mobile@Work 10.2.0.0 for Android or supported newer versions.
- Mobile@Work 9.8 for iOS or supported newer versions.
- iOS MDM
- macOS MDM

Note The Following:

- The setting is automatically enabled in the cases described in ["The mutual authentication setting on Core" on page 321](#).
- **After you enable mutual authentication, you cannot disable it.**

### Before you begin

1. As discussed in ["Mutual authentication client identity certificate" on page 324](#), create a SCEP certificate enrollment setting if you do not want to use the default local certificate enrollment setting for mutual authentication. The SCEP setting must select the **Decentralized** option. For details, see ["Certificate Enrollment settings" on page 333](#).



When you enable mutual authentication, change the certificate enrollment selection for mutual authentication **before any more devices register**. Any devices already registered and using mutual authentication will not be able to check-in with Core. Those devices will need to re-register with Core. Note that devices already registered but not using mutual authentication can continue to check-in.

---

2. If you are using iOS devices with the Apps@Work web clip using certificate authentication, change the **Apps@Work Port** field in the System Manager in **Settings > Port Settings**. Ivanti recommends port 7443. However, you can use any port except the port that the Admin Portal uses, which is either 443 or 8443, which you specify in the **MIFS Admin Port** field in the System Manager in **Settings > Port Settings**.

### Procedure

1. In the Admin Portal, go to **Settings > System Settings > Security > Certificate Authentication**.
2. Select **Enable client mutual certification on Android client, iOS client and Apple MDM communication**.
3. In the **Certificate Enrollment Configuration** field, most customers use the default selection. Otherwise, select a SCEP certificate enrollment setting.
4. Click **Save**.

### Related topics

- "Setting up Apps@Work for iOS and macOS" in the *Core Apps@Work Guide*
- "Port settings" in the *Core System Manager Guide*
- "Apps@Work for Android authentication to Core" in the *Core Apps@Work Guide*

## Enabling TLS inspecting proxy support when using mutual authentication

Contact Ivanti Professional Services or an Ivanti certified partner to set up this deployment.

Core can support a TLS inspecting proxy to handle HTTPS requests from your devices to Core when using mutual authentication. For example, you can use a TLS offload proxy such as an Apache or F5 server. This proxy is also known as a Trusted Front End. It intercepts and decrypts HTTPS network traffic and when it determines that the final destination is Core, it re-encrypts and forwards the traffic to Core. The devices that register to Core (using port 443) must send HTTPS requests to the TFE rather than to Core. Also, the TFE must be provisioned with digital certificates that establish an identity chain of trust with a legitimate server verified by a trusted third-party certificate authority.

### Related topics

"Advanced: Trusted Front End" in the *Core System Manager Guide*

## Migrating Mobile@Work for Android to use mutual authentication

For devices that register after enabling mutual authentication, Mobile@Work uses port 443 for device check-ins. However, devices that were already registered continue to use port 9997. You can migrate Mobile@Work for Android from using port 9997 without mutual authentication to using port 443 with mutual authentication. The device users do not need to re-register with Core.

### Before you begin

Instruct Android device users to upgrade to Mobile@Work 10.1 or supported newer versions. Prior Mobile@Work releases do not support migration.

### Procedure

1. In the Admin Portal, go to **Policies & Configs > Policies**.
2. Select the sync policy for the devices that you want to migrate. Select **Edit**.
3. In the Modify Sync Policy dialog box, select **Migrate Mobile@Work Client**.
4. Click **Save**.
5. Click **OK**.

On the next device check-in, Core will send the mutual authentication client identity certificate to the device. In all subsequent device check-ins, the device will use mutual authentication on port 443.

On that first device check-in, the device's **client migration status** changes to **Pending**. After Core has sent the mutual authentication client identity certificate to the device, the **client migration status** changes to **Success**. You can search on this value in the **Client Migration Status** field in **Advanced Search** on **Devices & Users > Devices**.

### Related topics

["When devices use mutual authentication" on page 322](#)

## Certificates settings

Use a certificate setting to upload a trusted public key root certificate or certificate chain. If it is a certificate chain, it can include the root certificate or only intermediate certificates.

**IMPORTANT:** You cannot upload an identity certificate – a certificate that contains a private key – into a certificate setting. To upload an identity certificate to Core, use the certificate enrollment setting called single file identity.

You configure Core to deliver the uploaded certificate or certificate chain to devices so that the devices can trust, for example, specific web services, email servers, or network components like VPN and Wi-Fi.

Two ways are available to deliver the certificate to a device:

- You reference the certificate setting from another Core setting, and apply the appropriate labels to the referencing setting. Only the following settings can reference a certificate setting:
  - An AppConnect app configuration, Web@Work setting, or Docs@Work setting can reference a certificate setting as the value of a key-value pair.
  - A Wi-Fi setting can reference a certificate setting in its **Apply to Certificates** field (used with specific authentication and data encryption values on the Wi-Fi setting).
- You want to deliver a trusted public key certificate directly to a set of devices, without referencing the certificate setting from another setting. In this case, label the certificate setting. This case is less common.

Note The Following:

- When upgrading from a Core prior to Core 9.5.0.0, each certificate setting that contained an identity certificate is automatically converted to a single file identity certificate enrollment setting. Any settings that referenced the certificate setting refer to the new single file identity certificate enrollment setting.
- You cannot import a certificate setting from a Core prior to Core 9.4.0.0 if the certificate setting contained an identity certificate. You must manually create a single file identity certificate enrollment setting.

## Adding a certificate setting

### Procedure

1. Log in to the Admin Portal.
2. Go to **Policies & Configs > Configurations**
3. Click **Add New > Certificates**.

4. Fill in the entries:

- **Name:** Enter brief text that identifies certificate setting.
- **Description:** Enter additional text that clarifies the purpose of this certificate setting.
- **File Name:** Click **Browse** to select the X.509 certificate file (.cer, .crt, .pem, or .der) to upload to Core Core. The certificate must be encoded as binary DER or ASCII PEM.

5. Click **Save**.

Label the certificate setting if you want to deliver the certificate directly to a set of devices, regardless whether it is referenced from another setting. If you are referencing the certificate setting from another setting, label the other setting.

## Certificate Enrollment settings

Certificate enrollment settings are used as follows:

- As part of a larger process of setting up a certificate enrollment server to support authentication for VPN on demand, Wi-Fi, Exchange ActiveSync, AppTunnel and so on.
- To provide devices identity certificates that you uploaded to Core for the case when you want to provide the same identity certificate to many users' devices.
- To provide user-provided certificates to devices when end users use the Core user portal to upload their identity certificates to Core.
- To specify that AppConnect apps on devices use derived credentials.

The available options are:

- **Blue Coat:** Select **Blue Coat** to create a Blue Coat certificate enrollment setting for integrating with the Blue Coat Mobile Device Security service.
- **Client-Provided:** Select **Client-Provided** if you want AppConnect apps to use derived credentials for authentication, digital signing, or encryption.
- **Entrust:** Select **Entrust** if you are using the Entrust Datacard certificate enrollment solution.
- **GlobalSign:** Select **GlobalSign** if you are using GlobalSign as the CA for certificate enrollment.
- **Local:** Select **Local** if you are using Core as the CA.
- **OpenTrust:** Select **OpenTrust** if you are using the OpenTrust integration. See ["Configuring OpenTrust CA" on page 346](#).
- **Single File Identity:** Select **Single File Identity to upload an identity certificate for distribution to devices**.

- **SCEP:** Select **SCEP** for standard certificate-based authentication using a separate CA.



SCEP Configurations created before upgrading to Core 7.0.0.0 or later should be replaced with a new SCEP Configuration. Failure to do so might result in cert renewal failure from Core 9.4.0.0.

---

- **Symantec Managed PKI:** Select **Symantec Managed PKI** if you are using Symantec's Certificate Enrollment solution. See "[Configuring Symantec Managed PKI](#)" on page 354 for more information.
- **Symantec Web Services Managed PKI:** Select **Symantec Web Services Managed PKI** if you are using the Symantec Web Services Managed PKI solution. See "[Configuring Symantec Web Services Managed PKI](#)" on page 356 for more information.
- **User-Provided:** Select **User-Provided** if device users will upload their personal certificates. The user portal includes a certificate upload section for this purpose. A web services API is also available for you to upload user-provided certificates.

## If Certificate Enrollment integration is not an option

If Certificate Enrollment integration is not an option for your organization, consider configuring Core as an intermediate or root CA. See "[Certificate Enrollment settings](#)" on the previous page for more information.

## Supported variables for certificate enrollment

The following variables are supported for the required and optional fields when configuring integration with supported Certificate Authorities (CA's):

- \$EMAIL\$
- \$USERID\$
- \$FIRST\_NAME\$
- \$LAST\_NAME\$
- \$DISPLAY\_NAME\$
- \$USER\_DN\$
- \$USER\_UPN\$
- \$USER\_LOCALE\$
- \$DEVICE\_UUID\$
- \$DEVICE\_UUID\_NO\_DASHES\$
- \$DEVICE\_UDID\$
- \$DEVICE\_IMSI\$

- \$DEVICE\_IMEI\$
- \$DEVICE\_SN\$
- \$DEVICE\_ID\$
- \$DEVICE\_MAC\$
- \$DEVICE\_CLIENT\_ID\$
- \$USER\_CUSTOM1\$
- \$USER\_CUSTOM2\$
- \$USER\_CUSTOM3\$
- \$USER\_CUSTOM4\$
- \$REALM\$
- \$TIMESTAMP\_MS\$
- \$RANDOM\_16\$
- \$RANDOM\_32\$
- \$RANDOM\_64\$
- \$CONFIG\_UUID\$\*

\* This substitution variable works only for the values under the **Subject Alternative Names** section for the following configurations: Entrust, Local, SCEP, Symantec Managed KPI. It is used for Sentry certificate-based tunneling (CBT).

## Certificate generation time

Certificate enrollment settings can be referenced from other settings on Core that require an identity certificate. Some settings that can reference certificate enrollment settings are Exchange settings, Email settings, Wi-Fi settings, VPN settings, AppConnect app configuration settings, Docs@Work settings, and Web@Work settings.

Most certificate enrollment settings cause an identity certificate to be generated. The identity certificate is generated at one of these times:

- ["Early generation" on the next page](#)
- ["On-demand generation" on the next page](#)



Some certificate enrollment settings do not cause an identity certificate to be generated. Specifically, for user-provided certificate enrollment settings and single file identity certificate enrollment settings, the certificate is available on Core. For client-provided certificate enrollment settings, the certificate is available in Mobile@Work.

---

## Early generation

Early generation occurs when you apply a label to a setting that references the certificate enrollment setting. Core generates identity certificates at this time for:

- Exchange settings for Android devices
- Email settings for Android devices
- Wi-Fi settings for Android devices
- VPN settings for Android devices
- AppConnect app configurations
- Docs@Work settings
- Web@Work settings

For each device that has the same label as the setting, Core generates an identity certificate for the device for *each* setting that references the certificate enrollment setting. Core delivers the identity certificate to the device at a later time when Core delivers the setting to the device. Core delivers a setting to a device when the device checks in with Core.



After Core generates an identity certificate, if Core does not send the certificate to a device within 14 days, Core deletes the certificate from its file system. The certificate will be generated on-demand.

---

## On-demand generation

On-demand generation occurs when Core sends a setting that references the certificate enrollment setting to the device. On-demand generation occurs for all settings (that reference a certificate enrollment setting) that are not listed in the early generation list above. A setting, including the certificate, is delivered to a device when the device checks in with Core.

# Configuring a client-provided certificate enrollment setting

This section covers client-provided certificate enrollment settings.

Client-provided certificate enrollment settings are applicable only to iOS and Android devices.

## Overview of client-provided certificate enrollment settings

Derived credentials are identity certificates derived from the certificates on a smart card. The derived credentials are stored on the device in Mobile@Work on iOS devices, and in Secure Apps Manager on Android devices. AppConnect apps on mobile devices can use derived credentials for these purposes:

- authentication to backend servers, such as email servers, web servers, or app servers
- digital signing



- encryption
- decryption of older emails for which the original encryption certificate has expired (iOS only)
- authenticating the user to Standalone Sentry when using AppTunnel with Kerberos authentication to the backend server

You create a client-provided certificate enrollment setting when you want an AppConnect app to use derived credentials for one of these purposes. You then refer to the client-provided certificate enrollment in the appropriate setting.



The certificate enrollment setting is called *client-provided* because Mobile@Work for iOS or Secure Apps Manager for Android, known as *client* apps, provide the identity certificate to the AppConnect app.

---

Only the following settings can refer to a client-provided certificate enrollment setting:

- AppConnect app configuration

It can refer to a client-provided certificate enrollment setting in:

- the value in a key-value pair in its **App-specific Configurations** section
- the identity certificate in its **AppTunnel Rules** section

- Web@Work setting

It can refer to a client-provided certificate enrollment setting in:

- the value in a key-value pair in its **Custom Configurations** section
- the identity certificate in its **AppTunnel Rules** section

- Docs@Work setting

It can refer to a client-provided certificate enrollment setting in:

- the value in a key-value pair in its **Custom Configurations** section
- the identity certificate in its **AppTunnel Rules** section

Make sure the version of Mobile@Work for iOS or the Secure Apps Manager for Android on the device supports client-provided certificate enrollment settings as shown in the following table:

Reference to the client-provided certificate enrollment setting	iOS:  Mobile@Work prior to 8.5	iOS:  Mobile@Work 8.5 and 8.6	iOS:  Mobile@Work 9.0 or supported newer versions	Android:  All versions of Secure Apps Manager supported or compatible with Core
In key-value pairs	Not supported	Supported	Supported	Supported
In AppTunnel rules	Not supported	Not supported	Supported	Not supported

### Related topics

- *Core Derived Credentials Guide*
- *PIV-D Manager App for iOS Release Notes*
- *PIV-D Entrust App for Android Release Notes*

## Specifying a client-provided certificate enrollment setting

To specify a client-provided certificate enrollment setting:

1. Go to **Policies & Configs > Configurations**.
2. Select **Add New > Certificate Enrollment > Client-Provided**.

3. In the New Client-Provided Certificate Enrollment Setting dialog box, use the following guidelines to specify your settings.

Item	Description
Name	Enter brief text that identifies this certificate enrollment setting.
Description	Enter additional text that clarifies the purpose of this certificate enrollment setting.
Select purpose	Select one of the following, depending on the intended use of the client-provided identity certificate: <ul style="list-style-type: none"><li>• <b>Authentication</b></li><li>• <b>Decryption</b></li><li>• <b>Encryption</b></li><li>• <b>Signing</b></li></ul>
Provider	Select the derived credential provider.

4. Click **Save**.

## Configuring an Entrust CA

Core supports integration with the Entrust Administration Services (EAS). This integration allows Core to work with Entrust to obtain certificates directly from the CA.

### Entrust Prerequisites

The information in this section assumes the following:

- You have the URL for your Entrust server (received from Entrust).
- You have the Admin ID and password.

### Procedure

1. Go to **Policies & Configs > Configurations** and click **Add New > Certificate Enrollment > Entrust**.

2. Use the following guidelines to specify the settings.

- **Name:** Enter brief text that identifies this group of settings.
- **Description:** Enter additional text that clarifies the purpose of this group.
- **API URL:** Enter the URL for your Entrust server (received from Entrust).
- **Admin ID:** The credentials to log into the Entrust server.
- **Admin Password:** Enter the Admin Password.
- **Group:** The Entrust group associated with users. Custom attribute variable substitutions are supported.



If the profile you selected contains an iggroup variable, then the you must configure the same value here as well

---

- **Key Usage:** Use these options to filter out the certificates returned by Entrust, which may return multiple certificates with different uses depending on the selected profile.



When multiple certificates are returned by a DigitalID profile, the first one that matches the selected key usage flags is used. If none of the returned certificates match the selected key usage flags, an error is raised. Use the **Issue Test Certificate** feature to ensure the expected certificate is selected.

---

- **Profile:** Use these options to filter out the certificates returned by Entrust, which may return multiple certificates with different uses depending on the selected profile.

Select a profile template from Entrust. Once you select this profile, more options (required and optional variables) are available to you based on the profile you select. Entrust refers to profiles as DigitalIDs.

- **Profile Description:** Pre-populated based on the profile you select.
- **Application Description:** Pre-populated based on the profile you select.
- **Centralized:** Select to allow Core to retrieve certificates on behalf of devices.

**Decentralized:** Select to let managed devices retrieve their own certificates.

This feature is supported on iOS devices only.

- **Store keys on Core:** Specifies whether Core stores the private key sent to each device. When storing keys is enabled, private keys are encrypted and stored on the local Core.
  - If you select this option **after** devices have been provisioned, certificates will be re-provisioned for all impacted devices.

- **User Certificate:** Specifies that the certificate is distributed to multiple devices assigned to a single user.
  - **Device Certificate:** Specifies that the certificate is bound to the given device.
  - **Entrust SCEP CA:**
    - **URL:** Enter the URL of the Entrust SCEP CA.
    - **Key Type:** Select RSA.
    - **Key Length:** Select 1024 or 2048.
  - **Subject Alternative Names table:** Select a type and value. At run-time, these variables are resolved into user values. (See "[Certificate Enrollment settings](#)" on page 333 for more information.) Custom attribute variable substitutions are supported.
3. (Optional) Click **Issue Test Certificate** to verify the configuration by generating a test certificate to ensure there are no errors. Although this step is optional, it is recommended. A real certificate is not generated.
  4. Click **Save**.

NOTE: If values that you enter in fields result in errors, you cannot save the configuration. If values that you enter result in warnings, you can save the configuration after confirming the warning messages. To see configuration errors, go to **Services > Overview**.

## Revoking the certificate

You can revoke an Entrust API Version 9 certificate.

Revoking a certificate adds the certificate to the CRL (Certificate Revocation List). The certificate is also removed from the Entrust manager. When a device authenticates with Core, the system first checks the CRL to verify that the certificate is not on the list. If the certificate is on the list, authentication fails.

To revoke a certificate:

1. Navigate to **Logs > Certificate Management**.
2. Select the certificate that you want to revoke.
3. Select **Actions > Revoke**.

## Configuring a GlobalSign CA

Core supports integration with GlobalSign as a certificate authority (CA) for certificate enrollment. This integration enables GlobalSign to perform the proxy tasks that would normally be performed by Core, allowing the device to obtain certificates from the GlobalSign CA.

## GlobalSign Prerequisites

The information in this section assumes that you have set up the following information with GlobalSign:

- A user name and password for Core to use to access the GlobalSign server
- GlobalSign profiles
- Whether you want the generated certificates to have the enhanced key usage extension Encrypting File System (EFS)
- Whether you want the generated certificates to be the GlobalSign type "personal" or "department"

To specify GlobalSign settings:

1. Go to **Policies & Configs > Configurations** and click **Add New > Certificate Enrollment > GlobalSign**.

2. Use the following guidelines to specify the settings.

- **Name:** Enter brief text that identifies this certificate enrollment setting.
- **Description:** Enter additional text that clarifies the purpose of this certificate enrollment setting.
- **Store keys on Core:** Specifies whether Core stores the private key sent to each device. When storing keys is enabled, private keys are encrypted and stored on the local Core.

If you select this option **after** devices have been provisioned, certificates will be re-provisioned for all impacted devices.

- **User Certificate:** Specifies that the certificate is distributed to multiple devices assigned to a single user.
- **Device Certificate:** Specifies that the certificate is bound to the given device.
- **URL:** Enter the URL for the GlobalSign server. This field defaults to:

<https://system.globalsign.com/cr/ws/GasOrderService>

Typically, you only change this if you are working with a GlobalSign test environment.

- **User Name:** The user name for Core to use to access the GlobalSign server. Custom device and user attributes variable names are supported.
- **Password:** Enter the password then re-enter to confirm. Custom device and user attributes variable names are supported.
- **Profile:** Click **Refresh** to populate the drop-down list of profiles from GlobalSign. Then, select a profile.



You must enter a valid **User Name** and **Password** before clicking **Refresh**.

---

- **Profile Description:** Pre-populated based on the profile you select.
- **Application Description:** Pre-populated based on the profile you select.
- **Product Code:** Select either **EPKIPSPersonal** or **EPKIPSDept**, depending on whether you want the generated certificates to be the GlobalSign type "personal" or "department".
- **Certificate Expiration:** Specify when the generated certificate will expire.
- **EFS option:** Select this setting if you want the generated certificate to have the enhanced key usage extension Encrypting File System (EFS).

Selecting this setting has no impact if the selected profile has disabled EFS.

- **Common Name:** Specify the Common Name to use in the generated certificate.
- **Organization Unit:** Specify the Organization Unit to use in the generated certificate.

- **E-Mail:** Specify the email address to use in the generated certificate.
  - **Subject Alternative Names Value:** Enter a type and value. At run-time, these variables are resolved into user values. Add multiple SAN entries with corresponding values. Click **Add+**, select the SAN type (NT Principal Name) from the drop-down list, then select one of the available values. (See ["Supported variables for certificate enrollment" on page 334](#) for more information.)
3. (Optional) Click **Issue Test Certificate** to verify the configuration by generating a test certificate to ensure there are no errors. Although this step is optional, it is recommended. A real certificate is not generated.
  4. Click **Save**.

NOTE: If values that you enter in fields result in errors, you cannot save the configuration. If values that you enter result in warnings, you can save the configuration after confirming the warning messages. To see configuration errors, go to **Services > Overview**.

## Revoking the certificate

You can revoke a GlobalSign certificate.

Revoking a certificate adds the certificate to the CRL (Certificate Revocation List). The certificate is also removed from the GlobalSign server. When a device authenticates with Core, the system first checks the CRL to verify that the certificate is not on the list. If the certificate is on the list, authentication fails.

To revoke a certificate:

1. Navigate to **Logs > Certificate Management**.
2. Select the certificate that you want to revoke.
3. Select **Actions > Revoke**.

## Configuring Core as the CA

This section describes how to configure Core as the CA.

To specify local settings:

1. Go to **Policies & Configs > Configurations**.
2. Click **Add New > Certificate Enrollment > Local**.



3. Use the following guidelines to specify the settings.

- **Name:** Enter brief text that identifies this group of settings. Example: Local Certificate Settings for Wi-Fi
- **Description:** Enter additional text that clarifies the purpose of this group of settings.
- **Store keys on Core:** Specifies whether Core stores the private key sent to each device. When storing key is enabled, private keys are encrypted and stored on the local Core.

If you select this option **after** devices have been provisioned, certificates will be re-provisioned for all impacted devices.

Select this option for certificates used for email on devices with multi-user sign-in.

- **User Certificate:** Specifies that the certificate is distributed to multiple devices assigned to a single user.

Select this option for certificates used for email on devices with multi-user sign-in.

- **Device Certificate:** Specifies that the certificate is bound to the given device.
- **Local CAs:** Select the name of the self-signed certificate you generated.
- **Key Type:** Specifies the key exchange algorithm used (typically RSA or elliptic curve).
- **Subject:** Enter an X.509 name represented as an array of OIDs and values.

See ["Supported variables for certificate enrollment" on page 334](#) for more information.

- **Subject Common Name Type:** Select the CN type specified in the certificate template. If you enter the \$USER\_DN\$ variable in the Subject field, select **None** from the drop-down list.
- **Key Usage:** Specify acceptable use of the key (signing and/or encryption).
- **Key Length:** Select a Key Length.

The values are 1024, 1536, 2048 (the default), 3072, and 4096.

- **CSR Signature Algorithm:** Select the signature algorithm.

The values are SHA1, SHA256, SHA384 (default), and SHA512.

- **Subject Alternative Names table:** Enter a type and value. At run-time these variables are resolved into user values.

See ["Supported variables for certificate enrollment" on page 334](#) for more information.

4. (Optional) Click **Issue Test Certificate** to verify the configuration by generating a test certificate to ensure there are no errors. Although this step is optional, it is recommended. A real certificate is not generated.
5. Click **Save**.

NOTE: If values that you enter in fields result in errors, you cannot save the configuration. If values that you enter result in warnings, you can save the configuration after confirming the warning messages. To see configuration errors, go to **Services > Overview**.

## Revoking the certificate

You can revoke a local certificate.

Revoking a certificate adds the certificate to the CRL (Certificate Revocation List). When a device authenticates with Core, the system first checks the CRL to verify that the certificate is not on the list. If the certificate is on the list, authentication fails.

To revoke a certificate:

1. Navigate to **Logs > Certificate Management**.
2. Select the certificate that you want to revoke.
3. Click **Actions > Revoke**.

## Configuring OpenTrust CA

Core supports integration with the OpenTrust Mobile Provisioning Server (MPS). This integration enables OpenTrust to perform the proxy tasks that would normally be performed by Core. The following describes the configuration in Core.

Note The Following: Compatibility notes

- This integration does not support the pushing Certificate Authorities Bundles to devices, which is offered by OpenTrust.
- Core supports one certificate per OpenTrust configuration. OpenTrust supports creating profiles having multiple credentials (called application in the OpenTrust context).

### Before you begin

The information in this section assumes the following:

- You have the URL for your OpenTrust cloud instance.
- You have the client-side JSON connector identity certificate Core will use to authenticate to the MPS.
- You have implemented a centralized OpenTrust cloud.
- You have created a Mobile Management Profile on MPS containing a single centralized credential.

### Procedure

1. Go to **Policies & Configs > Configurations** and click **Add New > Certificate Enrollment > OpenTrust**.

2. Use the following guidelines to specify the settings:

**NOTE:** Although optional fields are not required by OpenTrust, they are still used if present. Therefore, you must still specify the appropriate variable for each optional field. For example, the phone number might be an optional field because the tablets in your organization do not have phone numbers. However MPS might still use this information to request a certificate from the PKI server if it is present.

- **Name:** Enter brief text that identifies this group of settings.
  - **Description:** Enter additional text that clarifies the purpose of this group.
  - **Store keys on Core:** Specifies whether Core stores the private key sent to each device. When storing key is enabled, private keys are encrypted and stored on the local Core.
  - If you select this option after devices have been provisioned, certificates will be re-provisioned for all impacted devices
  - **User Certificate:** Specifies that the certificate is distributed to multiple devices assigned to a single user.
  - **Device Certificate:** Specifies that the certificate is bound to the given device.
  - **API URL:** Enter the URL for the OpenTrust server.
  - **Certificate 1:** This is the name of the uploaded certificate.
  - **Password 1** (Optional): This password is optional.
  - **Add Certificate:** Click this link to add one or more certificates, as necessary.
  - **Profile:** This is the MPS Mobile Profile to use for the integration. If you do not see an expected profile, then it most likely contains multiple credentials, a configuration that Core does not currently support.
  - **Profile Description:** This is pre-populated based on the profile you select.
  - **Application Description:** This is populated automatically with the corresponding OpenTrust content associated with the selected profile.
3. (Optional) Click **Issue Test Certificate** to verify the configuration by generating a test certificate to ensure there are no errors. Although this step is optional, it is recommended. A real certificate is not generated.
4. Click **Save**.

**NOTE:** If values that you enter in fields result in errors, you cannot save the configuration. If values that you enter result in warnings, you can save the configuration after confirming the warning messages. To see configuration errors, go to **Services > Overview**.

## Revoking the certificate

You can revoke a OpenTrust certificate.

Revoking a certificate adds the certificate to the CRL (Certificate Revocation List). The certificate is also removed from the OpenTrust manager. When a device authenticates with Core, the system first checks the CRL to verify that the certificate is not on the list. If the certificate is on the list, authentication fails.

### Procedure

1. Navigate to **Logs > Certificate Management**.
2. Select the certificate that you want to revoke.
3. Click **Actions > Revoke**.

## Configuring a single file identity certificate enrollment setting

Use a single file identity certificate enrollment setting to upload an identity certificate to Core for distribution to devices. A typical use case for a single file identity certificate is using the certificate to authenticate devices to a network server, such as:

- Standalone Sentry  
When device authentication on Standalone Sentry is configured as Group Certificate, you typically distribute the same identity certificate to multiple devices.
- a Wi-Fi network component  
When you configure a Wi-Fi setting to use TLS or TTLS for its EAP type, you can distribute the same identity certificate to multiple devices.
- a VPN network component  
When you configure a VPN setting, depending on the type of VPN setting, you can use certificate-based authentication. For the authentication, you can distribute the same identity certificate to multiple devices.

You can upload either:

- An identity certificate.  
The certificate is a PKCS 12 certificate which contains exactly one private key. It is a .p12 or .pfx file. The file can optionally include the certificate chain. The certificate chain can include only intermediate certificates, or intermediate certificates through the root certificate. The root certificate is not necessary if it is from a well known certificate authority.  
You also provide the password for the identity certificate's private key.
- Multiple files, which include among them:
  - the private key and its password.
  - the public certificate.
  - the supporting certificates in the certificate chain. The root certificate is not necessary if it is from a well known certificate authority.

- Examples of combinations you can upload are:
  - a .p12 or .pfx file containing a an identity certificate and its private key and password, plus additional .pem files containing the intermediate certificates.
  - a .pem file containing the private key and password, a .pem file containing the public certificate, plus additional .pem files containing the intermediate certificates.

## Procedure

1. Log in to the Admin Portal.
2. Go to **Policies & Configs > Configurations**
3. Click **Add New > Certificate Enrollment > Single File Identity**.
4. Fill in the entries:
  - **Name:** Enter brief text that identifies certificate enrollment setting.
  - **Description:** Enter additional text that clarifies the purpose of this certificate enrollment setting.
  - **Certificate 1:** Click **Browse** to select the .p12 or .pfx file of the identity certificate, if you are uploading only one file.
  - If you are uploading multiple files, select the file (.p12, .pfx, or .pem) that contains the private key.
  - **Password 1:** Enter the password for the certificate's private key.
5. If you are uploading multiple files, click **Add Certificate** to add another file.
6. Fill in the entries:
  - **Certificate 2:** Click **Browse** to select the .pem file to upload to Core Core. The certificate must be formatted as binary DER or ASCII PEM.
  - **Password 2:** The Password field is applicable only for the file that contains the private key.
7. Optionally, click **Add Certificate** to add another file.
8. Click **Save**.

After you save the single file identity certificate enrollment setting, you can view or change the certificate by editing the setting.

## Configuring SCEP

This section describes how to specify settings that allow the device to obtain certificates from a certificate authority (CA) using Simple Certificate Enrollment Protocol (SCEP).

To specify the SCEP settings:

1. Go to **Policies & Configs > Configurations** and click **Add New > Certificate Enrollment > SCEP**.

2. Use the following guidelines to specify the settings:

- **Name:** Enter brief text that identifies this group of settings.
- **Description:** Enter additional text that clarifies the purpose of this group.
- **Centralized:** Core retrieves certificates on behalf of devices. Core also manages the certificate lifetime and triggers renewals. See [""SCEP proxy functions" on page 354"](#).



Select this option for certificates used for email on devices with multi-user sign-in.

---

- **Decentralized:** Devices retrieve their own certificates.

Use this feature if using the SCEP setting for mutual authentication. It is not supported for any other use cases with Android/iOS and macOS devices. See ["Enabling mutual authentication for Apple and Android devices" on page 329](#).

This feature is not available for Android devices.

- **Store keys on Core:**

Specifies whether Core stores the private key sent to each device. When storing key is enabled, private keys are encrypted and stored on the local Core.

If you select this option after devices have been provisioned, certificates will be re-provisioned for all impacted devices.



Select this option for certificates used for email on devices with multi-user sign-in.

---

- **Proxy requests through Core:**

This feature is not available for Android devices.

When this option is enabled, Core acts as a reverse proxy between devices and the target certificate authority. This option is only available when **Decentralized** is selected.

- **User Certificate:** Specifies that the certificate is distributed to multiple devices assigned to a single user.



Select this option for certificates used for email on devices with multi-user sign-in.

---

- **Device Certificate:** Specifies that the certificate is bound to the given device.
- **URL:** Enter the URL for the SCEP server.
- **CA-Identifier:** (Optional) Enter the name of the profile for SCEP servers that support named-profiles.

- **Subject:** Enter an X.509 name represented as a comma-separated array of OIDs and values. Typically, the subject is set to the user's fully qualified domain name. For example,

C=US,DC=com,DC=MobileIron,OU=InfoTech or

CN=www.mobileiron.com.

You can also customize the Subject by appending a variable to the OID. For example,

CN=www.mobileiron.com-\$DEVICE\_CLIENT\_ID\$.

For ease of configuration you can also use the \$USER\_DN\$ variable to populate the Subject with the user's FQDN.

- **Subject Common Name Type:** Select the CN type specified in the certificate template. If you enter the \$USER\_DN\$ variable in the Subject field, select None from the drop-down list.
- **Key Usage:** Specify acceptable use of the key by signing.
- **Encryption:** Specify acceptable use of the key by encryption.
- **Key Type:** Specify the key type.
- **Key Length:** The values are 1024, 1536, 2048 (the default), 3072, and 4096.
- **CSR Signature Algorithm:** The values are SHA1, SHA256, SHA384 (default), and SHA512.
- **Finger Print:** The finger print of the CA issuing the root certificate.
- **Challenge Type:** Select **None**, **Microsoft SCEP**, or **Manual** to specify the type of challenge to use. The Challenge Type will depend on what the NDES server is configured to use.
- **Challenge URL:** For a Microsoft SCEP challenge type, enter the URL of the trustpoint defined for your Microsoft CA.
- **User Name:** Enter the user name for the Microsoft SCEP CA.
- **Password:** Enter the password for the Microsoft SCEP CA.
- **Subject Alternative Names Type:** Select NT Principal Name, RFC 822 Name, or None, based on the attributes of the certificate template. You can enter four alternative name types.



If this SCEP setting is for authenticating the device to the Standalone Sentry using an identity certificate: select NT Principal Name and select Distinguished Name for a second Subject Alternative Name

---



- **Subject Alternative Names Value:** Select the Subject Alternate Name Value from the drop-down list of supported variables. You can also enter custom variables in addition to and instead of the supported variables.



If this SCEP setting is for authenticating the device to the Standalone Sentry using an identity certificate: enter \$USER\_UPN\$ for the value corresponding to NT Principal Name and enter \$USER\_DN\$ for the value corresponding to Distinguished Name.

3. (Optional) Click **Issue Test Certificate** to verify the configuration by generating a test certificate to ensure there are no errors. Although this step is optional, it is recommended. A real certificate is not generated.
4. Click **Save**.

You cannot make changes to the saved SCEP settings. When you open a saved SCEP setting, the **Save** button is disabled.



If values that you enter in fields result in errors, you cannot save the configuration. If values that you enter result in warnings, you can save the configuration after confirming the warning messages. To see configuration errors, go to **Services > Overview**.

## X.509 Codes

The Subject field uses an X.509 distinguished name. You can use one or more X.509 codes, separated by commas. This table describes the valid X.509 codes:

TABLE 1. X.509 CODES

Code	Name	Type	Max Size	Example
C	Country/Region	ASCII	2	C=US
DC	Domain Component	ASCII	255	DC=company, DC=com
S	State or Province	Unicode	128	S=California
L	Locality	Unicode	128	L=Mountain View
O	Organization	Unicode	64	O=Company Name, Inc.
OU	Organizational Unit	Unicode	64	OU=Support
CN	Common Name	Unicode	64	CN=www.company.com



If the SCEP entry is not valid, then you will be prompted to correct it; partial and invalid entries cannot be saved.

## SCEP proxy functions

Choosing to enable SCEP proxy functions has the following benefits:

- A single certificate verifies Exchange ActiveSync, Wi-Fi, and VPN configurations
- There is no need to expose a SCEP listener to the Internet.
- Core can detect and address revoked and expired certificates.

## Configuring Symantec Managed PKI

Symantec Managed PKI support enables you to configure certificate-based authentication. Symantec Managed PKI is a source for certificates that you can reference in a variety of configurations, such as for Exchange, VPN, and AppConnect.

### Prerequisites

- A valid Symantec Verisign Managed PKI account is required.
- (Optional) Get finger print from issuing CA for root certificate.
- One or more client certificate and password from CA.

### Procedure

To specify the Symantec Managed PKI settings:

1. Go to **Policies & Configs > Configurations** and click **Add New > Certificate Enrollment > Symantec Managed PKI**.

2. Use the following guidelines to specify the settings:

- **Name:** Enter brief text that identifies this group of settings.
- **Description:** Enter additional text that clarifies the purpose of this group.
- **Centralized:** Core retrieves certificates on behalf of devices. Core also manages the certificate lifetime and triggers renewals. See ["Using a proxy" on the next page](#).



Select this option for certificates used for email on devices with multi-user sign-in.

---

- **Decentralized:** This feature is not available for Android devices. Devices retrieve their own certificates.
- **Store keys on Core:** Specifies whether Core stores the private key sent to each device. When storing key is enabled, private keys are encrypted and stored on the local Core.

If you select this option **after** devices have been provisioned, certificates will be re-provisioned for all impacted devices.



Select this option for certificates used for email on devices with multi-user sign-in.

---

- **Proxy requests through Core:** This feature is not available for Android devices.
  - When this option is enabled, Core acts as a reverse proxy between devices and the target certificate authority. This option is only available when **Decentralized** is selected.
- **User Certificate:** Specifies that the certificate is distributed to multiple devices assigned to a single user.



Select this option for certificates used for email on devices with multi-user sign-in.

---

- **URL Mode:** Specifies the mode and the corresponding URL supplied by Symantec.
- **CA-Identifier:** Required information supplied by Symantec.
- **Subject:** See ["Supported variables for certificate enrollment" on page 334](#) for more information.
- **Subject Common Name Type:** Select the CN type specified in the certificate template. If you enter the \$USER\_DN\$ variable in the Subject field, select **None** from the drop-down list.
- **Key Usage:** Use these options to indicate which key usage to request from the CA.
- **Key Type:** This is the Key Exchange algorithm: RSA or Elliptic Curve.
- **Key Size:** The values are 1024, 1536, 2048 (the default), 3072, and 4096.
- **CSR Signature Algorithm:** The values are SHA1, SHA256, SHA384 (the default), and SHA512.
- **Finger Print:** The finger print of Symantec Managed PKI.

- **Certificate 1:** Upload for the client authentication with the server.
- **Password 1:** This password is optional. Best used when certificate and password are in separate files.
- **Subject Alternative Names table:** Enter a type and value. At run-time these variables are resolved into user values. (See "[Supported variables for certificate enrollment](#)" on page 334 for more information.)



The Required Fields and Optional Fields for the certificate are displayed based on how the MDM (Web Service Client) profile was set up in the Symantec PKI manager.

---

3. (Optional) Click **Issue Test Certificate** to verify the configuration by generating a test certificate to ensure there are no errors. Although this step is optional, it is recommended. A real certificate is not generated.
4. Click **Save**.



If values that you enter in fields result in errors, you cannot save the configuration. If values that you enter result in warnings, you can save the configuration after confirming the warning messages. To see configuration errors, go to **Services > Overview**.

---

## Using a proxy

Choosing to enable proxy functions has the following benefits:

- A single certificate verifies Exchange ActiveSync, Wi-Fi, and VPN configurations
- There is no need to expose a SCEP listener to the Internet.
- Core can detect and address revoked and expired certificates.

## Configuring Symantec Web Services Managed PKI

Integration with Symantec Web Services Managed PKI version 8.x enables you to configure certificate-based authentication. The following describes how to configure Symantec Web Managed PKI in Core.

## Before you begin

- Set up your account for Symantec Web Services Managed PKI with Symantec.
- Create an MDM (Web Service Client) profile in the Symantec PKI manager that you will use for the Core integration.

### SeatID

Be sure to include the Symantec SeatID as a required certificate profile field. In a Symantec Web Services Managed PKI environment, Symantec uses the SeatID to track the number of seats for billing purposes.

To correctly track the number of seats, the SeatID value in the Core SCEP settings must map to the value you created for the SeatID in the Symantec PKI Manager. For example, if the user's email address is used as the SeatID in Symantec PKI Manager, the Core SCEP settings should map the Core email address attribute to the Symantec SeatID.

Core associates each issued Symantec certificate to a SeatID in the Symantec PKI Manager. If the SeatID does not exist, a new Symantec user account and SeatID is automatically created for the user at the time the certificate is requested.

- Gather the following items:
  - The server address for the Symantec Web Services Managed PKI.  
On Core the default is set to pki-ws.symauth.com.
  - The Registration Authority (RA) certificate Core will use to authenticate to the Symantec CA.

## Procedure

1. Go to **Policies & Configs > Configurations** and click **Add New > Certificate Enrollment > Symantec Web Managed PKI**.

2. Use the following guidelines to specify the settings:



The Required Fields and Optional Fields for the certificate are displayed based on how the MDM (Web Service Client) profile was set up in the Symantec PKI manager.

- **Name:** Enter brief text that identifies this group of settings.
- **Description:** Enter additional text that clarifies the purpose of this group.
- **Store keys on Core:** Specifies whether Core stores the private key sent to each device. If you are using a Symantec profile that is set up to store keys on the Symantec server, you typically do not select this option.



If you select this option after devices have been provisioned, certificates will be re-provisioned for all impacted devices.

- **User Certificate:** Specifies that the certificate is distributed to multiple devices assigned to a single user.

The certificate is revoked when the user is removed from Core.

- **Device Certificate:** Specifies that the certificate is bound to the given device. Make sure the Symantec certificates are unique for each device.

The certificate is revoked when the device is retired from Core.

- a. **API URL:** Enter the server address for the Symantec Web Services Managed PKI (received from Symantec).

The default is set to pki-ws.symauth.com.



Do not add https:// before the server name, and do not add path information after the server name.

Only the hostname of the Symantec CA server should be provided.

- **Certificate 1:** Navigate and select the RA certificate you received from Symantec. This is usually a.p12 file. Enter the password for the certificate when prompted.
- **Password 1:** (Optional if certificate and password are stored in the same file.) Enter the password for the certificate.
- **Add Certificate:** Click this link to add one or more certificates, as necessary.
- **Profile:** This is the profile to be used for the integration. If you do not see an expected profile, then it most likely contains multiple credentials, a configuration that Core does not currently support.
- **Profile Description:** This is pre-populated based on the profile you select.
- **Application Description:** This is populated automatically based on the selected profile.

3. (Optional) Click **Issue Test Certificate** to verify the configuration by generating a test certificate to ensure there are no errors. Although this step is optional, it is recommended. A real certificate is not generated.
4. Click **Save**.



---

If values that you enter in fields result in errors, you cannot save the configuration. If values that you enter result in warnings, you can save the configuration after confirming the warning messages. To see configuration errors, go to **Services > Overview**.

---

## Revoking the certificate

You can revoke a Symantec Web Services Managed PKI certificate.

Revoking a certificate adds the certificate to the CRL (Certificate Revocation List). The certificate is also removed from the Symantec Web Services Managed PKI manager. When a device authenticates with Core, the system first checks the CRL to verify that the certificate is not on the list. If the certificate is on the list, authentication fails.

To revoke a certificate:

1. Navigate to **Logs > Certificate Management**.
2. Select the certificate that you want to revoke.
3. Click **Actions > Revoke**.

## Configuring a user-provided certificate enrollment setting

One user-provided certificate enrollment setting for each purpose

Configure a user-provided certificate enrollment setting for every purpose for which users can upload a certificate (PKCS 12 file) in the user portal. For example, consider a case in which users have three different purposes for providing certificates: S/MIME signing, S/MIME encryption, and authenticating to a backend server. In this case, you create three user-provided certificate enrollment settings.

You provide a display name for each user-provided certificate enrollment setting. The display name you choose is important because the device user sees it in two places:

- in the user portal when deciding what certificate to upload
- In the user portal, the display name is called "configuration". The user's selection associates the uploaded certificate with a user-provided certificate enrollment setting. The user can upload the same certificate, or different certificates, for each display name.
- in Mobile@Work for iOS, when Mobile@Work for iOS prompts the user for the private key password.

- Mobile@Work prompts for the password if a password was not required when the user uploaded the certificate to the user portal. Mobile@Work uses the display name to inform the user about which certificate to provide the password for. For details, see ["The private key password" below](#).

Note The Following:

- The PKCS 12 file must contain the certificate and one private key. Core does not support PKCS 12 files with more than one private key.
- A web services V2 API is also available for uploading user-provided certificates to Core and associating the certificates with a user-provided certificate enrollment setting.
- See the *Core V2 API Guide*.
- The V1 API that uploaded user certificates to Core is no longer available. If you used the V1 API to upload user certificates, Core will continue to use the certificates until either:
  - the user uploads a replacement in the user portal
  - you use the V2 API to upload a replacement

Note that the V1 API associated the user certificate with a certificate type: All, WIFI, VPN, SMIMESIGNING, SMIMEENCRIPTION, EMAIL or EXCHANGE. Although Core still supports using these certificates and their associated type, the user portal does not display these certificates in the user portal.

Core stores the certificate and private key

When the user uploads a user-provided certificate in the user portal, the user uploads a PKCS 12 file. Core stores the file, which includes the certificate and its private key. Core does not remove the PKCS 12 file after delivering it to the user's device. Therefore, if the user registers another device, the PKCS 12 file is available to deliver to the additional device.

The private key password

In each user-provided certificate enrollment setting, you specify whether the user is required to provide a password for the certificate's private key. When a password is required, users must provide a password when using the user portal to upload a certificate associated with this certificate enrollment setting.

**Important: Always require a password unless both of the following are true:**

- The devices that will use the user-provided certificate are iOS devices running Mobile@Work 9.0 or supported newer versions.
- The apps that will use the certificate are AppConnect apps.

When you do not require a private key password when the user uploads a certificate, Mobile@Work for iOS and an AppConnect for iOS app that uses the certificate behave as follows:

1. When the AppConnect app launches, control switches to Mobile@Work for iOS.
2. Mobile@Work prompts the device user for the private key password.



3. The device user enters the password.



---

If the device user exits Mobile@Work without providing the password, when the AppConnect app next launches, Mobile@Work unauthorizes the app, with the reason that the app is missing credentials.

---

4. Control returns to the AppConnect app.

Whether you require a password depends on your security requirements. If a password is required, Core stores the password along with the PKCS 12 file containing the certificate and private key. However, if your security environment requires limiting the password's storage to the device that uses the certificate, then do not require a password.

When the private key of a user-provided certificate is deleted

The private key of a PKCS 12 file, and password if provided, can be deleted from the Core file system.

Whether you want the private key and password deleted from Core depends on your security requirements.

The following mechanisms are available to delete the private key and password:

- A user can delete the private key and password using the user portal.
- A web services API can delete the private key and password.
- You can specify in the Admin Portal that Core deletes private keys and passwords older than some number of days.

**IMPORTANT:** When the private key and associated password is deleted, Core retains the public certificate and maintains an entry in its certificate table so it can track where the certificate is used, when it expires and display information about it in the UI. Without the private key and associated password, Core is unable to use the identity certificate with any new certificate enrollments, AppConnect configuration and devices. Once the private key and associated password is deleted, the user-provided certificate must be uploaded again before it can be used.

Because the certificate without the private key is still available on Core, you can view information about the certificate, such as its expiration date. This information can help you manage devices still using the certificate.

### Related topics

- ["Viewing, replacing, and deleting certificates in the user portal" on page 583](#)
- *Core V2 API Guide*

Specifying the settings for a user-provided certificate enrollment setting

To specify the settings for a user-provided certificate enrollment setting:

1. Go to **Policies & Configs > Configurations** and click **Add New > Certificate Enrollment > User-Provided**.
2. Use the following guidelines to specify the settings:
  - **Name:** Enter brief text that identifies this setting.
  - **Description:** Enter additional text that clarifies the purpose of this setting.
  - **Display Name:** Enter the name that will appear on the user portal where device users upload their certificates. This name also appears in Mobile@Work if Mobile@Work prompts the device user for a certificate's private key password.
  - **Require Password:** This option requires the user to provide a password for the certificate's private key when uploading a certificate associated with this certificate enrollment setting.
  - **Important:** Always require a password except as described in ["The private key password" on page 360](#).
  - **Delete Private Keys After Days:** Select the number of days after a user-provided certificate is uploaded to Core after which Core deletes the private key and, if provided, its password, from Core.  
  
The default is **None**, which means Core does not delete the private key and its password.  
  
The default is **None**, which means Core does not delete the private key and its password.
3. Click **Save**.

# Android shared-kiosk mode overview

For task-worker deployments, companies may offer dedicated Android devices that are customized for a specific user role. Depending on a user's profile, different apps and configurations may be presented on a device. For example, a user in a technical role may have a specific set of apps presented for their use, while another user in a maintenance role may have access to a different set of apps. For more details, see:

- ["Setting up the Android shared-kiosk mode" below](#)
- ["Configuring the Android shared-kiosk mode" on page 365](#)
- ["User experience for staging and shared kiosk users" on page 370](#)
- ["Suggestions for configuring shared-kiosk mode" on page 372](#)

## Setting up the Android shared-kiosk mode

---



Samsung Kiosk mode is deprecated in Android 8.1 and above. You must implement Android kiosk mode instead.

---

For task-worker deployments, companies may offer dedicated Android devices that are customized for a specific user role. Depending on a user's profile, different apps and configurations may be presented on a device. For example, a user in a technical role may have a specific set of apps presented for their use, while another user in a maintenance role may have access to a different set of apps. See the following sections:

The Android shared-kiosk mode acts as an app filter for different groups of users who share devices. A user who is logged in to the shared kiosk is only able to view the apps appropriate for their role. One of the main advantages to the shared-kiosk mode is that you can allow individual user groups access to different sets of apps from the same device. When a user logs out of an Android shared kiosk, their apps and user data, including history, are cleared from the display of the next user who logs onto the device. The shared kiosk requires connectivity to the Core for the user login and logout actions to take effect. In addition, the shared kiosk is only available to Android Enterprise deployments with Managed Google Play accounts.

FIGURE 1. TASK WORKS IN ANDROID SHARED KIOSK MODE



The shared kiosk requires two types of users, a staging user and a shared kiosk user, and at least two policies that correspond to these users. The staging user is used to prompt the login screen to appear on a shared device. In effect, the staging user is the logged out device owner (default owner) when a shared user is not logged into the device. Also, the staging user is a special type of admin user who allows other users to login to the actual kiosk device. After the shared kiosk user logs in successfully, then the staging policy is replaced by a shared kiosk policy. The kiosk user has access to the apps installed on the device according to the policy assigned to it. Although you can create multiple shared kiosk policies, there is only one kiosk policy active on a kiosk device at a time. When the kiosk user logs out of the shared kiosk, the device reverts to the staging user and, consequently, the staging policy.

Since the staging user only has the ability to access the login page, you need to create a staging policy that is dedicated to this user. In contrast, the shared kiosk users are able to access the set of apps that you define in their policy. (Naturally, you also need to install the permitted apps on the shared kiosk devices.) The shared kiosk policy allows you to create a filter of permitted apps from all of the apps you have installed previously. You cannot directly upload apps into an Android-shared-kiosk-mode policy. Often you want to dedicate a shared-kiosk-mode policy to a type of shared kiosk user, or user group, depending on your organization. For example, a company may have day-shift and night-shift employees that have different roles and require access to separate sets of apps. In this case, you need to create a day-shift policy and a night-shift policy.



Android shared kiosk only supports work-managed devices.

## Configuring the Android shared-kiosk mode

To configure the Android shared-kiosk mode, you need to create a staging user role. Then you need to create one kiosk policy for the staging user as well as one or more policies for the shared kiosk users. For example, you can create one policy for managers and another one for employees. Within each policy, you can define the apps that the users, or user group, can access. Then you need to create and add a label to the device. Finally, you need to apply labels to both the staging and shared kiosk policies.



You define user groups with a user group feature, such as LDAP. You cannot define user groups within the Android shared kiosk mode.

To configure the Android shared-kiosk mode, do the following:

1. ["Configuring a staging user" below](#)
2. ["Creating a staging policy for the staging user" on the next page](#)
3. ["Creating a shared-kiosk-mode policy for the shared kiosk users" on page 367](#)
4. ["Creating and Adding labels to Android shared kiosk policies" on page 368](#)
5. ["Applying a label to the staging policy" on page 370](#)
6. ["Applying a label to a shared kiosk policy" on page 370](#)

## Configuring a staging user

The first step in allowing users to access the Android shared-kiosk mode is to assign a user to the staging role. The staging user must have the same login as the person in your organization who registered Mobile@Work during the initial setup of the software. Also, this user needs to have the Google Device Account role. Ivanti suggests that you make this user name easy to distinguish by using a name such as "staging-user."



A Google Device Account applies only to Managed Google Play Accounts and **new** managed devices. The device account allows the staging user to enroll large numbers of managed devices, that is more than ten devices, without applying the limits imposed by Google.

### Procedure

1. In Admin Portal, go to **Devices & Users**. Then select **Users**.
2. Select the check box next to a user.
3. From **Actions**, select **Assign Roles**. The **Assign Role(s)** screen displays.
4. Select the check box next to **Use Google Device Account (for Android enterprise device only)**.
5. Click **Save**.

## Creating a staging policy for the staging user

You need to create a policy that is dedicated to the staging user. This policy is not active until you apply a label to the staging policy.

### Procedure

1. In Admin Portal, go to **Policies & Configs > Policies**.
2. Click **Add New > Android > Android Kiosk Mode**.
3. In the New Android Kiosk App Setting Policy dialog box, enter a **Name** and **Description** for the policy.
4. Select **Active** for the **Status** field to enable this policy.
5. Scroll down to the Kiosk Settings section:
  - **Disable Quick Settings**  
If you select this option, the device does not display the system notification pull-down menu at the top of the shared kiosk screen.  
If you enable the following options, the settings are displayed as menu items in the shared-kiosk mode on the device.
  - **Allow User to Access WIFI Settings**. This is an optional setting.
  - **Allow User to Access Bluetooth Settings**. This is an optional setting.
  - **Allow User to Access Location Settings**. This is an optional setting.
  - Enter a 4 - 6 digit PIN in the **Kiosk Exit PIN** field.  
You can assign a pin to the staging user kiosk policy. However, it is not mandatory. Without a kiosk exit pin, the staging user cannot exit the kiosk mode .
  - Select the **Enable Shared Device** check box. This is a mandatory setting. By default, the **Enable Login (Only for Staging user)** radio button is selected. Check that this option is selected.
6. Scroll up to the Kiosk Branding section, customize the kiosk with a background color and background image if desired.
  - Use the pull-down menu below the **Background Color** field to select the background color of the kiosk screen.
7. Click **Save**.

## Creating a shared-kiosk-mode policy for the shared kiosk users

You want to create one or more policies for the shared kiosk user who has access to the apps on the shared device based on their assigned policies. Each shared kiosk policy specifies a different set of apps available to the assigned user or user groups. For example, one policy could be for day-shift workers and a second one for night-shift workers. Also within these policies, you may want to configure branding to customize the device. This policy is not active until you apply a label to the shared kiosk policy.



You need to install any apps that you wish to include in the kiosk using the App Catalog page before you begin this procedure. You cannot install apps from within the shared-kiosk -mode policy. You can only use the shared-kiosk -mode policy to setup which apps are displayed.

### Procedure

1. Go to **Policies & Configs > Policies**
2. Click **Add New > Android > Android Kiosk Mode**.
3. Enter a **Name** and **Description** for the policy.
4. Select **Active** for the **Status** field to turn on this policy.
5. Scroll down to the Kiosk Settings section, select:
  - **Disable Quick Settings**  
If you select this option, the device does not display the system notification pull-down menu at the top of the shared kiosk screen.  
If you enable the following options, the settings are displayed as menu items in the shared-kiosk mode on the device.
  - **Allow User to Access WIFI Settings**. This is an optional setting.
  - **Allow User to Access Bluetooth Settings**. This is an optional setting.
  - **Allow User to Access Location Settings**. This is an optional setting.
  - Select the **Enable Shared Device** check box and then click the **Enable Logout** radio button. This is a mandatory setting.
  - Use the arrows next to the **Logout user if session exceeds** field to select the number of hours before a shared kiosk user is automatically logged out of the kiosk device. This is an optional setting.

6. In the **Choose Apps** section, select the app or apps that will be available to the shared kiosk user.



The built-in apps must be enabled in Device Owner mode. This may not be the case with all manufacturers.

- Add the permitted apps to the **Kiosk Mode Allowed App** section.
- Click **+Add** in the Built-in Apps to add apps such as the Built-in Camera or Built-In Dialer to the **Kiosk Mode Allowed Apps**.
- Add apps from the **Built-in Apps** section by clicking **+Add**.
- Add apps from the **App Catalog Apps** section by clicking **+Add**.
- Add apps manually by entering a Package ID in the **Manually Add Apps with Package ID** field. Then click **+Add**.

The order that the apps appear in the **Kiosk Mode Allowed Apps** section, reflects how they appear on the user screen. To change the position of an app on the screen, change its position in the **Kiosk Mode Allowed Apps** list by selecting it and dragging it up or down.



To hide an app, select an app in the **Kiosk Mode Allowed Apps** section and click the eye icon. To ensure the selected app is reinstalled when the user logs out, clearing user session and data, select the Enable force reinstall on Logout icon (which resembles a sheet of paper). You may want to select this icon for apps that contain sensitive data and for apps that do not support managed app configurations.

7. Scroll up to the Kiosk Branding section, customize the kiosk with a banner, background color, or background image as desired.
8. Click **Save**.

## Creating and Adding labels to Android shared kiosk policies

After you create the staging policy and one or more shared kiosk policies, you need to create and add a filtered label to the policies to push the configuration to the target devices. You must create a label for the staging user and each of the shared kiosk users.

### Procedure

1. Go to **Devices & Users > Labels**.
2. Click **Add Label**. The "Add a label" page is displayed.
3. Enter a name and description of the label.
4. Click the **Filter** radio button.



5. Create a rule for the label based on the type of user logged into the device. In the Criteria section, use the **Field**, **Operator**, and **Value** fields (or enter the rule in the **Type search expression here** field):

- **Field:** Enter the user id as "user.user\_id".
- **Operator:** Enter "Equals" or some other operator to return a single username.
- **Value:** Enter the user account name

Here is an example of a rule for a staging user:

"user.user\_id" = "<StagingUsername>" AND common.retired = "false"

See the following image for an example of a rule for a kiosk user:

**Add Label**

Name: DonaldDay

Description: Applies the DonaldDay Kiosk when user DonaldDay logs in

Type: ☐ Manual ☒ Filter

**Criteria**

of the following rules are true

User ID: [v] Equals: [v] DonaldDay

"user.user\_id" = "DonaldDay"

For more information about field definitions, see ["Device field definitions" on page 80](#).

6. Click **Save**.
7. Apply this label to the related policy. See the following sections.



The Display Name field on the "Add a label" page changes to reflect the user logged in. This is how the Filtered Label distinguishes which Kiosk Policy is applied.

## Apply labels to Android shared kiosk policies

After you create the staging policy and one or more shared kiosk policies, you need to apply a label to the policies to push the configuration to the target devices.



You must assign mutually exclusive labels to the staging and shared kiosk policies. In other words, the labels cannot resolve to a device that could be assigned to both policies at the same time. If that situation occurs, the policy with the higher priority is assigned to the device.

---

## Applying a label to the staging policy

The label must contain local users or LDAP user group information (or some way of associating the target users). These are the users that will use the policy.

### Procedure

1. Go to **Policies & Configs > Policies**.
2. Select the check box next to the staging policy.
3. Select **Actions > Apply to Label**. The Apply to Label dialog box opens.
4. Select the check box next to the label.
5. Click **Apply**.

## Applying a label to a shared kiosk policy

The label must contain local users or LDAP user group information. These are the users that will use the policy.

### Procedure

1. Go to **Policies & Configs > Policies**.
2. Select the check box next to the shared kiosk user policy.
3. Select **Actions > Apply to Label**. The Apply to Label screen dialog box opens.
4. Select the check box next to the label.
5. Click **Apply**.
6. If needed, repeat the procedure to assign an additional label to another shared kiosk policy.

## User experience for staging and shared kiosk users

The staging and shared kiosk users have different user experiences when logging in and out of the kiosk. If you have defined a pin in the staging kiosk policy, the staging user has access to the Exit Kiosk menu command within **Settings**. However, the shared kiosk user has access to their permitted apps as well as to the **Logout Kiosk** command.



Both the login and logout operations must be done when the device is online which allows a connection to the Core server during these operations.

---

## Staging user experience

### Procedure


1. Click the **Mobile@Work** menu on the device and then select **Kiosk** to put the device into kiosk mode. The banner and background image are displayed on the screen of the staging user if they have been configured.
2. Click the **Settings** icon--the **Exit Kiosk** command as well as the **WIFI, Bluetooth, and Location Settings** options are displayed.
3. To exit the kiosk, select **Settings** icon and then select **Exit Kiosk**. Then you are prompted to enter a pin.
4. After you enter the pin, the shared kiosk mode is released and the Android home screen is displayed. See the following ["Android shared-kiosk login screen example" below](#).

---

**i** To re-engage in shared-kiosk mode, repeat step 1.

---

FIGURE 1. ANDROID SHARED-KIOSK LOGIN SCREEN EXAMPLE



## Shared-kiosk mode user experience

### Procedure

1. The staging login page is displayed.
2. Enter the shared-kiosk user credentials. It can take up to 30 seconds for the login to complete. Then the shared-kiosk screen is displayed. The **Settings** icon as well as the icons of the available apps are displayed on this screen. Any branding settings, such as banner, background color, or background image, are also displayed.
3. Use any of the allowed apps.(The shared kiosk user has access to at least one app.)
4. Click the **Settings** option, and then the **WIFI**, **Bluetooth**, and **Location Settings** options are displayed. along with the **Logout Kiosk** command.
5. To exit, select **Settings > Logout Kiosk** command. Then the staging login page is displayed on the device.

## Monitor Android shared-kiosk mode

While you are setting up the shared-kiosk mode, you may want to verify which user, staging or shared, is logged into a device.

### Procedure

1. Go to **Devices & Users > Devices**.
2. Select the check box next to a shared-kiosk device.
3. Click the **Devices** panel to display users who are currently logged in. When a shared-kiosk user successfully logs in, the display name on the **Devices** panel is updated accordingly.

## Suggestions for configuring shared-kiosk mode

As the administrator, you must ensure that the configuration for staging and shared kiosk users is accurate in regards to placing users in the correct user group. (The Core software cannot verify that a user is included in the correct group for your organization.) In addition, session control for shared-kiosk users is described.



When a user who does not have shared kiosk permission logs into a kiosk, the user receives an error but stays in the staging user mode.

---

## Configuration Example for shared-kiosk mode

See the following figure for an example of a configuration that employs a staging user as well as two shared-kiosk-mode user groups, "User Group "1 and "User Group 2".

FIGURE 1. ANDROID SHARED KIOSK MODE CONFIGURATION EXAMPLE

Configuration			
	Staging User Presents Login screen, entry state.	User Group 1 Set of users with unique set of apps and configs	User Group 2 Set of users with unique set of apps and configs
User	Must set Device Account == TRUE	Any user on Core / Cloud	Any user on Core / Cloud
Device	Enrolled as Managed Device (Device Owner)		
Apps	Common set of apps distributed to all groups		
App configs	Null	App config per-user or per-group	App config per-user or per-group
Kiosk config / policy	Assigned with "Login" == TRUE	Assigned with "Logout" == TRUE Subset of apps; some apps may be "forced re-installed"	Assigned with "Logout" == TRUE Subset of apps; some apps may be "forced re-installed"

## Session Control for shared kiosk devices

You can control the length of a user session in shared kiosk mode using two methods. Within the ["Creating a shared-kiosk-mode policy for the shared kiosk users" on page 367](#) procedure, you can set the number of hours before a shared kiosk user is automatically logged out with the **Logout user** field. After the timeout period is reached, the device triggers a log out on the device and the device returns to the staging user.

Also, you can immediately force a shared kiosk user off the device by forcing a log out with the Shared Kiosk - Sign Out device command.

### Procedure

1. Go to **Devices & Users > Devices**.
2. Select the check box next to a shared-kiosk device.
3. Click **Actions > Android Only > Shared Kiosk - Sign Out**.

# Working with Events

This section addresses the components related to The Event Center.

- ["About events" below](#)
- ["Managing events" below](#)
- ["Event settings" on page 379](#)
- ["Customizing Event Center messages" on page 399](#)
- ["Viewing and Exporting Events" on page 407](#)

## About events

The Event Center enables Core administrators to configure *events* to specific *alerts* that can be sent to users, administrators, or both. Event types include:

- International Roaming Event
- SIM Changed Event
- Memory Size Exceeded Event
- System Event
- Policy Violations Event
- Device Status Event

An alert is a message sent via SMS, email, or through a push notification. You can select a predefined message template, or create a custom message to use for the alert.

For example, you can specify an SMS to be sent each time a user travels to a different country, informing the user that different rates may apply.

## Events page

Use the **Logs > Event Settings** page in Admin Portal to manage the events you are interested in and the corresponding alerts you want to automate.

### Required role

To edit settings on the **Event Settings** page, the administrator must have the **Manage events** role.

## Managing events

The tasks that are common to all event types are:

- ["Creating an event" below](#)
- ["Editing an event" below](#)
- ["Deleting an event" on the next page](#)
- ["Ensuring the alert is sent to the correct recipients" on the next page](#)
- ["Applying the event to a label" on page 377](#)
- ["Setting alert retries" on page 377](#)
- ["Setting device push notifications" on page 378](#)
- ["Android notification sync policy" on page 378](#)

## Creating an event

### Procedure

To create an event, in the Admin Portal:

1. Go to **Logs > Event Settings**.
2. Click **Add New**.
3. Select the type of event from the drop-down.
4. Complete the information for the selected event.

Each event type has settings specific to the event type. See ["Event settings" on page 379](#) for information on the settings.

5. Click **Save**.

## Editing an event

### Procedure

To edit an event, in the Admin Portal:

1. Go to **Logs > Event Settings**.
2. Select the event you want to edit.
3. Click **Edit**.
4. Make your changes.
5. Click **Save**.

## Deleting an event


### Procedure

To delete an event, in the Admin Portal:

1. Go to **Logs > Event Settings**.
2. Select the event you want to delete.
3. Click **Delete**.

## Ensuring the alert is sent to the correct recipients

When you create an event, you designate recipients for the resulting alert. Each event type includes the alert configuration section shown in the following figure.



The screenshot shows the 'Alert Configuration' section of a dialog box. At the top, there is a checkbox labeled 'Generate Alert' which is checked. Below this, the 'Alert Configuration' section includes several settings: 'Alert for Every Country Visited in the Trip' with radio buttons for 'Yes' (selected) and 'No'; 'Maximum Alerts' with radio buttons for 'Unlimited' (selected) and 'Limited' (with an adjacent input field); and 'Severity' with radio buttons for 'Critical', 'Warning' (selected), and 'Information'. There is a 'Template' dropdown menu currently set to 'Default International Roaming Alert template', with 'View' and 'Create' buttons to its right. At the bottom, there are three dropdown menus for 'Send SMS:', 'Send Email:', and 'Send Through APNs:', all of which are currently set to 'User only'.

For each type of alert (i.e. SMS, email, and C2DM push notification), you can select to send the alert to one of the following:

- **None**
- **User only**
- **User + Admin**
- Admin only

If you select one of the Admin options, a **CC to Admins** section is displayed in the dialog box. This section displays a list of devices. Under the Available heading, select a device (or devices), that is associated with an email address that you want to notify, other than the device user. Core will send a notification to the email address associated with the device or devices that appear under the Selected heading.



FIGURE 1. CC TO ADMINS

The screenshot shows a dialog box titled "CC to Admins:". It contains two list boxes. The left list box is labeled "Available" and the right list box is labeled "Selected". Between the two list boxes are two small buttons with arrows: the top one points to the right and the bottom one points to the left. At the bottom of the dialog box are two buttons: "Save" and "Cancel".

---

**i** Only users who have registered devices can appear in the **Apply to Users** list.

---

## Applying the event to a label

To specify the devices to which the event should apply, you select one or more labels when you create the event. The amount of time it takes to apply an event to a label depends on the number of devices identified by the label. Therefore, it may take some time for the label name to display as selected for the event.

## Setting alert retries

You can specify the number of times Core attempts to send an SMS alert or registration email.

### Procedure

1. Enter the number of retries for SMS and registration email.

Reminders are sent at 48-hour intervals until the number of reminders specified are sent, or the device is registered.

For example, if you use the default for **Number of Retries for Email** (which is 2), an email is sent immediately after registration. If the device is not registered within 48 hours, a second email is sent. No other reminders are sent because you specified two reminders.

2. Click **Save**.

## Setting Core SMS, email, and push notifications

You can designate specific hours for the sending of SMS, email, and push notifications. The default notification time is 0300 (3 a.m.), which can be disruptive.

### Procedure

To override the default notification schedule:

1. From the Admin Portal, go to **Settings > System Settings > General > Alert**.
2. Select the **Override Default Schedule SMS, Email, Push notification** check box. The section expands.
3. Enter the notification start time and end time, in UTC hours.
4. Select the days of the week when sending notifications are allowed.
5. Click **Save**.

## Setting device push notifications

The Send Message feature provides device push notification support. The service enables you to:

- Check the validity and CRL of the certificate for every incoming request.
- Check for pending notifications for the device, if not maintain the connection for the configured time.
- Send a response if a pending event has been created.



The notification pushed to the device might include an active URL. This URL can be opened in the Android client by clicking **GO TO LINK** in the notification.

---

### Procedure

1. From the Admin Portal, go to **Device & Users > Devices**.
2. Select the check box for the device.
3. Click **Actions > Send Message**. The **Send Message** dialog appears.
4. Select the **Push Notification** check box.
5. Click **Send Message**.

## Android notification sync policy

The Android Notification Sync Policy allows you to specify the frequency and content of device updates.

### Procedure

To set the Android Notification Sync Policy:

1. Go to **Policies & Configs > Policies**.
2. Click **Add New > Sync** to display the **New Sync Policy** dialog box.  
If there is already an existing Sync policy the **Modify Sync Policy** screen will be displayed.
3. Enter the name of the policy and a description if needed.
4. Enter the name of the ServerIP/Host Name.

5. Select the **Use TLS** check box.
6. Use the **Sync While Roaming** drop-down menu to specify what if any content is synced while the device is roaming.
7. Choose a type of notification using the **Android Notification Mechanism** drop-down menu.
8. Enter a **Hearbeat Interval** in minutes.
9. Enter a **Sync Interval** in minutes.
10. Enter an IOS Location-Based WakeUps Interval in minutes.
11. Enter a **MTD wakeup interval** in minutes. This interval determines how often Mobile@Work wakes up and scans a device. Setting this value to a low interval, such as 5 minutes, is more taxing on the device's battery than setting it at a higher interval such as 30 minutes.
12. Click **Save**.

## Event settings

Each event type has specific settings that need to be configured when you create or edit the event. This section describes the settings for each type.

- ["International roaming event settings" below](#)
- ["SIM changed event settings" on page 382](#)
- ["Memory size exceeded event settings" on page 385](#)
- ["System event settings" on page 388](#)
- ["System event field description" on page 388](#)
- ["Policy violations event settings" on page 391](#)
- ["Policy violations event field description" on page 392](#)
- ["Device status event settings" on page 396](#)

## International roaming event settings



International roaming detection is not supported for dual-mode devices (that is, devices that switch between GSM and CDMA).

---

### Procedure

To create an international roaming event, in the Admin Portal:

1. Go to **Logs > Event Settings**.
2. Click **Add New**.

3. Select **International Roaming Event** from the drop-down menu. The New International Roaming Event dialog box opens.

**New International Roaming Event**

Save | Cancel

Name:

Description:

**Actions**

☒ Generate Alert

**Alert Configuration**

Alert for Every Country: ☒ Yes ☐ No

Visited in the Trip:

Maximum Alerts: ☒ Unlimited ☐ Limited

Severity: ☐ Critical ☒ Warning ☐ Information

Template:  View Create

Send SMS:

Send Email:

Send Through Push Notification:

Apply to Labels:

Available: All-Smartphones, All-Syscomm, Android

Selected:

Search Users:

Save | Cancel

4. Use the following guidelines to create an international roaming event:

Field	Description
Name	Identifier for this notification.
Description	Additional text to clarify the purpose of this notification.
Generate Alert	Turns on/off the alert defined for this event.
Alert for Every Country Visited in the Trip	Applies a compliance action for each country visited after the user leaves the home country.
Maximum Alerts	Specifies whether there is a limit on the number of alerts generated for all countries within a given trip. If you select <b>Limited</b> , then you can specify the number of alerts to allow. Once the user returns to the home country, the count is returned to 0.
Severity	Specifies the severity defined for the alert: <b>Critical</b> , <b>Warning</b> , and <b>Information</b> .
Template	Specifies the template to populate the resulting alert. Click <b>View</b> to display the content of the current template. Select an alternate template from the drop-down or click <b>Create</b> to create a new template.  See <a href="#">"Customizing Event Center messages" on page 399</a> for information on creating a new template.
Send SMS	Specifies whether to send an alert in a text message, and whether to send it to the user, the admin, or both. Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section.  If you select "Admin only" or "User + Admin", then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.
Send Email	Specifies whether to send an alert in an email, and whether to send it to the user, the admin, or both. Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section.  If you select "Admin only" or "User + Admin", then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.
Send through Push Notification	Specifies whether to send a message via, and whether to send it to the user, the admin, or both. Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section.

Field	Description
	<p>If you select “Admin only” or “User + Admin”, then the <b>CC to Admins</b> section displays. Use this section to specify administrative users who should receive the alert.</p> <p>The length of the message is limited to 255 characters.</p>
Apply to Labels	Associate this event with the selected labels. See the “Using labels to establish groups” section in the <i>Getting Started with Core</i> for more information.
Search Users	Enter the user ID to find devices to which you want to apply this event.
Apply to Users	Associate this group of settings with the selected users.
Search Admins	Enter the admin ID to find devices to which you want to apply this event.
CC to Admins	If you selected “Admin only” or “User + Admin”, then the CC to Admins section appears. Use this section to specify administrative users who should receive the alert.

5. Click **Save**.



If more than one international roaming event applies to a device, only the last one you edited and saved is triggered.

---

## SIM changed event settings

To create a SIM changed event, in the Admin Portal:

1. Go to **Logs > Event Settings**.
2. Click **Add New**.

3. Select **SIM Changed Event** from the drop-down menu. The New SIM Changed Event dialog box opens.

**New SIM Changed Event**

Name:

Description:

**Actions**

☒ Generate Alert

**Alert Configuration**

Severity: ☐ Critical ☒ Warning ☐ Information

Template:

Send SMS:

Send Email:

Send Through Push Notification:

Apply to Labels:

Search Users:

Apply to Users:

4. Use the following guidelines for creating a SIM changed event.

Field	Description
Name	Identifier for this event.
Description	Additional text to clarify the purpose of this event.
Generate Alert	Turns on/off the alert defined for this event.
Severity	Specifies the severity defined for the alert: Critical, Warning, and Information.
Template	<p>Specifies the template to populate the resulting alert.</p> <p>Click <b>View</b> to display the content of the current template. Select an alternate template from the drop-down or click <b>Create</b> to create a new template. See <a href="#">"Customizing Event Center messages" on page 399</a> for information on creating a new template.</p>
Send SMS	<p>Specifies whether to send an alert in a text message, and whether to send it to the user, the admin, or both.</p> <p>Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section. If you select "Admin only" or "User + Admin", then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.</p>
Send Email	<p>Specifies whether to send an alert in an email, and whether to send it to the user, the admin, or both.</p> <p>Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section. If you select "Admin only" or "User + Admin", then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.</p>
Send through Push Notification	<p>Specifies whether to send a message, and whether to send it to the user, the admin, or both.</p> <p>Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section. If you select "Admin only" or "User + Admin", then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.</p> <p>The length of the message is limited to 255 characters.</p>
Apply to Labels	Associate this event with the selected labels. See the "Using labels to establish groups" section in <i>Getting Started with Core</i> for more information.



Field	Description
Search Users	Enter the <b>user ID</b> to find devices to which you want to apply this event.
Apply to Users	Associate this group of settings with the selected users.
CC to Admins	If you selected “Admin only” or “User + Admin”, then the <b>CC to Admins</b> section displays. Use this section to specify administrative users who should receive the alert.

5. Click **Save**.



If more than one SIM changed event applies to a device, only the last one you edited and saved is triggered.

---

## Memory size exceeded event settings

This section address how to create a memory size exceeded event.

### Procedure

1. Go to **Logs > Event Settings**.
2. Click **Add New**.

3. Select **Memory Size Exceeded Event** from the drop-down menu.

The screenshot shows a configuration window titled "New Memory Size Exceeded Event". At the top right are "Save" and "Cancel" buttons. The form includes the following fields and sections:

- Name:** A text input field with a red border.
- Description:** A text input field containing the text "Generated when the memory size on the phone exceeds a limit".
- Used Memory Size Exceeds:** A numeric input field set to "80", followed by the label "% of Total Memory Size".
- Actions:** A section with a sub-header "Alert Configuration".
  - ☒ Generate Alert
  - Alert Every: A dropdown menu set to "1 Week".
  - Severity: Three radio buttons labeled "Critical", "Warning" (which is selected), and "Information".
  - Template: A dropdown menu set to "Default Memory Exceeded Alert template", with "View" and "Create" buttons to its right.
  - Send SMS: A dropdown menu set to "User only".
  - Send Email: A dropdown menu set to "User only".
  - Send Through Push Notification: A dropdown menu set to "User only".
- Apply to Labels:** A section with two columns: "Available" and "Selected".
  - The "Available" column contains a list box with the items "All-Smartphones", "All-Syscomm", and "Android".
  - The "Selected" column is currently empty.
  - Arrows between the columns allow for moving items back and forth.
- Search Users:** A text input field with the placeholder "Search by Username" and a magnifying glass icon.
- At the bottom, there is another "Apply to" section with "Available" and "Selected" columns, both of which are currently empty.

At the bottom left of the window are "Save" and "Cancel" buttons.

4. Use the following guidelines to create a memory size exceeded event:

Field	Description
Name	Identifier for this event.
Description	Additional text to clarify the purpose of this notification.
Used Memory Size Exceeds	Specifies the percentage of total memory that triggers the alert.
Generate Alert	Turns on/off the alert defined for this event.
Alert every	Specifies the time, in days, after which the alert count is reset.
Severity	Specifies the severity defined for the alert: <b>Critical</b> , <b>Warning</b> , and <b>Information</b> .
Template	<p>Specifies the template to populate the resulting alert. Click <b>View</b> to display the content of the current template.</p> <p>Select an alternate template from the drop-down or click <b>Create</b> to create a new template.</p> <p>See "<a href="#">Customizing Event Center messages</a>" on page 399 for information on creating a new template.</p>
Send SMS	<p>Specifies whether to send an alert in a text message, and whether to send it to the user, the admin, or both.</p> <p>Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section. If you select "Admin only" or "User + Admin", then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.</p>
Send Email	<p>Specifies whether to send an alert in an email, and whether to send it to the user, the admin, or both.</p> <p>Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section. If you select "Admin only" or "User + Admin", then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.</p>
Send through Push Notification	<p>Specifies whether to send a message, and whether to send it to the user, the admin, or both.</p> <p>Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section. If you select "Admin only" or "User + Admin", then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.</p> <p>The length of the message is limited to 255 characters.</p>

Field	Description
Apply to Labels	Associate this event with the selected labels. See the “Using labels to establish groups” section in <i>Getting Started with Core</i> for more information.
Search Users	Enter the user ID to find devices to which you want to apply this event.
Apply to Users	Associate this group of settings with the selected users.
CC to Admins	If you selected “Admin only” or “User + Admin”, then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.

- Click **Save**.



Memory exceeded events are sent only once per week when the configured memory limit is reached. If more than one memory size exceeded event applies to a device, only the last one you edited and saved is triggered.

## System event settings

A system event applies a compliance action when a component of a Core implementation is not working. System alerts are intended for relevant administrators.

### Procedure

- In the Admin Portal, go to **Logs > Event Settings**.
- Click **Add New**.
- Select **System Event** from the drop down menu.
- Use the guidelines in "[System event field description](#)" below to complete the form:
- Click **Save**.

## System event field description

TABLE 1. SYSTEM EVENT FIELD DESCRIPTIONS

Field	Description
Name	Identifier for this event.
Description	Additional text to clarify the purpose of this notification.
Sentry (standalone and integrated) is unreachable	Applies a compliance action if Core is unable to contact the Sentry.


TABLE 1. SYSTEM EVENT FIELD DESCRIPTIONS (CONT.)

Field	Description
MobileIron gateway is unreachable	Select this option to send an alert if Core cannot connect to the Core gateway.
LDAP server is unreachable	Select this option to send an alert if Core cannot connect to any of the configured LDAP servers.
DNS server is unreachable	Select this option to send an alert if Core cannot connect to one of the configured DNS servers.
Mail server is unreachable	Select this option to send an alert if Core cannot connect to the configured SMTP server.
NTP server is unreachable	Select this option to send an alert if Core connect to the configured NTP server.
Certificate Expired or Certificate Error	Select this option to send an alert for certificate expiration. An alert is sent 60 days before expiration and on the expiration date. Certificates supported include Admin Portal and device certificates.
Provisioning Profile Expired	This feature is not supported for Android devices.
SMTP Relay server is unreachable	Applies a compliance action if the configured SMTP relay (used for SMS archive) does not respond to a ping or SMTP ping.
SMTP Relay server error	Applies a compliance action if the configured SMTP relay (used for SMS archive) returns an error. The alert includes available details to enable troubleshooting.
System storage threshold has been reached	Applies a compliance action if the system storage threshold has been reached.  Refer to <i>Core System Manager Guide</i> for information on setting this threshold or manually purging the data.
Connector state events	Applies a compliance action if the health of the Connector changes.  Core defines a healthy connector as one that connects to the server at expected intervals and syncs successfully with the LDAP server. An alert is generated if a Connector changes from healthy to unhealthy, or from unhealthy to healthy.
Connector requires upgrade	Applies a compliance action if the automated upgrade of the Connector fails. This alert prompts you to manually upgrade the Connector.
Connector can not connect to LDAP server	Applies a compliance action if a configured LDAP server is no longer reachable.

TABLE 1. SYSTEM EVENT FIELD DESCRIPTIONS (CONT.)

Field	Description
Connector is unreachable	Applies a compliance action if the Core server does not receive the expected response to the scheduled probe of the Connector.  This alert generally indicates network problems.
Application update failed	Alerts the administrator that the Apps@Work or Bridge update for Windows failed. For more information, administrators can the server logs.
Android enterprise app requires new permission approval	Generates an alert if an Android Enterprise app has new permissions that the administrator needs to approve in the App Catalog.
Mobile Threat Definition Update	Alerts administrators when a new version of the mobile threat definition is available. The notification includes any impacts to the existing MTD Local Action policies if threats were removed from the latest update.
Generate Alert	Turns on/off the alert defined for this event.
Maximum Alerts	Specifies whether there is a limit on the number of alerts generated for a given event. If you select <b>Limited</b> , then you can specify the number of alerts to allow. By default, compliance is checked every 24 hours. See <a href="#">"Managing Compliance" on page 165</a> and <a href="#">"Creating an event" on page 375</a> for more information.
Alert Every	Specifies the time, in days, after which the alert count is reset.
Severity	Specifies the severity defined for the alert. Select <b>Critical</b> , <b>Warning</b> , or <b>Information</b> .
Template	Specifies the template to populate the resulting alert. Click <b>View</b> to display the content of the current template.  Select an alternate template from the drop-down or click <b>Create</b> to create a new template. See <a href="#">"Customizing Event Center messages" on page 399</a> for information on creating a new template.
Send SMS	Specifies whether to send an alert in a text message, and whether to send it to the user, the administrator, or both. Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section. If you select "Admin only" or "User + Admin", then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.

TABLE 1. SYSTEM EVENT FIELD DESCRIPTIONS (CONT.)

Field	Description
Send Email	Specifies whether to send an alert in an email, and whether to send it to the user, the administrator, or both. Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section. If you select “Admin only” or “User + Admin”, then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.
Send through Push Notification	<p>Specifies whether to send a message via Android C2DM, and whether to send it to the user, administrator, or both.</p> <p>Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section. If you select “Admin only” or “User + Admin”, then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.</p> <p>The length of the message is limited to 255 characters.</p>
Apply to Labels	<p>Send the alert to users in the selected labels. See the “Using labels to establish groups” section in <i>Getting Started with Core</i> for more information.</p> <hr/> <p> In most cases, if you do select a label, it should not be a label with broad coverage. System event alerts are usually not appropriate for device users.</p> <hr/>
Search Users	Enter the <b>user ID</b> to find users to which you want to send the alert.
Apply to Users	Send the alert to the selected users.

## Policy violations event settings

### Procedure

1. In the Admin Portal, go to **Logs > Event Settings**.
2. Click **Add New**.

3. Select **Policy Violation Event** from the drop- down menu. The New Policy Violations Event dialog box opens.

4. Follow the guidelines in "[Policy violations event field description](#)" below to complete the form.
5. Click **Save**.



**Apply only one Policy Violations event to each device.** If more than one policy violations event applies to a device, only the last one you edited and saved is triggered. Therefore, do not create a separate policy violations event for each type of security policy violation.

In that one Policy Violations event, select all of the security policy settings that you want to trigger the event. Use the template variable `$DEFAULT_POLICY_VIOLATION_MESSAGE` in your message template to specify the security policy violation that triggered the event.

## Policy violations event field description

The following table describes fields for configuring a policy violation event.



TABLE 2. POLICY VIOLATION EVENT FIELD DESCRIPTION

Field	Description
Name	Identifier for this event.
Description	Additional text to clarify the purpose of this notification.
<b>Connectivity</b>	
Out-of-contact with Server for X number of days	Select this option to send an alert when a device has been out of contact for the number of days specified in the Security policy assigned to it.
Out-of-policy for X number of days	Select this option to send an alert when a policy has been out of date for the number of days specified in the Security policy assigned to it.
<b>Device Settings</b>	
Passcode is not compliant	Applies a compliance action if a device is detected having a passcode that does not meet the requirements specified in the associated security policy.
<b>App Control</b>	
Disallowed app found	Applies a compliance action if an app that is specified as Disallowed is installed on a device.  Apps are specified as <b>Required</b> , <b>Allowed</b> , or <b>Disallowed</b> under <b>Apps &gt; App Control</b> .
App found that is not in Allowed Apps list	Applies a compliance action if an app that does not appear on the list of allowed apps has been detected on a device.  Apps are specified as <b>Required</b> , <b>Allowed</b> , or <b>Disallowed</b> under <b>Apps &gt; App Control</b> .
Required app not found	Applies a compliance action if an app that is specified as Required is not installed on a device.  Apps are specified as <b>Required</b> , <b>Allowed</b> , or <b>Disallowed</b> under <b>Apps &gt; App Control</b> .
<b>Data Protection/Encryption - iOS - Android</b>	
Data Protection/Encryption is disabled	Applies a compliance action if an Android device has its Data Encryption feature turned off.
<b>Security - Windows</b>	
OS Build is less than the required OS build	Select this option to apply a compliance action if the device build is less than the OS build defined in the Security policy.

TABLE 2. POLICY VIOLATION EVENT FIELD DESCRIPTION (CONT.)

Field	Description
Last Hotfix is less than the required hotfix	Select this option to apply a compliance action if the device OS build is less than the hotfix build defined in the Security policy.
Last Hotfix installation date is out of date	Select this option to apply a compliance action if the device OS has not been updated in the time interval defined in the Security policy.
<b>iOS</b>	
Disallowed iOS model found	Select this option to apply a compliance action when a restricted iOS model is registered.
Disallowed iOS version found	Select this option to apply a compliance action when a restricted iOS version is registered.
Compromised iOS device	Select this option to apply a compliance action when a compromised iOS is registered or connects to the server. That is, an iOS device has been compromised by circumventing the operator and usage restrictions imposed by the operator and manufacturer.
iOS Configuration not compliant	Applies a compliance action if an iOS device does not have the expected security policy or app settings. This state may indicate that a setting was changed or was not applied successfully.
Restored Device connected to server	Applies a compliance action if a previously wiped device has been restored and attempts to connect through the Core deployment.
MobileIron iOS App Multitasking disabled by user	Applies a compliance action if the device user disables multitasking for the iOS app. Disabling multitasking increases the likelihood that a compromised device will go undetected for a significant period of time.
Device MDM deactivated ( <b>iOS 5 and later</b> )	Applies a compliance action when the MDM profile on a managed iOS 5 device is removed.
<b>macOS</b>	
Disallowed macOS version found	Applies a compliance action if Core finds a registered device running a prohibited version of macOS.
Device MDM deactivated	Applies a compliance action if Core detects that MDM (Mobile Device Management) has been deactivated on a registered macOS device.
FileVault encryption disabled	Applies a compliance action if Core detects a registered macOS device with disabled FileVault encryption.
<b>Android</b>	

TABLE 2. POLICY VIOLATION EVENT FIELD DESCRIPTION (CONT.)


Field	Description
Disallowed Android OS version found	Applies a compliance action if an Android device having a disallowed OS version is detected. You can specify disallowed versions in the security policy.
Compromised Android device detected	Applies a compliance action if a modified Android device is detected. That is, an Android device has been compromised by circumventing the operator and usage restrictions imposed by the operator and manufacturer.
Device administrator not activated for DM client or agent	<p>Generate an alert when a managed Android device is found to have no device administrator privilege activated for Mobile@Work or the Samsung DM Agent.</p> <hr/> <p> The Samsung DM Agent is not required on Samsung MDM 4.x, starting with Mobile@Work for Android version 5.9.</p> <hr/>
<b>Actions</b>	
Generate Alert	Turns on/off the alert defined for this event.
Maximum Alerts	Specifies whether there is a limit on the number of alerts generated for a given event. If you select Limited, then you can specify the number of alerts to allow.
Alert Every	Specifies the time, in days, after which the alert count is reset.
Severity	Specifies the severity you define for this alert. Select <b>Critical</b> , <b>Warning</b> , or <b>Information</b> .
Template	<p>Specifies the template to populate the resulting alert. Click <b>View</b> to display the content of the current template. Select an alternate template from the drop down or click <b>Create</b> to create a new template.</p> <p>See <a href="#">"Customizing Event Center messages" on page 399</a> for information on creating a new template.</p>
Send SMS	<p>Specifies whether to send an alert in a text message, and whether to send it to the user, the administrator, or both.</p> <p>Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section. If you select "Admin only" or "User + Admin", then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.</p>
Send Email	Specifies whether to send an alert in an email, and whether to send it to the user, the administrator, or both.

TABLE 2. POLICY VIOLATION EVENT FIELD DESCRIPTION (CONT.)

Field	Description
	Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section. If you select “Admin only” or “User + Admin”, then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.
Send through Push Notification	<p>Specifies whether to send a message via Android C2DM, and whether to send it to the user, the administrator, or both.</p> <p>Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section. If you select “Admin only” or “User + Admin”, then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.</p> <p>The length of the message is limited to 255 characters.</p>
Apply to Labels	Send the alert to users in the selected labels. See the “Using labels to establish groups” section in <i>Getting Started with Core</i> for more information.
Search Users	Enter the user ID to find users to which you want to send the alert.
Apply to Users	Send the alert to the selected users.
CC to Admins	If you selected “Admin only” or “User + Admin”, then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.

## Device status event settings

The device status event applies only to Android and iOS devices. The following describes the steps to create a device status event in the Admin Portal.

### Procedure

1. Go to **Logs > Event Settings**.
2. Click **Add New**.

3. Select **Device Status Event** from the drop-down menu. The New Status Event dialog box opens.

**New Device Status Event**

Name:

Description:

Triggers when: ☒ Device status is changed  
☒ Android device reports policy/config errors  
☒ Android device reports policy/config warnings  
☒ Work schedule policy applied

**Actions**

**Alert Configuration**

Severity: ☐ Critical ☒ Warning ☐ Information

Template:

Send SMS:

Send Email:

Send Through Push Notification:

Apply to Labels:   
All Smartphones  
Android  
Company-Owned  
Employee-Owned

Search Users:

Apply to:

4. Use the following guidelines to complete the form:

Field	Description
Name	Identifier for this event.
Description	Additional text to clarify the purpose of this notification.
Triggers when	Specifies the conditions on the device that will trigger an alert: <ul style="list-style-type: none"> <li>• Device status is changed (Android and iOS)</li> <li>• Android device reports policy/config errors</li> <li>• Android device reports policy/config warnings</li> <li>• Work schedule policy applied (Android and iOS)</li> </ul>
<b>Actions</b>	
Severity	Specifies the severity you define for this alert. Select <b>Critical</b> , <b>Warning</b> , or <b>Information</b> .
Template	Specifies the template to populate the resulting alert. Click <b>View</b> to display the content of the current template. Select an alternate template from the drop-down or click <b>Create</b> to create a new template.  See " <a href="#">Customizing Event Center messages</a> " on the next page for information on creating a new template.
Send SMS	Specifies whether to send an alert in a text message, and whether to send it to the user, the administrator, or both.  Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section. If you select "Admin only" or "User + Admin", then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.
Send Email	Specifies whether to send an alert in an email, and whether to send it to the user, the administrator, or both.  Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section. If you select "Admin only" or "User + Admin", then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.
Send through Push Notification	Specifies whether to send a message, and whether to send it to the user, the administrator, or both.

Field	Description
	Specify users in the <b>Apply to Users</b> section or by selecting a label in the <b>Apply to Labels</b> section. If you select “Admin only” or “User + Admin”, then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.  The length of the message is limited to 255 characters.
Apply to Labels	Send the alert to users in the selected labels. See the “Using labels to establish groups” section in <i>Getting Started with Core</i> for more information.
Search Users	Enter the user ID to find users to which you want to send the alert.
Apply to Users	Send the alert to the selected users.
CC to Admins	If you selected “Admin only” or “User + Admin”, then the <b>CC to Admins</b> section appears. Use this section to specify administrative users who should receive the alert.

5. Click **Save**.



If more than one device status event applies to a device, only the last one you edited and saved is triggered.

## Related topics

["Work Schedule policy" on page 144](#)


## Customizing Event Center messages

The Event Center sends emails, SMSes, and push notification messages based on triggering events. When you configure events, you can use the default message template or create a new one. Event Center templates enable you to specify content and basic formatting using HTML markup.

## Displaying Event Center templates

To display Event Center templates:

1. In the Admin Portal, go to **Settings > Templates**.



2. Select **Event Center Templates**.

This list includes the default template for each Event Center type. Default templates are not editable.

3. Click the **View** link for the message template you want to view.

View Messages of Template Default Policy Violation Alert template				
Language	SMS	Email Subject	Email Body	Push Notification
Chinese	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA
Dutch	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA
English	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA
French	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA
German	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA
Italian	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA
Japanese	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA	\$SEVERITY:\$PHONE_NUMBER (\$USER_NAME) \$DEFAULT_POLICY_VIOLATION_MESSA
	\$SEVERITY:\$PHONE_NUMBER	\$SEVERITY:\$PHONE_NUMBER	\$SEVERITY:\$PHONE_NUMBER	\$SEVERITY:\$PHONE_NUMBER

## Adding custom Event Center messages

To add a custom Event Center message:



1. Either click the **Create** button in the event dialog or select the event type from **Settings > Templates > Event Center Templates > Add New**.

The following figure shows the event dialog.

**New International Roaming Event**

Save Cancel

Name:

Description: Generated when the device is in an international roaming zone

**Actions**

☒ Generate Alert

**Alert Configuration**

Alert for Every Country: ☒ Yes ☐ No

Visited in the Trip:

Maximum Alerts: ☒ Unlimited ☐ Limited

Severity: ☐ Critical ☒ Warning ☐ Information

Template: Default International Roaming Alert template View Create

Send SMS: User only

Send Email: User only

Send Through Push Notification: User only


Apply to Labels: Available  
All-Smartphones  
All-Syscomm  
Android  
...

Selected


Search Users: Search by Username

Save Cancel

The following figure shows the Event Center Templates menu.



The dialog for the corresponding event type opens.



Event Center messages are displayed with the HTML markup that provides the basic formatting for the content.

- 2.
3. In the **Name** field, enter a name for the template.

The name must be unique for events of the same type.

4. In the **Edit Template for** field, select the language this template will be used for.

Note that only those languages that have been enabled for the system will be displayed in this list.

- 5. Make changes to the displayed messages.
- 6. Click **Save**.

## Adding other types of templates

There are "Other" types of events that have templates that you can modify and use. The "Other" list includes the default template for: Action on Device, App Distribution, Selective Wipe, and Wipe. Default templates are not editable.

### Procedure

- 1. Go to **Settings > System Settings**.
- 2. Click **Templates > Others**.

The Others template page displays.

- 3. Find the language you want the template to display in and then click the **Edit** icon.

The Edit Template dialog box opens. For this example, the Edit Template: Wipe (English) dialog box opens.

Edit Template: Wipe (English)

Type: Wipe  
Language: English

Message Type	Template
Wipe Email Subject:	Wipe has been requested for your phone \$PHONE\$
Wipe Email Body:	<html><body><p></p><p><span style="font-family: Arial,Helvetica,sans-serif;">Dear \$USER\$,</sp family: Arial,Helvetica,sans-serif;">Your mobile phone \$PHONE\$ has been returned to factory default s administrator to determine whether a backup snapshot can be used to restore your phone.</span></p>

<

SaveCancel

4. Enter the information in the form.
  - **Email Subject** - Modify the default text or enter a short phrase that gives a summary of the message.
  - **Email Body** - Modify the provided text for your needs. See ["Using variables in Event Center messages"](#) below.
5. When finished, click **Save**.

## Related topics

["Customizing registration messages" on page 70](#)

## Using variables in Event Center messages

Supported and required variables for Event Center messages vary by the type of message. The following table summarizes these variables. You can also click the **Variables Supported** link to display this information. Note that, unlike variables used for registration variables, Event Center variables do not end with \$.

TABLE 1. VARIABLES IN EVENT CENTER MESSAGES

Template Type	Required Variables
International Roaming	\$CURRENT_COUNTRY \$HOME_COUNTRY \$PHONE_NUMBER \$SEVERITY \$USER_NAME
Threshold Reached	\$PHONE_NUMBER \$SEVERITY \$THRESHOLD_ON \$THRESHOLD_TYPE \$THRESHOLD_UNIT \$THRESHOLD_VALUE \$USED_VALUE \$USER_NAME
SIM Changed	\$CURRENT_PHONE_NUMBER \$NEW_PHONE_NUMBER \$SEVERITY \$USER_NAME
Memory Size Exceeded	\$FREE_MEMORY_SIZE

TABLE 1. VARIABLES IN EVENT CENTER MESSAGES (CONT.)

Template Type	Required Variables
	\$MEMORY_SIZE_LIMIT \$PHONE_NUMBER \$SEVERITY \$TOTAL_MEMORY_SIZE \$USER_NAME
System Event	\$DEFAULT_SYSTEM_MESSAGE \$SERVER_IP \$SERVER_NAME \$SEVERITY
Policy Violation	\$DEFAULT_POLICY_VIOLATION_MESSAGE \$PHONE_NUMBER \$SEVERITY \$USER_NAME

## Variable descriptions

The following table describes the variables used in Event Center messages.

TABLE 2. VARIABLE DESCRIPTIONS


Variable	Description
\$CURRENT_COUNTRY	The country in which the device is currently located.
\$CURRENT_PHONE_NUMBER	The phone number currently associated with the device in Core, but not matching the phone number currently used by the device.
\$DEFAULT_POLICY_VIOLATION_MESSAGE	<p>The hard-coded message associated with the policy violation that triggered the alert.</p> <hr/> <div>  Due to the length limits of SMS and C2DM, the text might be truncated. </div> <hr/>
\$DEFAULT_SYSTEM_MESSAGE	The third-party system message or error that triggered the alert.
\$FREE_MEMORY_SIZE	The amount of free memory currently available on the device.

TABLE 2. VARIABLE DESCRIPTIONS (CONT.)

Variable	Description
\$HOME_COUNTRY	The home country of the device.
\$MEMORY_SIZE_LIMIT	The threshold set for the device memory.
\$NEW_PHONE_NUMBER	The phone number replacing the \$CURRENT_PHONE_NUMBER\$ as a result of a SIM change.
\$PHONE_NUMBER	The phone number used by the device.
\$SERVER_IP	The IP address of the server triggering a system event alert.
\$SERVER_NAME	The hostname of the server triggering the system event alert.
\$SEVERITY	The defined severity of the system event, i.e., Information, Warning, or Critical.
\$THRESHOLD_ON	The total used for calculations, i.e., International Roaming or Total Usage.
\$THRESHOLD_TYPE	The type of usage measured, i.e., SMS, Data, or Voice.
\$THRESHOLD_UNIT	The unit associated with the type of usage, i.e., minutes, messages, or MB.
\$THRESHOLD_VALUE	The defined threshold value for this event, e.g., 1000 (voice minutes).
\$TOTAL_MEMORY_SIZE	The total memory reported by the device.
\$USED_VALUE	The amount of memory currently used on the device.
\$USER_NAME	The display name of the user associated with the device.

## Specifying which template to use

When you create or edit an event, you specify which template to use for resulting alerts. To select a template:

1. Create or edit an event.
2. Select a template from the drop-down or click the **Create** button to create a new template.

## Filtering Event Center messages


In the Event Center Templates page, you can filter messages by event type. Just select the preferred event type from the **Event Type** drop-down.

## Editing Event Center messages

You can edit your custom Event Center templates. However, default Event Center templates are not editable.

To edit a custom Event Center template:

1. In Admin Portal, go to **Settings > Templates > Event Center Templates**.



2. Click the edit icon for the custom template you want to edit.
3. Make your changes.
4. Click **Save**.

## Deleting Event Center messages

You can delete any of the Event Center messages you have created:

1. In Admin Portal, go to **Settings > Templates > Event Center Templates**.
2. Select the items you want to delete.
3. Click **Delete**.

## Viewing and Exporting Events

Use the Events screen to track the events that have triggered alerts. To display the Events screen, go to **Logs > Events**.

## Marking as Read or Unread

To enable tracking of which events have been noted and/or addressed by an administrator, you can mark an event as **Read**. Likewise, you can switch this flag back to **Unread**.

To set the Read/Unread flag:

1. Select one or more events.
2. Select **Read** or **Unread** or from the **Actions** menu.

## Filtering events

You can display the events using the following filters:

TABLE 1. FILTERING EVENTS

Filter	Description
Read/Unread	Select <b>Read</b> or <b>Unread</b> from the <b>Show</b> drop-down list. To resume displaying all events, select <b>All</b> .
All	Select <b>All</b> to resume displaying all events.
Labels	Select the preferred label from the <b>Labels</b> drop-down to filter based on the label specified in the event.
User	Enter a user ID and click the search icon to filter based on the user IDs specified in the event.
Start Date/End Date	Select dates in the <b>Start Date</b> and <b>End Date</b> fields to filter events by date range.
Event Type	Select an event type from the <b>Type</b> drop-down to filter by event type.
Event Status	Select an event status from the status drop-down to filter based on the event's lifecycle state.

## Event lifecycle and status

Events go through the following lifecycle:

Created -> Dispatch Pending -> Dispatching -> Dispatched

The following two failure states may also occur:

- Dispatch Failed: The process of generating the alert failed. This is usually the result of an SMTP problem. Check the SMTP configuration in System Manager, as well as the health of your SMTP server.
- Expired: Another event occurred that makes the alert obsolete, resulting in expiration before dispatch.

## Exporting event history


To export a CSV file containing the currently displayed events on the **Logs > Events** page, click the **Export** button.

## Adding a note

You can add a note to one or more events to help track the work that has been done in response. Each event can hold one note; adding another note replaces the existing note. To add a note:



1. Select one or more events.
2. Click **Actions > Add Note**.



The screenshot shows a small window titled "Add Note" with a close button (X) in the top right corner. Inside the window, there is a label "Note:" followed by a large, empty text input field. To the right of the input field is a red circular icon with a white exclamation mark. At the bottom of the window, there is a blue button labeled "Add".

3. Enter the text of the note.
4. Click **Add**.
5. Press F5 to refresh the screen and confirm that the note displays in the Note field for the selected events.

# Troubleshooting Core and devices

This section addresses troubleshooting various aspects of Core and devices.

About Core logs .....	410
Audit log information .....	418
Best practices: label management .....	419
Device events .....	420
ActiveSync Device information .....	423
MDM events .....	423
Certificate events .....	424
App Tunnel events .....	425
Audit Logs use cases .....	430
MDM Activity .....	434
Certificate Management .....	434
Service Diagnostic tests .....	438
Device log encryption on Android devices .....	440
Encrypting device logs with your own certificate .....	441
Pull client logs for client devices .....	442

## About Core logs

As you oversee management and security of users, data and devices, you will need information about the actions and events that occur in your Core instance. Core logs many actions that can impact your Core instance, and provides the Audit Logs page for you to sort and view the logged information.

The following pages of logs, found in the Admin Portal under **Logs**, enable you to easily navigate through the Core log entries to find the information you need.

- **Audit Logs:** for Core device management entries
- **MDM Activity:** for Android MDM entries
- **Certificate Management:** for certificate-related entries

Note The Following:

- Logs are stored in the Core file system, not in the Core database. Therefore, the size of the logs does not impact Core performance.
- Core will show up to 1 million audit log records.

## Audit logs

Using log entries, the Admin Portal tracks status and operations for each managed device. You can use log entries to confirm that actions were completed and to investigate problems.

The Audit Logs page includes panels that:

- enable you to filter through all events that Core has logged since the last time the logs were purged
- shows either the events recorded since the logs were last purged, or the events matching the criteria you specified in the Filters panel

FIGURE 1. AUDIT LOGS

The screenshot shows the 'Audit Logs' section of an application. At the top, there are tabs for 'Audit Logs', 'MDM Activity', 'Certificate Management', 'Event Settings', and 'Events'. Below the tabs is a 'Filters' panel on the left with a search bar 'Search by Performed On...', an 'Export to CSV' button, and a list of filters: 'Device (1797)', 'ActiveSync Device (0)', 'MDM (87)', 'Certificate (238)', and 'App Tunnel (0)'. The main area displays a table of audit logs with the following columns: ACTION, STATE, PERFORMED BY, ACTION DATE, COMPLETED AT, PERFORMED ON, and DETAILS. The table contains 10 rows of data, all with the action 'Account Sync Completed'. The states alternate between 'Failed' and 'Success'. The 'PERFORMED BY' is 'misystem' for all entries. The 'ACTION DATE' and 'COMPLETED AT' timestamps are shown for each entry. The 'PERFORMED ON' is 'DEP Account' for all entries. The 'DETAILS' column contains a 'Check update...' link for each entry. At the bottom of the table, there is a 'Reset' button, a 'Search' button, and a pagination bar showing 'Page 1 of 110' and '50 per page'. The status 'Displaying 1 - 50 of 5455' is shown at the bottom right.

ACTION	STATE	PERFORMED BY	ACTION DATE	COMPLETED AT	PERFORMED ON	DETAILS
Account Sync Completed	Failed	misystem	2019-05-23 12:35:2...	2019-05-23 12:35:2...	DEP Account	Check update...
Account Sync Completed	Success	misystem	2019-05-23 12:35:2...	2019-05-23 12:35:2...	DEP Account	Check update...
Account Sync Completed	Failed	misystem	2019-05-23 12:20:2...	2019-05-23 12:20:2...	DEP Account	Check update...
Account Sync Completed	Success	misystem	2019-05-23 12:20:2...	2019-05-23 12:20:2...	DEP Account	Check update...
Account Sync Completed	Failed	misystem	2019-05-23 12:05:2...	2019-05-23 12:05:2...	DEP Account	Check update...
Account Sync Completed	Success	misystem	2019-05-23 12:05:2...	2019-05-23 12:05:2...	DEP Account	Check update...
Account Sync Completed	Failed	misystem	2019-05-23 11:50:2...	2019-05-23 11:50:2...	DEP Account	Check update...
Account Sync Completed	Success	misystem	2019-05-23 11:50:2...	2019-05-23 11:50:2...	DEP Account	Check update...
Account Sync Completed	Failed	misystem	2019-05-23 11:35:2...	2019-05-23 11:35:2...	DEP Account	Check update...

## Searching the information in the audit logs

### Procedure


To search the information that Core logs:

1. In Admin Portal, go to **Logs**.

Core displays the Audit Logs page, which initially lists the events logged since the last time the logs were purged.

2. In the **Filters** panel, click on the number of events in a category to display only that category's events.

For example, click the **72** next to **App**.



The screenshot shows a 'Filters' panel with a search bar at the top labeled 'Search by Performed (On|By)/Details'. Below the search bar is an 'Action Date' section with a 'Select time...' dropdown. A list of filter categories follows, each with a right-pointing arrow and a count in parentheses: Device (1133), ActiveSync Device (0), MDM (0), Certificate (73), App Tunnel (0), App (72), Policy (97), Compliance Action (0), Configuration (176), DEP (0), and Admin (119). At the bottom of the panel are two buttons: 'Reset' and 'Search'.

3. Alternatively, click to expand one of the information types that you want to view (for example, **App**).
4. Check the items within that category that you want to view (for example, **Add App** and **Install App**).
5. Repeat Step 3 and Step 4 for each category that you want to include in this search.
6. (Optional) To search for events involving a particular administrator, or actions that contain a specific word or phrase in the details, use the **Search by Performed (On|By)/Details** box in the Filters panel as follows:
  - enter the search string in the text box.
  - for example, to find events involving Mobile@Work, enter the text **Mobile@Work**.
7. (Optional) To limit the time frame of the actions, use the **Action Date** box (see ["Setting event time criteria in audit logs" on the next page](#))

8. Click **Search**.

The Audit Logs page shows all events matching your search criteria and time period. If you do not specify a time period, the default used is the period between the time you run the search and when the log data was last purged.

9. To reset all search criteria, click **Reset**.


## Setting event time criteria in audit logs

When you are working with audit logs, the default time frame for the events displayed is the time between the current time and the last time the logs were purged (for information about setting the log retention time, see ["Specifying how long log information is saved" on page 417](#)). For example, if the logs were purged two weeks ago, the Audit Logs display all the events matching any criteria you set that occurred from two weeks ago to the current moment.

You can change the time frame of events you view in the **Filters** panel. You can select by time or date.

To specify a time frame for events you view from the audit logs:

1. In Admin Portal, go to **Logs**.
2. In the Filters panel, click the drop-down arrow in **Action Date**.



3. Select one of the times listed or **Others**.

Selecting a time displays the events matching criteria you set, if any, for the time period from the last time the logs were purged until the time you specify.

Any events that occurred between the specified time period and the current moment are not displayed. For example, if you select **1 hour ago**, no events that happened within the last hour are displayed.

4. If you select **Others**:

- using the left column of time choices in Filters, you can specify an exact date, hour or minute (or any combination of these criteria) as one end of the time frame and use the date of the last audit log purge as the other end of the time frame
- using the left and right columns of time choices in Filters, you can specify both the beginning and end of the time range.

Use the following table to help you set the time range for your search.

The image shows two side-by-side screenshots of a 'Filters' dialog box. Both screenshots have a title bar 'Filters' and a search bar 'Search by Performed (On/By/Details)'. The left screenshot shows the 'Action Date' dropdown set to 'Others...' and the 'Select time...' dropdown. The right screenshot shows the 'Action Date' dropdown set to 'Others...' and the 'Others...' dropdown, with both 'Select date...' and 'Select time...' dropdowns visible. Below these are 'Select hour...' and 'Select minute...' dropdowns.

Note The Following:

- When you set only one end of the time frame, the date or time you specify must be later than the last date the log data was purged. If the last log purge was May 13th, for example, May 12th would not be a valid date for selecting events.
- When you set both ends of the time frame, ensure that the time or date specified in the left column occurs before the time or date specified in the right column. For example, if you specify **1 hour ago** in the left column and **1 day ago** in the right column, Core will display a message asking you to reset your time criteria because 1 hour ago happens after 1 day ago.

TABLE 1. TIME CRITERIA SELECTION EXAMPLES

Time criteria selected	Value selected	Result
In the left column, select both: <ul style="list-style-type: none"> <li>• <b>Others</b></li> <li>• <b>Select date</b></li> </ul>	Click May 12th in the displayed calendar	Displays all events matching your criteria that occurred from the last audit log data purge until May 12th.
In the left column, select both: <ul style="list-style-type: none"> <li>• <b>Others</b></li> <li>• <b>Select hour</b></li> </ul>	Select 2AM from <b>the list of hours</b>	Displays all events matching your criteria that occurred from the last audit log data purge until 2AM of the current day.
In the left column, select both: <ul style="list-style-type: none"> <li>• <b>Others</b></li> <li>• <b>Select minute</b></li> </ul>	Select 15 from the list of <b>minutes</b>	Displays all events matching your criteria that occurred from the last audit log data purge until the 15th minute of the current hour.

TABLE 1. TIME CRITERIA SELECTION EXAMPLES (CONT.)

Time criteria selected	Value selected	Result
<p>In the left column, select:</p> <ul style="list-style-type: none"> <li>• <b>Others</b></li> <li>• Select date</li> </ul> <p>In the right column, select:</p> <ul style="list-style-type: none"> <li>• a time interval from <b>Select time</b></li> </ul>	<p>In the left column:</p> <ul style="list-style-type: none"> <li>• Select <b>April 10th</b> from the calendar</li> </ul> <p>In the right column:</p> <ul style="list-style-type: none"> <li>• Select <b>1 day ago</b></li> </ul>	Displays all events matching your criteria that occurred between April 10th and 24 hours ago.
<p>In the left column, select:</p> <ul style="list-style-type: none"> <li>• <b>Others</b></li> <li>• Select hour</li> </ul> <p>In the right column, select:</p> <ul style="list-style-type: none"> <li>• a time interval from <b>Select time</b></li> </ul>	<p>In the left column:</p> <ul style="list-style-type: none"> <li>• Select <b>2AM</b></li> </ul> <p>In the right column:</p> <ul style="list-style-type: none"> <li>• Select 1 hour ago</li> </ul>	Displays all events matching your criteria for the time period that started at 2AM the morning of the current day and ended an hour ago.

## Viewing audit log information

The Audit Logs page displays the information that Core records for your Core instance. You specify what information is displayed on this page when you use the controls in the **Filters** panel of the page. See ["Searching the information in the audit logs" on page 411](#) for details.

To view the information that Core logs:



1. In Admin Portal, go to **Logs**.

Core displays the Audit Logs page. The information panel displays:

**Action** (for example, Admin Portal sign-in)

ACTION	STATE	PERFORMED BY	ACTION DATE	PERFORMED ON	DETAILS
Add LDAP	Success	miadmin	2015-06-05 05:33:42...	LDAP - ldap://ESWin2003002.a...	LDAP S... ldap://ES...
Admin Portal Sign In	Success	miadmin	2015-06-05 05:39:22...	Admin Portal - 10.10.19.88	Success
Add Standalone Sentry	Success	miadmin	2015-06-05 05:39:34...	Standalone Sentry - app1077.a...	Standal... added
Admin Portal Sign In	Success	miadmin	2015-06-05 05:40:18...	Admin Portal - 10.10.19.88	Success
Admin Portal Sign In	Success	miadmin	2015-06-05 05:42:19...	Admin Portal - 10.10.19.88	Success
Admin Portal Sign In	Success	miadmin	2015-06-05 05:42:19...	Admin Portal - 10.10.19.88	Success
Add Configuration	Success	miadmin	2015-06-05 05:42:19...	Exchange - ExchangeStep1 : V...	Configur...
Add Label	Success	miadmin	2015-06-05 05:42:20...	labellastcheckin	Label 'la...
Add Label	Success	miadmin	2015-06-05 05:42:21...	labelusername	Label 'la...
Add Label	Success	miadmin	2015-06-05 05:42:22...	labelldapname	Label 'la...

- **State** (for example, **Success**)
  - **Performed By** (for example, **myadmin**)
  - **Action Date**
  - **Completed At**
  - **Performed On** (for example, **Admin Portal**)
  - **Details**
2. (Optional) Enter a number in **Page** to specify what page to view.
  3. (Optional) Select a number from **per page** to specify how many records are displayed on a page.
  4. (Optional) Click **Export to CSV** to export the records that match the current search criteria.

## Specifying how long log information is saved

You specify how long log data is retained on your server. Determining how long to retain data is a balance between having data you need and having the available server resources to run your Core. The default value is 90 days.

To set how long log information is kept:

1. In System Manager, go to **Settings > Data Purge**.
2. In **Audit Logs Purge Configuration**, select the number of days Core retains log information.
3. Click **Apply**.

## Audit log information

Several categories of information are available for you to view and audit. The category list, displayed on the left side of the Audit Logs page, includes:

- **Device**
  - **ActiveSync Device**
  - **MDM**
  - **Certificate**
  - **App Tunnel**
  - **App**
  - **Policy**
  - **Compliance Action**
  - **Configuration**
  - **DEP (Device Enrollment)**
  - **Admin**
  - **User**
  - **LDAP**
  - **Other**
  - **Label**
  - **Sentry**
  - **AfW**
  - **Custom Attributes**
  - **Compliance Policy**
  - **E-FOTA**
  - **Migration**
  - **MTD (Mobile Threat Defense)**
  - **Access Integration**

- Derived Credential Provider
- Zebra FOTA

## Best practices: label management

If Notes for Audit Logs is enabled, whenever a change is made to a label, a text box displays for the administrator to provide a reason for the change.

**Apply To Label**

Search by Name or Description

☐ Apply configuration settings to Labels

Reason:

Cancel Apply

Windows Label for all Windows devices. Not Applied

Windows Phone Label for all Windows Phone Devices. Not Applied

Page 1 of 1 1 - 10 of 10

Apply

Example text to enter would be a change ticket order number. This information then displays in the Audit logs, in the Details column as "Reason."

Dashboard	Devices & Users	Admin	Apps	Policies & Configs	Services	Settings	Logs
Audit Logs	MDM Activity	Certificate Management	Event Settings	Events			
Export to CSV							
	ACTION	STATE	PERFORMED BY	ACTION DATE	COMPLETED AT	PERFORMED ON	DETAILS
	Apply Label To Configu...	Success	miadmin	2020-01-20 03:52:39...	2020-01-20 03:52:39...	Restrictions - iOSRestriction : V...	Label All-Sn
	Preference Config Cha...	Success	misystem	2020-01-20 03:49:04...	2020-01-20 03:49:04...	System	Label All-Smartphones Reason: AddLabel
	Modify Configuration	Success	miadmin	2020-01-20 03:48:22...	2020-01-20 03:48:22...	Restrictions - iOSRestriction : V...	Configuratio
	Admin Portal Sign In	Success	miadmin	2020-01-20 03:46:26...	2020-01-20 03:46:26...	Admin Portal -	Successfully

This affects the following label-related activities:

- Add/Edit/Delete/Save Label (Both filter and manual)
- In **Devices & Users > Devices > Advanced Search > Save to Label**
- Add/Edit/Remove Label to devices
- Add/Edit/Remove Label to configurations
- Add/Edit/Remove Label to policies
- Add/Edit/Remove Label to apps
- Add/Edit/Remove Label to iBooks

The Notes for Audit Logs feature is also applicable to any administrator-made changes to iOS and macOS restrictions.

To enable this feature, see "Setup tasks" in *Getting Started with MobileIron Core*.

## Device events

Device events record device-related actions taken by an administrator in the Admin Portal.

To monitor device actions, select one or more of the logged device actions in the **Filters** panel:

- **Allow App Tunnel:** Manually allow app tunnels from the selected device.
- **Apply Label:** Associate an item with a label.
- **Apply Multiple Labels to One Device:** Associate an item with multiple labels.
- **Block App Tunnel:** Manually disallow app tunnels from the selected device.
- **Cancel Wipe:** Cancels pending "Wipe" command if it was not yet delivered to the device. Applies to all modes.
- **Change Language:** Change the language associated with a device.
- **Change Ownership:** Toggle device ownership between Employee and Company.
- **Check Available OS Update:**
- **Check Compliance:** Check device against compliance criteria.
- **Delete Retired Device:** Remove entry for a device that is not longer managed.
- **Device Location:**
- **Disable:**
- **Disable Activation Lock:** Turn off the activation lock feature for the selected iOS device.
- **Disable Data Roaming:** Turn off the ability to use data when the device is roaming.

- **Disable due to out of compliance:**
- **Disable Kiosk:** Exit kiosk mode on the designated Android device.
- **Disable KNOX Container:** Turn off the Samsung KNOX container feature for the selected device.
- **Disable Personal Hotspot:** Prevent the device user from using the personal hotspot feature.
- **Disable Voice Roaming:** Turn off the ability to make voice calls when the device is roaming.
- **Download Available OS Update:**
- **Enable:**
- **Enable Activation Lock:** Turn on the activation lock feature for the selected iOS device.
- **Enable Data Roaming:** Turn on the ability to use data while roaming for the selected iOS device.
- **Enable Kiosk:** Start kiosk mode on the designated Android device.
- **Enable KNOX Container:** Turn on the Samsung KNOX container feature for the selected device.
- **Enable MDM Lost Mode:** Enable lost mode for the selected iOS device.
- **Enable Personal Hotspot:** Allow the device user to use the personal hotspot feature.
- **Enable Voice Roaming:** Turn on the ability to make voice calls when the device is roaming.
- **Found:** Designate the selected lost device as found.
- **Install Downloaded OS Update:**
- **Install Help@Work:** Install the Help@Work app.
- **Locate:** Retrieve the last known location for the selected device.
- **Lock:** Force the selected device to require a passcode for user access.
- **Lost:** Designate the selected device as lost.
- **MobileIron Bridge:** Create a configuration for the Bridge application for Windows 10 Management.
- **Push Profile:** Prompt a manual distribution of profiles to the selected device.
- **Re-provision Device:** Restart the provisioning process for the selected device.
- **Reboot:** Reboot the selected Windows device.
- **Register Device:** Start the registration process for the selected device.
- **Remote Control:** Establish a remote control session (Help@Work) on the selected Android device.
- **Remote Display:** Establish a remote view session (Help@Work) on the selected iOS device.
- **Remove Device Attribute:** Remove an attribute from a device.
- **Remove Label:** Remove the association between the specified label and the selected item.

- **Remove Multiple labels from one device:** Remove the association between the specified labels and the selected item.
- **Request Derived Credential: Device user request in user portal for a derived credential.**
- **Request Unlock AppConnect Container** (Android only): Initiate unlock AppConnect container.
- **Request Unlock Device:** Initiate unlock device.
- **Request Unlock Passcode:** Initiate unlock passcode.
- **Resend Provision Message:** No longer supported.
- **Reset AppConnect Passcode:** Device user request in user portal to reset the AppConnect passcode.
- **Reset Password:**
- **Restart iOS Device:** Restart iOS device.
- **Reset PIN:** Generate a new registration PIN for the selected Windows device.
- **Retire:** End management of the selected device.
- **Send Activation Lock Bypass Code:** Send the bypass code to the selected iOS device.
- **Send Alert:** Send compliance alert to the selected device.
- **Send APNS message:** Launch a client and authenticate against Core.
- **Send Message:** Send SMS message to the selected device.
- **Set Device Attribute:** Set an attribute to a device.
- **Shutdown iOS Device:** Shutdown iOS device.
- **Sign In:** Launch a client and authenticate against Core.
- **Sign Out:** End session between the client and Core.
- **Substitution Variable Change:** Change a configuration due to a change in the value of a substitution variable.
- **Unlock AppConnect Container** (Android only): Begin unlock device and AppConnect container.
- **Unlock Device and AppConnect Container:** (Android only): Begin unlock device and AppConnect container.
- **Unlock Device Only:** Clear the passcode for the selected device.
- **Update Device Comment:** Change the Comment field in the record for the selected device.
- **Update OS Software:** Update iOS software.
- **Wakeup:** Force the device client to check in.

- **Windows License:** Alert administrators to upgrade the SKU of Windows 10 desktop devices. Options can be Windows 10 Pro to Enterprise or Windows 10 Education to Enterprise.
- **Wipe:** Return the device to factory default settings.



Events beginning with **Request**, such as **Request Unlock Device**, are logged when an administrator clicks the corresponding command in the Admin Portal. The corresponding event without the word **Request**, such as **Unlock Device**, is logged when Core actually sends the request to the device. Core sometimes delays sending requests to regulate Core performance.

## ActiveSync Device information

These events do not apply to Mac devices.

To monitor ActiveSync device actions, select one or more of the logged ActiveSync device actions in the **Filters** panel

- **ActiveSync Device Comment:** Add or change the comment associated with an ActiveSync device entry.
- **Add Correlation:**
- **Allow Device:** Allow a blocked ActiveSync device to access the ActiveSync server.
- **Assign ActiveSync Policy:** Apply an ActiveSync policy to the selected device.
- **Block Device:** Prevent the selected device from accessing the ActiveSync server.
- **Link To MI Device:** Associate an ActiveSync device with a device registered with Core.
- **Remove:** End the association between the Core device and the ActiveSync device record.
- **Remove Correlation:**
- **Revert ActiveSync Policy:** Restore the Default ActiveSync Policy to the selected device.

## MDM events

MDM events indicate when a device takes an action due to a Core request. These events pertain only to iOS and Mac devices unless otherwise noted.

To monitor these actions, select one or more of the logged MDM actions in the **Filters** panel.

- **Apply Redemption Code:** Apply Redemption Code: Use a Apple License code.
- **Clear Passcode:** Clear Passcode: Reset device passcode.
- **Device Lock:** Set screen lock on device.
- **Install Encrypted Sub-Profile:**
- **Install Managed Application:** Install a managed app.

- **Install MDM Profile:** Install the MDM profile on the device.
- **Install Provisioning Profile:** Install the provisioning profile for a managed app.
- **Lock Device (Android):** Lock an Android device.
- **Profile Change:** Change the profile on an iOS or Android device.
- **Remove Encrypted Sub-Profile:**
- **Remove Managed Application:** Uninstall a managed app.
- **Remove MDM Profile:** Remove the MDM profile from the device.
- **Remove Provisioning Profile:** Remove the provisioning profile for a managed app.
- **Settings:** Modify device settings.
- **Unlock Device (Android):** Unlock an Android device and the AppConnect container on the device.
- **Unlock Device Only (Android):** Unlock an Android device.
- **Wipe Device** (called **Erase Device** in the **MDM Activity** tab): Restore the iOS device to factory defaults.
- **Wipe Device (Android):** Restore the Android device to factory defaults.



This MDM log information is also provided in the **Logs > MDM Activity** tab.

---

## Certificate events

To monitor actions involving certificates, select one or more of the logged certificate actions in the **Filters** panel.

- **Apply User Provided Certificate:** Use a certificate already provided by the user and sent to Core.
- **Create Device Certificate:** Issue a device certificate.
- **Create User Certificate:** Issue a user certificate.
- **Delete User Provided Certificate:** Destroy certificate provided by the user via the self-service portal.
- **Device Certificate Expired:** Warn on a device certificate that is no longer valid due to expiration.
- **Device Certificate Renewal:** Re-enrolls a device certificate.
- **Reuse Device Certificate:** Use an existing device certificate.
- **Reuse User Certificate:** Use an existing user certificate.
- **Revoke Device Certificate:** Reclaim a device certificate.
- **Revoke User Certificate:** Reclaim a user certificate.
- **Upload User Provided Certificate:** Send certificate provided by the user via the self-service portal.



- **User Certificate Expired:** Warn on a user certificate that is no longer valid due to expiration.
- **User Certificate Renewal:** Re-enroll a user certificate.



The contents of the **Logs > Certificate Management** shows information about certificates, such as their expiration dates. It allows you to take actions, such as re-enroll, remove, and revoke on the certificates.

---

## App Tunnel events

To monitor actions involving app tunnels, select one or more of the logged app tunnel actions in the **Filters** panel.

- **Allow App Tunnel:** Permit the specified app tunnel.
- **App Tunnel Comment:** Add a comment on the selected app tunnel.
- **Block App Tunnel:** Do not allow the specified app tunnel.
- **Remove App Tunnel:** Delete the selected app tunnel configuration.

## App information

To monitor actions involving apps, select one or more of the logged app actions in the **Filters** panel.

- **Add App:** Add an app to the app catalog.
- **Add App Control Rule:** Add an app control rule.
- **Add App Dependency:**
- **Add App Resource:** Add screenshots or icons for an app.
- **Apply Label to App:** Associate a label with an app.
- **Delete App Control Rule:** Remove an app control rule.
- **Edit App Control Rule:** Change one or more attributes of an app control rule.
- **Install App:** Send installation request for the selected app.
- **Manage VPP Labels:** Specify labels and account for Apple License app distribution.
- **Modify App:** Edit app catalog entry.
- **Remove App:** Delete entry from the app catalog.
- **Remove Label From App:** End the association between an app and a label.
- **Uninstall App:** Remove the app from the device based on managed app criteria.

## Policy information

To monitor actions involving policies, select one or more of the logged policy actions in the **Filters** panel.

- **Activate Policy:** Set flag to make the selected policy active.
- **Add Policy:** Create a new policy.
- **Apply Label to Policy:** Associate a policy and a label.
- **Deactivate Policy:** Clear flag to make the selected policy inactive.
- **Delete Policy:** Delete a policy.
- **Export Policy:** Export a policy from Core.
- **Import Policy:** Import a policy into Core.
- **Modify Policy:** Change an attribute of an existing policy.
- **Modify Policy Priorities:**
- **Modify Policy Priority:** Change the priority for an existing policy.
- **Remove Label From Policy:** End the association between a policy and a label.

## Compliance Action events

To monitor compliance actions, select one or more of the logged compliance actions in the **Filters** panel

- **Add Compliance Action:** Create a set of actions to be taken on devices that violate policies.
- **Delete Compliance Action:** Remove a set of actions to be taken on devices that violate policies.
- **Modify Compliance Action:** Make changes to a set of actions to be taken on devices that violate policies.
- **Modify Compliance Check Preferences:** Make changes to compliance preferences.

## Configuration events

- **Add Configuration:** Create a new configuration.
- **Apply Label To Configuration:** Associate a configuration with a label.
- **Export Configuration:** Export a configuration from Core.
- **Import Configuration:** Import a configuration to Core.
- **Modify Configuration:** Change the settings in a configuration.
- **Remove Configuration:** Delete a configuration.
- **Remove Label From Configuration:** End the association between a configuration and a label.

- **Remove Labels From Configuration:** End the association between a configuration and multiple labels.

## Admin events

- **Add Space:** Define a new delegated administration space.
- **Admin Portal Sign In:** Start an Admin Portal session.
- **Admin Portal Sign Out:** End an Admin Portal session.
- **Assign Space Admin:** Specify an administrator for a space.
- **Change Space Priority:** Set a different priority for a space.
- **Delete Space Admin:** Remove space admin access from the user.
- **Modify Space:** Make changes to rules that define a space.
- **Remove Admin From Space:** Remove the admin user from the space.
- **Remove Space:** Delete all rules that define a space and reallocate its devices.
- **Update Device Space:** Recalculate space rules to determine device membership.
- **User Locked Out:** Prevent administrator from further attempts at signing in after limit on authentication failures is exceeded.

## User events

- **Add User:** Define a new Core user.
- **Delete User:** Remove a Core user.
- **Link to LDAP User:** Associate a local Core user with an LDAP user.
- **Modify User:** Make changes to a user's attributes.
- **Modify User Role:** Make changes to the roles assigned to a user.
- **Re-sync with LDAP:** Synchronize LDAP data.
- **Remove User Attribute:** Remove an attribute from a user.
- **Renew Google Apps password:** Manually regenerate a user's Google Apps password.
- **Require Password Change:** Force a local user to change their Core password.
- **Send Invitation:** Invite a user to register with Core.
- **Set User Attribute:** Set an attribute for a user.
- **User Portal Sign In:** Start User Portal session.
- **User Portal Sign Out:** End User Portal session.

## LDAP events

- **Add LDAP:** Integrate an LDAP server with Core.
- **Delete Admin LDAP Entity:** Delete an Admin LDAP entity that has no roles.
- **Delete LDAP:** End the integration between an LDAP server and Core.
- **Delete LDAP Entity:** Delete a user LDAP entity that has no roles.
- **Modify LDAP:** Make changes to the record for an integrated LDAP server.
- **Modify LDAP Preferences:** Make changes to the preferences for integrated LDAP servers.
- **Upload LDAP Certificate:** Add an LDAP certificate to Core.

## Other events

- **Application Started:** Start Core services.
- **Application Stopped:** Stop Core services.
- **Complete feature usage collection:** Complete the current run of feature usage collection.
- **Feature usage collection error:** Encountered error during collection.
- **Feature usage collection scheduling error:** Encountered scheduling error during collection.
- **Initiate feature usage collection:** Start feature usage collection.
- **Purge feature usage data:** Purge collected feature usage information.
- **Preference Config Changes:** Make changes to the settings under **Settings > System Settings** in the Admin Portal.
- **Retrieve feature usage data:** Start collecting feature usage data.
- **Retrieve feature usage data file list:** Start retrieval of the usage data file list.

## Label events

- **Add Label:** Define a new label for Core.
- **Delete Label:** Remove a label from Core.
- **Modify Label:** Make changes to a label.
- **Save As Label:** Copy a label to a new label.

## Sentry events

- **Add Integrated Sentry:** Establish a relationship between Core and an Integrated Sentry.
- **Add Standalone Sentry:** Establish a relationship between Core and a Standalone Sentry.
- **Delete Integrated Sentry:** End the relationship between Core and an Integrated Sentry.
- **Delete Standalone Sentry:** End the relationship between Core and a Standalone Sentry.
- **Disable Integrated Sentry:** Suspend the interaction between Core and an Integrated Sentry.
- **Disable Standalone Sentry:** Suspend the interaction between Core and a Standalone Sentry.
- **Edit Integrated Sentry:** Make changes to the settings for an Integrated Sentry.
- **Edit Standalone Sentry:** Make changes to the settings for a Standalone Sentry.
- **Enable Integrated Sentry:** Start the interaction between Core and an Integrated Sentry.
- **Enable Standalone Sentry:** Start the interaction between Core and a Standalone Sentry.
- **Manage Certificate:** Upload a certificate for Standalone Sentry.
- **Modify Sentry Preferences:** Make changes to the settings under **Services > Sentry**.
- **Regenerate Key:** Generate a new control key for attachment encryption.
- **Regenerate Attachment Encryption Control Key:**
- **Resync Integrated Sentry With Exchange:** Force Integrated Sentry to synchronize mailbox data with the Exchange server.

## Android Enterprise events

These events are only for Android devices.

- **Accept permissions for Android enterprise App:** Accept permissions on behalf of all users.
- **Apps@work setting modified:**
- **Connect Core to Android enterprise:** Establish binding between Core and Android Enterprise.
- **Disconnect Core from Android enterprise:** Remove binding between Core and Android Enterprise.
- **Save Restrictions for Android enterprise App:** Apply new or changed Android Enterprise restrictions.
- **Sync Google Users with Cores:** Synchronize user data between Google and Core.
- **Update catalog setting modified:**

## Custom attributes events

- **Add Custom Attribute:** Create a new customer attribute definition.
- **Modify Custom Attribute:** Modify a customer attribute definition.

## Compliance policy events

- **Add Compliance Policy Group:** Add a new compliance policy group.
- **Add Compliance Policy Rule:** Add a new compliance policy rule.
- **Apply Label to Compliance Policy Group:** Apply one or more labels to a compliance policy group.
- **Modify Compliance Policy Group:** Modify a compliance policy group.
- **Modify Compliance Policy Rule:** Modify a compliance policy rule.
- **Remove Compliance Policy Group:** Delete a compliance policy group.
- **Remove Compliance Policy Rule:** Delete a compliance policy rule.
- **Remove Label From Compliance Policy Group:** Delete one or more labels from a compliance policy group.

## Audit Logs use cases

A wealth of information is available to you in the Audit Logs. Querying the events allows you to monitor your Core system and resolve problems. You can run queries for one type of event, several types of events, or as many as you like. All you need to do is check the events you want to track, and then specify a time frame. The default time frame is the time between the last time the logs were purged and the current time.

For example:

- Use the certificate events to troubleshoot certificate issues. For example, query for certificates that have expired or have been revoked.
- Use the MDM events to troubleshoot MDM activity on devices. For example, query whether an MDM profile was removed, or whether a managed app was installed.
- Use the AppTunnel events to determine whether an administrator manually blocked or allowed AppTunnel on a device.
- Use the device events to determine activity taken on devices, such as unlocking the device, or deleting retired devices.
- Use the app events to determine whether an administrator has changed the app control rules in Core. A change to app control rules can result in Core taking, or not taking, compliance actions such as blocking email on devices.

This section presents several scenarios and how you can use the audit logs to resolve the problems they present.


## Personal information is wiped from devices

Suppose several of your users report that the personal information on their phones was wiped. How can you figure out how this happened? Using the audit logs, you can check the wipe actions recorded in the logs, and discover:

- who issued the Wipe commands
- when they occurred
- how many users are impacted

To resolve this problem:

1. In the Admin Portal, select **Logs**.
2. Select **Audit Logs**.
3. Click **Reset** at the bottom of the **Filters** panel to ensure that the previous search values are cleared.
4. In the **Filters** panel, specify a time interval that you suspect the device wipe(s) happened.
5. Open the **Device** events list.



Filters


Search by Performed (On|By)/Details

Action Date  
Select time... ▼

► Device (870)

► ActiveSync Device (0)

6. Select **Wipe**.



☐ Sign In (0)

☐ Sign Out (0)

☐ Unlock AppConnect Container (0)

☐ Unlock Device and AppConnect Container (0)

☐ Unlock Device (0)

☐ Update Device Comment (0)

☐ Wakeup (141)

☒ Wipe (0)


7. Click **Search**.
8. View the results of the search to determine:
  - when the devices were wiped
  - how many devices were wiped
  - which admin user issued the wipe commands

## Users are prompted for email passwords when not necessary

Suppose you set up your Exchange policy to not require your users to provide a password when they log in to email, but your users are still prompted for a password each time they access email.

To check for any changes to the Exchange policy that could cause this problem:

1. In the Admin Portal, select **Logs**.
2. Select **Audit Logs**.
3. Click **Reset** at the bottom of the **Filters** panel to ensure that the previous search values are cleared.
4. In the **Filters** panel, specify a time interval that you suspect changes to the Exchange policy happened.
5. Open the **Configuration** events list.



6. Select **Modify Configuration**.
7. Click **Search**.
8. View the results of the search to determine:
  - what changes were made recently to the Exchange policy
  - which admin user made the changes


## Users are prompted to create passwords

Suppose your users are prompted to create device passwords when that is not how you set up your Core. You can use the audit logs to discover if this requirement is set and when this change occurred.

To check for changes to mandatory passwords:



1. In the Admin Portal, select **Logs**.
2. Select **Audit Logs**.
3. Click **Reset** at the bottom of the **Filters** panel to ensure that the previous search values are cleared.
4. In the **Filters** panel, specify a time interval that you suspect changes to the security policy happened.
5. Open the **Policy** events list.



6. Select **Modify Policy**.
7. Click **Search**.
8. View the results of the search to determine:
  - what changes, if any, were made recently to the Security policy
  - which admin user made the changes

## Devices have lost their managed apps

If your users report missing managed apps, the cause is usually deleted labels.



For Android devices 11.0 or supported newer versions, the administrator does not have the ability to manage app installs on the personal side.

To determine whether labels were deleted from your Core:

1. In the Admin Portal, select **Logs**.
2. Select **Audit Logs**.
3. Click **Reset** at the bottom of the **Filters** panel to ensure that the previous search values are cleared.
4. In the **Filters** panel, specify a time interval that you suspect the labels were deleted.

5. Open the **Label** events list.



6. Select **Delete Label**.
7. Click **Search**.
8. View the results of the search to determine:
  - what labels, if any, were deleted recently
  - which admin user made the changes

## MDM Activity

The **Logs > MDM Activity** displays MDM-specific log entries.



Many of these entries are also available in **Logs > Audit Logs** in the **MDM** category.

Filter the log entries using the following criteria:

- Platform
- Date range
- States
- Actions
- User
- Device
- Error text
- Detail text
- Date range

## Viewing Errors

Errors result in the display of a **View Error** link in the **Error** column. Error details are not available for Android devices.

## Certificate Management

The **Logs > Certificate Management** tab displays certificate-related log entries. You can:

- view certificate log entries
- search certificate log entries
- remove selected certificates from the log
- revoke selected certificates from the log
- re-enroll selected certificates from the log



Actions on certificates are logged in **Logs > Audit Logs** in the **Certificate** category.

---

## How to search for certificate entries

When viewing the **Certificate Management** page, you can search for entries based on:

- expiration date
- user
- setting

### Procedure

To search the **Certificate Management** page:

1. In the Admin Portal, go to **Logs > Certificate Management**.
2. Specify one or more of the criteria in the following steps to describe the certificates you want to display.

3. (Optional) To specify a time range within which the certificates expired:

- In the **Expiration Date Range** field, click the calendar next to the field, and then click on a date. This date is the earliest day the certificates you are searching for expired.
- In the **To** field click the calendar next to the field, and then click on a date. This date is the latest day the certificates you are searching for expired.



An error message displays if you select a day in the **Expiration Date Range** field earlier than the day specified in the **To** field. For example you receive an error message if you:

- An error message displays if you select a day in the **Expiration Date Range** field earlier than the day specified in the **To** field. For example you receive an error message if you:
- select November 13th in the Expired Date Range field (earliest time a certificate expired).
- select October 15th in the To field (latest time a certificate expired).



The search can return fewer than all the certificates that expired during the specified time period if you specify other criteria in Step 4.

4. (Optional) In **Search by User/Setting Name**, enter a username or a setting name.

Certificate Enrollment	Displays the name of the Certificate Enrollment setting.
Setting	<p>Displays the configuration using the Certificate Enrollment.</p> <p>The configuration displays only for a non-cached Certificate Enrollment. Configuration names are not available for certificates created in VSP Version 6.0 or earlier.</p> <p>For a cached Certificate Enrollment certificate, you will always see - in the Setting Name, regardless of whether it was created prior to version 7.0 or created in version 7.0.</p> <p><b>For Android devices</b>, the <b>Setting Name</b> displays only for APPCONFIG, APPPOLICY, and WEB@WORK settings; otherwise a -displays.</p>

5. Click **Search**.

Search results are displayed in a table with the following columns:

Item	Description
User	The user name of the device user identified by the identity certificate.
Phone Number	The phone number associated with the device user identified by the identity certificate.
Email	The email address associated with the device user identified by the identity certificate.
Certificate Enrollment Name	The name of the certificate enrollment (such as SCEP, Local, Entrust) used to issue the identity certificate.
Setting Name	The name of the setting that uses the certificate enrollment, such as an Exchange or Web@Work setting.
Cert Type	Indicates whether the certificate is a user-provided certificate enrollment. Otherwise, this field is left blank.
Expiration Date	The date by which the identity certificate will no longer be valid.
Content	Click the <b>View</b> link to see the contents of the identity certificate itself.

## How to remove a certificate

This action removes the certificate from device, but does not remove the SCEP setting.

To remove a certificate:

1. Go to **Logs > Certificate Management**.
2. Select the certificate that you want to remove.
3. Click **Actions > Remove**.

## How to revoke a certificate

You can revoke certificates created using a Local Certificate Authority, OpenTrust, Entrust API Version 9, and Symantec Web Service PKI. Revoking a certificate adds the certificate to the CRL (Certificate Revocation List). When a device authenticates with Core, the system first checks the CRL to verify that the certificate is not on the list. If the certificate is on the list, authentication fails.

To revoke a certificate:

1. Go to **Logs > Certificate Management**.
2. Select the certificate that you want to revoke.

3. Click **Actions > Revoke**.

The certificate will be added immediately to the CRL so the next time the device attempts to authenticate, authentication will fail.

## How to re-enroll a SCEP certificate

This feature is not supported on Android devices.

## Service Diagnostic tests

The Service Diagnostic screen (**Services > Overview**) in the Admin Portal provides a health check for several services. The diagnostic tests determine whether your Core instance can connect to these services. An error indicates that you cannot reach the service.

The services checked are:

TABLE 1. SERVICE DIAGNOSTIC TESTS DESCRIPTIONS

Service	Test
AFW	Checks to see if: <ul style="list-style-type: none"><li>• Authentication server <a href="https://accounts.google.com/o/oauth2/token">https://accounts.google.com/o/oauth2/token</a> is reachable.</li><li>• API server <a href="https://www.googleapis.com/androidenterprise/v1/enterprises">https://www.googleapis.com/androidenterprise/v1/enterprises</a> is reachable.</li></ul>
APNS	Checks to see if: <ul style="list-style-type: none"><li>• MDM-APNS service is reachable.</li><li>• ENTERPRISE-APNS - No Enterprise APNS certificate configured.</li><li>• MDM-APNS - feedback service (<a href="https://tccentos122.auto.mobileiron.com:2196">tccentos122.auto.mobileiron.com:2196</a>) is not reachable.</li></ul>
APPCONFIG_COMMUNITY_REPO	Checks to see if the AppConfig Community Repository server is reachable: <a href="https://d2e3kgnhdeg083.cloudfront.net/com.example.OneTouchConfiguration/current/appconfig.xml">https://d2e3kgnhdeg083.cloudfront.net/com.example.OneTouchConfiguration/current/appconfig.xml</a>
APP_GATEWAY	Checks to see if App Gateway server is reachable: <a href="https://gwtest.mobileiron.com/gateway/gatewayServices/status.html">https://gwtest.mobileiron.com/gateway/gatewayServices/status.html</a>
BYPASS	Checks the connection between your Core instance and the Apple activation lock bypass server
CERTIFICATE_ENROLLMENT	Checks to see if:

TABLE 1. SERVICE DIAGNOSTIC TESTS DESCRIPTIONS (CONT.)

Service	Test
	<ul style="list-style-type: none"> <li>• Certificate Enrollment : System - iOS Enrollment SCEP is reachable.</li> <li>• Certificate Enrollment : System - iOS Enterprise AppStore SCEP is reachable.</li> <li>• Certificate Enrollment : System - Windows Phone Enrollment SCEP is reachable.</li> </ul>
CONFIGURATION	Tests the connection to the Certificate Enrollment server from your Core instance.
CONNECTOR	<p>Two tests are run:</p> <ul style="list-style-type: none"> <li>• One test checks whether Enterprise Connector is enabled (<b>Services &gt; Connector</b>)</li> <li>• If Enterprise Connector is enabled, the other test sends an HTTP Post request from your Core instance to each Connector configured, checking whether the Connector can communicate with your Core instance</li> </ul>
DEP	Sends a sample GET request to test the connection between your Core instance and the MDM server using Device Enrollment.
FCM	Checks whether Google Firebase Cloud Messaging (FCM) is reachable from your Core instance.
HEALTH_ ATTESTATION_ SERVICE	<p>Checks if the Health Attestation Service server is reachable.</p> <p><a href="https://has.spserv.microsoft.com/HealthAttestation/ValidateHealthCertificate/v1">https://has.spserv.microsoft.com/HealthAttestation/ValidateHealthCertificate/v1</a></p>
LDAP	<p>Two tests are run:</p> <ul style="list-style-type: none"> <li>• Checks LDAP from Core to verify the communication channel</li> <li>• For each Connector configured, checks the communication channel for the path from the LDAP server to Core, then Core to Connector, and finally from Connector to the LDAP server</li> </ul>
MAPQUEST	<p>Checks if the MapQuest Service server is reachable:</p> <p><a href="https://api.mqcdn.com/sdk/mapquest-js/v1.0.0/mapquest.js">https://api.mqcdn.com/sdk/mapquest-js/v1.0.0/mapquest.js</a></p>
PROXY	No proxy is configured.
SENTRY	Checks the connection between your Core instance and the Sentry used (either integrated standalone). As part of this test, the connection between ActiveSync server and Sentry is checked also.

TABLE 1. SERVICE DIAGNOSTIC TESTS DESCRIPTIONS (CONT.)

Service	Test
SENTRY_WITH_ACTIVASYNC	No Integrated Sentry server(s) configured. No Standalone Sentry server(s) configured.
SERVICES	Checks whether the IP addresses reserved for FCM are reachable.
VPP	Sends a GET request to verify the connection between Core and the Apple License server.

## Running Service Diagnostic tests

To run the Service Diagnostic tests:

1. Go to **Services > Overview**.
2. To test one or all of the services:
  - Click **Verify All** to test the listed services
  - Click **Verify** next to a specific service to test that service

## Device log encryption on Android devices

Log files can be emailed by using the **Send Log** option in Mobile@Work for Android. You can choose whether the log files are encrypted when they are provided to the email app. The choice affects the log files of the following:

- Mobile@Work for Android
- Secure Apps Manager
- AppConnect-enabled apps (including what the app logs and what the AppConnect wrapper around the app logs)

The security policy for a device contains the option for choosing whether the emailed log files are encrypted. The default setting is to **not** encrypt the files.

By default, encrypted log files can be decrypted only by Ivanti Technical Support. If you want to encrypt the log files using your own certificate, see ["Encrypting device logs with your own certificate" on the next page](#).



Regardless of the device log encryption setting, the log files never include passwords, certificate content, license information, or other sensitive authentication data.

By encrypting the emailed log files, you improve security because the data is readable only by Ivanti Technical Support when using the default encryption, or by your own enterprise when using your certificate for encryption. Since emailing logs for troubleshooting is a common practice, you typically choose to encrypt the logs.



## Procedure

1. Go to **Policies & Configs > Policies**.
2. Select the security policy for the appropriate devices.
3. Click **Edit**.
4. In the **Data Encryption** section, for **Device Log Encryption**, select **On**.
5. Click **Save**.

## Encrypting device logs with your own certificate

You can define a log encryption configuration that enables device users to send encrypted logs to an administrator's email address from their devices. The configuration includes a certificate for encrypting logs and an email address to which encrypted logs are to be sent. Devices sync with Core and receive the configuration after you assign the configuration to the relevant labels.

This feature requires:

- Mobile@Work 10.0.0.0 for Android or supported newer versions
- Secure Apps Manager 8.3.0.0 or supported newer versions
- On the security policy, device log encryption must be on.

## Related topics

["Device log encryption on Android devices" on the previous page](#)

## Before you begin

Upload a certificate to Core, as described in ["Certificates settings" on page 332](#).

## Procedure

1. In the Admin Portal, select **Policies & Configs > Configurations**.
2. Click **Add New** and select **LogEncryption**. The New Log Encryption Setting dialog box opens.

3. Fill in the following:

Field	Description
Name	Enter a name for the configuration.
Email Address	Enter an email address to which encrypted logs may be sent. The <b>To:</b> field of the email is automatically filled with this address. If you do not enter an email address here, the device user fills in the <b>To:</b> field.
Certificate	From the drop-down list, select a certificate you have already uploaded to Core.

4. Click **Save**.
5. On the Configurations page, select the configuration you just defined.
6. Click **Actions > Apply to Label**, and select the label to which you want to apply the log encryption configuration.

## Pull client logs for client devices

To troubleshoot challenging technical support issues when working with Ivanti Technical Support, you can pull client logs of an Android or iOS client device without requiring any interaction from the end user. From the Admin portal, use the Pull client log command to obtain client logs. The Pull client log action as well as the success or failure of the event is captured in the Audit logs. This feature does not work on Windows and chromeOS devices.



The Pull client log command is not available to delegated admin roles; only administrators who have the Manage Devices role can use this feature.

---

When the Pull client logs command is delivered to the device, it instructs the Mobile@Work client to collect logs running on the device. This may include logs from all the secure apps running on the device. These logs are pulled to the server's file storage.

Potentially, there is one interaction that may cause a message to be displayed to a device user. If the device has an AppConnect configuration and a number of secure apps installed, then the Mobile@Work client may momentarily go to the foreground of the device display and request secure apps logs from the Secure AppManager application. Under these conditions, a message is displayed on the device that states a device administrator is pulling Mobile@Work client logs and logs from the secure applications for analysis. Also, the message states that this is a short interruption.

When you have an AppConnect configuration that is running and SecureApps Manager and the SecureApps Manager does not communicate with Mobile@Work in a timely fashion, then the end user may be prompted to log in again.



You can retrieve the client logs from the System Manager. Select **Troubleshooting > Logs** in the Export Logs section. Select **Show Tech (All Logs)**. For more information see "Exporting logs" in the *Core System Manager Guide*.

---

Before you pull a client log, you may want to set log encryption and then upload this configuration on the device. When you enable log encryption, the client will encrypt logs when the Pull client log action is taken. By default, log encryption is set to off. To set log encryption, you can use the default log encryption certification or custom certification. See "[Device log encryption on Android devices](#)" on page 440 for instructions on how to set device log encryption for Android devices.

To access the Pull client log command:

1. Go to **Devices & Users > Devices**.
2. Select the check box next to a device. You may only select one device.
3. Click the **Actions** button.
4. Select **Pull Client Logs**. The Pull Client Logs dialog box displays. The **Devices** field displays the name of the device that you selected. You cannot add additional devices here.
5. (Optional) Add any notes about this action in the **Notes** section.
6. Click the **Pull Client Logs** button to launch this request to the server.

# Office 365

This section contains the overview, policies, configurations, user groups, reports and settings as pertains to Office 365:

- ["Office 365 App Protection overview" below](#)
- ["Office 365 App Protection policies" on the next page](#)
- ["Office 365 App Protection configurations" on page 454](#)
- ["Office 365 App Protection user groups" on page 456](#)
- ["Office 365 App Protection reports" on page 456](#)
- ["Office 365 App Protection settings" on page 462](#)

## Office 365 App Protection overview

Office 365 App Protection provides important Data Loss Prevention (DLP) for Office 365 apps, such as Microsoft Word, Excel, PowerPoint, and so on. It allows administrators to manage policies and configurations that secure data in Office 365 apps on Android devices.



Some Graph APIs can be in beta. Use this feature accordingly.

---

You can manage Office 365 apps by:

- Enforcing PIN for Office 365 apps
- Disabling contacts to sync from Office 365 apps
- Preventing users from printing from Office 365 apps
- Preventing outbound data sharing from Office 365 apps

## Prerequisites for using Office 365 App Protection

Before you can use Office 365 App Protection, you must have:

- A valid Core license.
- A valid Intune subscription or a Microsoft EMS subscription that includes Intune.
- A valid Office Enterprise or Business subscription with access to Office 365 apps on a mobile device.
- One or more Office 365 apps.
- Synced your Active Directory users to your Azure Active Directory.
- One Drive for Business installed on devices to protect data on Word, Excel, and PowerPoint.

- Intune Company Portal app installed on Android devices.
- Device users are not required to sign in, but this app must be installed on the device to protect data on device.

## Office 365 App Protection window

---



Before you register Core as an Azure app, only the **Services > Microsoft Graph > Settings** tab is enabled. Once you register Core as an Azure app, all the tabs are enabled.

---

Access the Office 365 App Protection window by logging into the Admin Portal and going to Services > Microsoft Graph. This window includes the following options:

- **Policies:** Use this tab to add and manage Office 365 DLP policies. You can perform the following actions on each policy:
  - Assign one or more User groups to the policy.
  - Assign apps to the policy.
  - Delete the policy.

See ["Adding Office 365 App Protection policies" on the next page](#) for details on how to add a Office 365 App Protection policy.

- **Configurations:** Use this tab to add and manage Office 365 DLP configurations. You can perform the following actions on each policy:
  - Assign one or more User groups to the configuration.
  - Assign apps to the configuration.
  - Delete the configuration.

See ["Office 365 App Protection configurations" on page 454](#) for details on how to add a Office 365 App Protection configuration.

- **User Groups:** Use this tab to search for and view user groups available to add to a policy or configuration.
- **Reports:** Use this tab to view and download user and app reports and manage wipe requests. These reports are populated with data that comes from Azure Active Directory during real-time syncs.
- **Settings:** Use this tab to register Core as an Office 365 app. These reports are populated with data that comes from Azure Active Directory during real-time syncs.

## Office 365 App Protection policies

Once you register Core as an Azure app you can add and manage Office 365 App Protection policies in the Microsoft Azure cloud for Office 365 apps.

This section includes the following topics:

- ["Adding Office 365 App Protection policies" below](#)
- ["Editing Office 365 App Protection policies" below](#)
- ["Managing Office 365 App Protection policies" on the next page](#)
- ["Add Office 365 App Protection policies window" on page 448](#)



Before using this feature, complete the prerequisites described in the following section:  
["Prerequisites for using Office 365 App Protection" on page 444.](#)

---

### Related topics

- ["Office 365 App Protection overview" on page 444](#)
- ["Office 365 App Protection configurations" on page 454](#)
- ["Office 365 App Protection user groups" on page 456](#)
- ["Office 365 App Protection reports" on page 456](#)
- ["Office 365 App Protection settings" on page 462](#)

## Adding Office 365 App Protection policies

Policies use data populated from Azure Active Directory during real-time syncs.

### Procedure

1. Log into the Admin Portal.
2. Go to **Services > Microsoft Graph > Policies > Add**.
3. Complete the **App protection policies** form.  
Refer to ["Add Office 365 App Protection policies window" on page 448](#) for details.
4. In the ["Compliance Actions" on page 452](#) section, select a Setting, enter the value, and select an Action. Refer to the ["App protection policies fields " on page 448](#) table.
5. Click **+Add** to configure additional compliance actions.
6. Click **Save** to add the policy to the list of DLP policies on the **Policies** table.

## Editing Office 365 App Protection policies

Policies use data populated from Azure Active Directory during real-time syncs.

## Procedure

1. Log into the Admin Portal.
2. Go to **Services > Microsoft Graph > Policies**.
3. Click the name of a policy you want to edit.
4. Complete the **App protection policies** form.

Refer to ["Add Office 365 App Protection policies window" on the next page](#) for details.

5. In the ["Compliance Actions" on page 452](#) section, select a Setting, enter the value, and select an Action. Refer to the ["App protection policies fields " on the next page](#)table.
6. Click **+Add** to configure additional compliance actions.
7. Click **Save** to save the policy edits.

## Managing Office 365 App Protection policies

You can take any of the following actions on each Office 365 App Protection policy:

- Assign User Groups
- Assign Apps
- Delete Policies

## Procedure

1. Log into the Admin Portal.
2. Go to **Services > Microsoft Graph > Policies**.
3. Locate a policy you want to manage and go to the **Actions** column.
4. Assign user groups to the App Protection policy.
  - a. Click the **Assign User Groups** icon.
  - b. Search for user groups.
  - c. Select one or more user groups to add to the policy.
  - d. Click **Save**.

5. Assign Office 365 apps to the app protection policy.
  - a. Click the **Assign Apps** icon.
  - b. Search for apps.
  - c. Select one or more apps to add to the policy.
  - d. Click **Save**.
6. Delete an Office 365 App Protection policy.
  - a. Click the **Delete Policy** icon.
  - b. Click **Yes** to confirm deletion of the policy.

The Office 365 App Protection policies take affect:

- After assigning the policy to a user group.
- A user from the assigned user group logs into an Office 365 app using AAD credentials.

## Add Office 365 App Protection policies window

Access this window by logging into the Admin Portal and selecting **Services > Microsoft Graph > Policy** and clicking **Add** or clicking a policy to edit.

The following table summarizes fields and descriptions in the **Add App Policies** window. Also, refer to the ["App protection policies fields "](#) below table.

TABLE 1 . APP PROTECTION POLICIES FIELDS

Fields	Description
Name	This required field is the name used to track the Office 365 App Protection policy in Core.
Description	Describes the profile's purpose (optional).
Platform	Select the platform for the Office 365 apps. The options are: <b>iOS</b> or <b>Android</b> . Some of the other options on this form will change depending on which platform you select. Refer to the relevant platform's Device Management Guide.
<b>Data Relocation</b>	
Prevent Android backups	Choose <b>Yes</b> to prevent this app from backing up data to the Android Backup Service Choose <b>No</b> to allow this app to back up data. (The default is <b>Yes</b> .)
Allow app to transfer data to other apps	Use this option to specify what apps can receive data from this app. The options are listed below.



TABLE 1. APP PROTECTION POLICIES FIELDS (CONT.)

Fields	Description
	<ul style="list-style-type: none"> <li>• <b>Policy managed apps:</b> Allow transfer only to other policy-managed apps.</li> <li>• <b>All apps:</b> Allow transfer to any app (default.)</li> <li>• <b>None:</b> Do not allow data transfer to any app, including other policy-managed apps.</li> </ul> <p>When any of the above options except <i>All apps</i> are selected, the exempted apps are listed to the right of the <i>Allow app to receive data from other apps</i> field. Modifying these settings changes how data is transferred to other applications.</p>
Allow app to receive data from other apps	<p>Select an option to specify what apps can transfer data to this app.</p> <ul style="list-style-type: none"> <li>• <b>Policy managed apps</b> - Allow app to receive data from only other policy-managed apps.</li> <li>• <b>All apps</b> Allow app to receive data from other apps (default.)</li> <li>• <b>None</b> - Do not allow app to receive data from any app, including other policy-managed apps.</li> </ul>
Prevent "Save As "	<p>Select to disable the use of the Save As (a new document) option in any app that uses this policy. De-select if you want to allow the use of Save As. (Default is unchecked.)</p> <p>Selecting Prevent Save As activates the <b>Select which storage services corporate data can be saved to field</b>. The options are:</p> <ul style="list-style-type: none"> <li>• OneDrive for Business</li> <li>• SharePoint</li> <li>• Local Storage</li> </ul>
Restrict cut, copy and paste with other apps	<p>Specifies when cut, copy, and paste actions can be used with this app. The options are listed below.</p> <ul style="list-style-type: none"> <li>• <b>Blocked:</b> Do not allow cut, copy, and paste actions between this app and any other app.</li> <li>• <b>Policy managed apps:</b> Allow cut, copy, and paste actions between this app and other policy-managed apps.</li> <li>• <b>Policy managed with paste in:</b> Allow cut or copy between this app and other policy-managed apps. Allow data from any app to be pasted into this app.</li> </ul>

TABLE 1. APP PROTECTION POLICIES FIELDS (CONT.)

Fields	Description
	<ul style="list-style-type: none"> <li>• <b>Any app:</b> No restrictions for cut, copy, and paste to and from this app. (This is the default.)</li> </ul>
Block screen capture and Android assistant	Check this to block the ability to use screen captures and block Android assistant. Default is allowed.
Encrypt app data	Select to encrypt app data that is associated with an Intune mobile application management policy. Encryption is provided by Microsoft. Data is encrypted synchronously during file I/O operations according to the setting in the mobile application management policy. Managed apps on Android use AES-128 encryption in CBC mode utilizing the platform cryptography libraries. The encryption method is not FIPS 140-2 certified. SHA-256 encryption is supported as an explicit instruction using the SigAlg parameter and will only work on devices 4.2 and above. Content on the device storage is always encrypted.
Disable app encryption when device encryption is enabled	This field activates when the <i>Encrypt app data</i> field is selected. Disables app encryption when the device encryption is enabled. Default is de-selected.
Disable contact sync	When this setting is enabled, users cannot sync contacts to the native address book. Default is un-checked.
Disable printing	Select this to block printing protected data from the app. Default is un-checked.
Restrict web content to display in the Managed Browser	<p>Check this to enforce web links in the app to be opened in the Managed Browser app.</p> <p>Uncheck this to open web links in Chrome. Default is de-selected.</p>
Block third party keyboards	When this setting is enabled, a third-party keyboard cannot be used with protected apps.
<b>Access</b>	
Require PIN for access	Select this to require users to enter a PIN to access this app. The user is prompted to set up this PIN the first time the app is run. Default is selected, which activates all the fields in the Access section of this page.
Allow simple PIN	<p><b>Allow simple PIN:</b> Check this to allow users to use simple PIN sequences like 1234 or 1111. Choose No to prevent them from using simple sequences. (The default value is checked.)</p> <ul style="list-style-type: none"> <li>• <b>PIN length:</b> Specify the minimum number of digits in a PIN sequence. (The default value is 4.)</li> </ul>

TABLE 1. APP PROTECTION POLICIES FIELDS (CONT.)

Fields	Description
	When the <i>Require PIN for access</i> field is de-selected, this field is deactivated.
Allow fingerprint of PIN (Android 6.0+)	<p>Select this to allow the user to use Touch ID instead of a PIN for app access. (The default is checked.)</p> <p>When the <i>Require PIN for access</i> field is de-selected, this field is deactivated.</p>
Override fingerprint with PIN after timeout (minutes)	<p>If required, depending on the timeout (minutes of inactivity), a PIN prompt will override Touch ID prompts. If this timeout value is not met, the Touch ID prompt will continue to show. This timeout value specified under "Recheck the access requirements after (minutes of Activity)". On iOS, this feature requires the app to have Intune SDK version 8.1.1 or above.</p> <p><b>Inactivity timeout:</b> Specify a time in minutes after which the PIN will override the use of a fingerprint.</p> <p>When the <i>Require PIN for access</i> field is de-selected, this field is deactivated.</p>
Disable app PIN when device PIN is managed	<p>Select to disable the app PIN when a device lock is detected on an enrolled device. If you select this option, it overrides the requirements for PIN or Touch ID. (The default is unchecked.)</p> <p>When the <i>Require PIN for access</i> field is de-selected, this field is deactivated.</p>
Require corporate credentials for access	<p>Select to require corporate credentials instead of a PIN for app access. Not selecting this option overrides the requirements for PIN or Touch ID. The user will be prompted to provide their corporate credentials. (The default is unchecked.)</p>
Recheck the access requirements after (minutes)	<p>Timeout for access requirements is measured in terms of the time of inactivity between any policy-managed application.</p> <ul style="list-style-type: none"> <li>• <b>Timeout:</b> Enter the number of minutes before the access requirements (defined earlier in the policy) are rechecked. For example, an administrator turns on PIN in the policy, which means a when device user opens a app, a PIN must be entered. When using the Recheck the access requirements setting, the device user would not have to re-enter the PIN on any app for another 30 minutes. (The default is 30.)</li> </ul>

## Compliance Actions

Use the Compliance Actions Settings to set the security requirements for your access protection policy. Several settings are provided with pre-configured values and actions.

### Procedure

1. Select a Setting, enter the value, and select an Action. Refer to the table below.
2. Click **+Add** to configure additional compliance actions.
3. At the top of the Policies tab, click **Save**.

TABLE 2. COMPLIANCE ACTION SETTINGS

Setting	Description
Max PIN attempts (default)	Specify the number of tries the device user has to successfully enter the correct PIN before the configured action is taken. (Default value is 30 minutes.) Actions include: <ul style="list-style-type: none"><li>• <b>Reset PIN</b> - The user must reset their PIN.</li><li>• <b>Wipe data</b> - The user account that is associated with the application is wiped from the device.</li></ul>
Offline grace period (default)	This is the number of minutes that apps can run offline. Specify the time (in minutes) before the access requirements for the app are rechecked. After this period is expired, the app will <b>Block Access</b> . The default is 720 minutes (12 hours.)
Offline grace period (default)	This is the number of minutes that apps can run offline. Specify the time (in days) before the access requirements for the app are rechecked. After this period is expired, the app will <b>Wipe data</b> . The default is 90 days.
Jailbroken/rooted device	<ul style="list-style-type: none"><li>• <b>Block access</b> - Prevent this app from running on jailbroken or rooted devices. The device user continues to be able to use this app for personal tasks, but will have to use a different device to access data in this app.</li><li>• <b>Wipe data</b> - The device user account that is associated with the application is wiped from the device</li></ul>
Min OS version	Select this to require a minimum operating system to use this app. Enter the value in the following format [major].[minor] and select one of the following actions:

TABLE 2. COMPLIANCE ACTION SETTINGS (CONT.)

Setting	Description
	<ul style="list-style-type: none"> <li>• <b>Block access</b> - The device user will be blocked from access if the version on the device does not meet the requirement.</li> <li>• <b>Wipe data</b> - The device user account that is associated with the application is wiped from the device.</li> <li>• <b>Warn</b> - The user will see a notification if the operating system version on the device does not meet the requirement. This notification can be dismissed.</li> </ul>
Min App version	<p>Check this option to require a minimum app version to use the app. The user will be blocked from access if the app version on the device does not meet the requirement.</p> <ul style="list-style-type: none"> <li>• <b>Block access</b> - The device user will be blocked from access if the app version on the device does not meet this requirement.</li> <li>• <b>Wipe data</b> - The device user account that is associated with the application is wiped from the device.</li> <li>• <b>Warn</b> - The user will see a notification if the app version on the device does not meet the requirement. This notification can be dismissed.</li> </ul>
Min Patch version	<p>Select to require devices have a minimum Android security patch released by Google. Click the calendar icon to select the date for the action below to occur:</p> <ul style="list-style-type: none"> <li>• <b>Block access</b> - The device user will be blocked from access if the Android version on the device does not meet this requirement.</li> <li>• <b>Wipe data</b> - The device user account that is associated with the application is wiped from the device.</li> <li>• <b>Warn</b> - The user will see a notification if the Android version on the device does not meet the requirement. This notification can be dismissed.</li> </ul>
Device manufacturer(s)	<p>Specify a device manufacturer that is required to use this app. Actions include:</p> <ul style="list-style-type: none"> <li>• <b>Block access</b> - Only devices that match the specified manufacturer can use the app. All other devices are blocked.</li> <li>• <b>Wipe data</b> - The user account that is associated with the application is wiped from the device.</li> </ul>

## Office 365 App Protection configurations

Once you register Core as an Azure app you can create custom configurations for Office 365 apps. App Configurations can be used to specify custom app configurations for Office 365 apps. Configurations can include setting a local encryption scheme for OneDrive, setting Skype parameters, and so on.

This section includes the following topics:

- ["Creating Office 365 App Protection configurations" below](#)
- ["Editing a Office 365 App Protection configuration" below](#)
- ["Managing Office 365 App Protection configurations " on the next page](#)



Before using this feature, complete the prerequisites described in the following section:  
["Prerequisites for using Office 365 App Protection" on page 444.](#)

---

### Related topics

- ["Office 365 App Protection overview" on page 444](#)
- ["Office 365 App Protection policies" on page 445](#)
- ["Office 365 App Protection user groups" on page 456](#)
- ["Office 365 App Protection reports" on page 456](#)
- ["Office 365 App Protection settings" on page 462](#)

## Creating Office 365 App Protection configurations

Configurations use data populated from Azure Active Directory during real-time syncs.

1. Log into the Admin Portal.
2. Go to **Services > Microsoft Graph > Configurations > Add**.
3. Add a name (required) and description (optional).
4. Click **Add+** to add one or more key-value pairs.  
The values are strings with no limitations or restrictions.
5. Click **Save** to add the configuration to the list in the configurations table.

## Editing a Office 365 App Protection configuration

Configurations use data populated from Azure Active Directory during real-time syncs.

## Procedure

1. Log into the Admin Portal.
2. Go to **Services > Microsoft Graph > Configurations**.
3. Click the name of a configuration you want to edit.  
Use the search field to search by name.
4. Make any necessary changes.
5. Click **Save** to update the configuration edits.

## Managing Office 365 App Protection configurations

You can take any of the following actions on each Office 365 App Protection configuration:

- Assign User Groups
- Assign Apps
- Delete Policies

## Procedure

1. Log into the Admin Portal.
2. Go to **Services > Microsoft Graph > Configurations**.
3. Locate a configuration you want to manage and go to the **Actions** column.
  - a. Assign user groups to the app protection configuration.
  - b. Click the **Assign User Groups** icon.
  - c. Search for user groups.
  - d. Select one or more user groups to add to the configuration.
  - e. Click **Save**.
4. Assign Office 365 apps to the app protection configuration.
  - a. Click the **Assign Apps** icon.
  - b. Search for apps.
  - c. Select one or more apps to add to the configuration.
  - d. Click **Save**.

5. Delete an Office 365 App Protection configuration.
  - a. Click the **Delete Configuration** icon.
  - b. Click **Yes** to confirm deletion of the configuration.

Changes to the configurations take effect after:

- assigning the configuration to a user group.
- a user from the assigned user group logs into an Office 365 app using AAD credentials.

## Office 365 App Protection user groups

Use the **User Groups** tab to search for and view user groups available to add to one or more Office 365 App Protection policies or configurations. Access a list of user groups by logging into the Admin Portal and selecting **Services > Microsoft Graph > User Groups**.



Before using this feature, complete the prerequisites described in the following section:  
["Prerequisites for using Office 365 App Protection" on page 444.](#)

---

### Related topics

- ["Office 365 App Protection overview" on page 444](#)
- ["Office 365 App Protection policies" on page 445](#)
- ["Office 365 App Protection configurations" on page 454](#)
- ["Office 365 App Protection reports" below](#)
- ["Office 365 App Protection settings" on page 462](#)

## Office 365 App Protection reports

Reports for out of compliance data, devices, apps, and users, is populated from Azure Active Directory during real-time syncs. Access the reports by logging into the Admin Portal and selecting **Services > Microsoft Graph > Reports**. Use the **Reports** tab to:

- search, view, or download a .csv report by user
- search, view, or download a .csv report by app
- create and manage wipe requests
- refresh reports

This section includes the following topics:



- ["" below "Office 365 App Protection reports window" below](#)
- ["Managing Out of Compliance Users reports" below](#)
- ["Managing Selective Wipe reports" on the next page](#)
- ["Downloading App Protection reports" on page 459](#)
- ["Downloading App Configuration reports" on page 460](#)



Before using this feature, complete the prerequisites described in the following section:  
["Prerequisites for using Office 365 App Protection" on page 444.](#)

---

## Related topics

- ["Office 365 App Protection overview" on page 444](#)
- ["Office 365 App Protection policies" on page 445](#)
- ["Office 365 App Protection configurations" on page 454](#)
- ["Office 365 App Protection user groups" on the previous page](#)
- ["Office 365 App Protection settings" on page 462](#)

## Office 365 App Protection reports window

Manage reports from the Admin Portal by going to **Services > Microsoft Graph** to open the Office 365 App Protection window. This window includes several options, which are listed in the left pane. When you select one, the right pane changes to include details of the selected option.

- **Out of Compliance Users:** This option is selected by default. Use it to manage reports on users who are out of compliance.
- **Selective Wipe:** Use this option to request Azure Active Directory wipe Office 365 app data from selected devices.
- **App Protection Reports:** Use this tab to view and download app protection reports by users and by apps. These reports are populated with data from Azure Active Directory during real-time syncs.
- **App Configuration Reports:** Use this tab to view and download app configuration reports by users and by apps. These reports are populated with data from Azure Active Directory during real-time syncs.

## Managing Out of Compliance Users reports

Use this option to manage reports on users who are out of compliance.

## Procedure

1. Log into the Admin Portal.
2. Select **Services > Microsoft Graph > Reports > Out of Compliance Users**.
3. Click **Download Report** to download a .csv report from Azure Active Directory of users who are out of compliance.
4. Click **Refresh Report** to get the most recent data from Azure Active Directory after the latest sync.
5. Select one or more of the users listed in the report or select all.
6. Click **Wipe Apps Data** to send a wipe request to Azure Active Directory for users.

## Managing Selective Wipe reports

Use this option to create and manage requests you send to Azure Active Directory to wipe Office 365 app data from selected devices.

### Creating wipe requests

#### Procedure

1. Log into the Admin Portal.
2. Select **Services > Microsoft Graph > Reports**.
3. Expand **Selective Wipe**.
4. Click **Create Wipe Request**.
5. Enter or search for a user name, then select one or more of the user's devices.
6. Click **Create Wipe Request** to request Azure Active Directory wipe Office 365 app data from one or more selected devices.

### Managing wipe requests

#### Procedure

1. Log into the Admin Portal.
2. Select **Services > Microsoft Graph > Reports**.
3. Expand **Selective Wipe**.
4. Click **Wipe Request**.
5. Select one or more pending wipe requests and click **Cancel Wipe Request**.
6. Click **Refresh** to update the status of the pending wipe requests.

## Downloading App Protection reports

App Protection Reports show applications protected by the policies that are created and assigned to them from the **Policies** tab. Use this option to download app protection .csv reports by users or apps.

### Downloading App Protection reports by user

#### Procedure

1. Log into the Admin Portal.
2. Select **Services > Microsoft Graph > Reports**.
3. Expand **App Protection Reports**.
4. Click **User**.
5. Search for, or enter a user name.

See "[App Protection User reports table](#)" below for details.

6. Click **Download Report**.

### App Protection User reports table

Select this option to view and download reports and to refresh the report data. This option provides app information for a specified user. These reports are populated with data that comes from Azure Active Directory during real-time syncs.

TABLE 1. APP PROTECTION USER REPORTS FIELDS

Fields	Description
Bundle ID/Package ID	This column lists the unique identifier for the app.
Device Name	This column lists the name of the device.
Device Type	This column lists the type of device.
Policies	This column lists the app protection policies assigned to this app.
Status	This column lists the sync status of the app. The options for this column are: <b>Synced</b> , <b>Synced, but out of date</b> , and <b>Not synced</b> .
Last Check-In	This column lists the time stamp of the last time this app synced with Azure.

## Downloading App Protection reports by app

### Procedure

1. Log into the Admin Portal.
2. Select **Services > Microsoft Graph > Reports**.
3. Click **App**.
4. Complete the form.  
See "[App Protection App reports table](#)" below for details.
5. Click **Download Report**.
6. Expand **App Protection Reports**.

### App Protection App reports table

This option provides user data for selected apps. These reports are populated with data that comes from Azure Active Directory during real-time syncs.

TABLE 2. APP PROTECTION APP REPORTS

Fields	Description
Platform	Select the OS platform for which you want to see apps. The options are Android and iOS.
App	Select the single app for which you want to receive a report. This list changes depending on the platform you select.
Status	Select the user's protection status from the list. The options are <b>Protected</b> and <b>Unprotected</b> .
User	This column lists the users that match the search criteria.
Email	This column provides the user's email address.

## Downloading App Configuration reports

App Configuration Reports show applications with configurations defined and assigned to them under the **Configuration** tab. Use this option to download app configuration .csv reports by users or apps.

## Downloading App Configuration reports by user

### Procedure

1. Log into the Admin Portal.
2. Select **Services > Microsoft Graph > Reports**.
3. Expand **App Configuration Reports**.
4. Click **User**.
5. Search for, or enter a user name.

See "[App Configuration User reports table](#)" below for details.

6. Click **Download Report**.

### App Configuration User reports table

Select this option to view and download reports and to refresh the report data. This option provides app information for a specified user. These reports are populated with data that comes from Azure Active Directory during real-time syncs.

TABLE 3. APP CONFIGURATION USER REPORTS FIELDS

Fields	Description
Bundle ID/Package ID	This column lists the unique identifier for the app.
Device Name	This column lists the name of the device.
Device Type	This column lists the type of device.
Configurations	This column lists the app protection configurations assigned to this app.
Last Check-In	This column lists the time stamp of the last time this app synced with Azure.

## Downloading App Configuration reports by app

### Procedure

1. Log into the Admin Portal.
2. Select **Services > Microsoft Graph > Reports**.
3. Expand **App Protection Reports**.
4. Click **App**.

5. Complete the form.

See ["App Configuration App reports table" below](#) for details.

6. Click **Download Report**.

## App Configuration App reports table

This option provides user data for selected apps. These reports are populated with data that comes from Azure Active Directory during real-time syncs.

TABLE 4. APP CONFIGURATION APP REPORTS

Fields	Description
Platform	Select the OS platform for which you want to see apps. The options are Android and iOS.
App	Select the single app for which you want to receive a report. This list changes depending on the platform you select.
User	This column lists the users that match the search criteria.
Email	This column provides the user's email address.

## Office 365 App Protection settings

Use the **Settings** tab to set up Office 365 App Protection policies to help protect your company's data.

**License Required:** This feature requires a separate license. In addition, this feature requires an Intune subscription from Microsoft. Prior to using this feature, ensure your organization has purchased the required licenses.

### Related topics

- ["Office 365 App Protection overview" on page 444](#)
- ["Office 365 App Protection policies" on page 445](#)
- ["Office 365 App Protection configurations" on page 454](#)
- ["Office 365 App Protection user groups" on page 456](#)
- ["Office 365 App Protection reports" on page 456](#)

## Zebra Support

Core enables administrators to apply firmware updates to Zebra Devices using Zebra's Cloud OTA (Over the Air) service. Zebra devices are managed without OTA. From Core version 10.6 or supported newer versions, Zebra OTA firmware update is supported. This allows you to activate the Zebra OTA service for your Core, thus enabling you to receive firmware updates for OTA-capable Zebra Devices through firmware policies.

Process for Zebra support:

1. ["Adding a Google account to an Android Enterprise managed device" on page 20](#)
2. ["Enrolling in the Zebra OTA \(Over The Air\) service" below](#)
3. ["Setting the firmware policy for Zebra devices" on page 468](#)
4. ["Checking the Zebra device firmware download status" on page 472](#)

## **Enrolling in the Zebra OTA (Over The Air) service**

You can activate the Zebra OTA (Over The Air) service for your Core that would enable you to receive firmware updates for OTA capable Zebra devices through firmware policies. Core uses OAuth 2.0 for authentication with Zebra.

### **Before you begin**

- Be sure you have [added a Google account to the Android Enterprise managed device](#).
- You will need to write down your Zebra OTA account credentials, when you get them.
- The enrollment process needs to be completed within ten minutes, otherwise the token expires.

## Procedure

1. In the Admin portal, go to **Services > Zebra**.
2. The **Zebra OTA Enrollment** page displays.

The screenshot shows the Mobiliron Core Admin portal interface. The top navigation bar includes links for Dashboard, Devices & Users, Admin, Apps, Policies & Configs, Services, Settings, and Logs. Below this, a sub-navigation bar lists various services: Overview, Access, Sentry, Connector, LDAP, Google, Operators, Local CA, and Trusted Root Certificates. The main content area is titled "Zebra OTA Enrollment" and contains a sub-header: "Follow the steps below to link your Mobiliron Core to Zebra's Cloud OTA Service. This will enable you to configure and apply Zebra's OTA firmware policies."

Step 1: Link to Zebra's OTA service.

Step 2: Verify that you have linked to the service.

Diagram illustrating the process: Mobiliron Core → ZEBRA → Mobiliron Core.

Clicking the button below will open a new window where you will log in with your Zebra OTA account credentials.

Follow the steps to request an approval to link to your account. If successful, you will see a message that you have been authorized.

Once authorized you must complete Step 2 within 10 minutes or you will need to start over.

Close the window and return here to complete Step 2.

Begin

In section one, click the **Begin** button. A new browser window opens the Zebra login page.

3. Enter your Zebra login credentials and click **Sign In**. If you do not have credentials, contact Zebra.


The screenshot shows a web browser window with the URL [https://pi.zebra.com/as/user\\_authz.oauth2?user\\_code=KQRT-GXQH](https://pi.zebra.com/as/user_authz.oauth2?user_code=KQRT-GXQH). The page title is "Sign In". Below the title, it says "Please enter your Username & Password". There are two input fields: "Username" and "Password". The Username field contains the text "zebra.com". The Password field contains a series of dots. Below the input fields is the Zebra logo and a "Sign In" button. At the bottom of the page, there are links for "Forgot your username?", "Don't know your password?", "Need to change your password?", and "Need additional password assistance?".



4. The Connect a device page displays with the Activation code already inserted. Click **Confirm**.



5. The Request for Approval page displays. Make sure all the check boxes are selected and then click **Allow**.



6. The Connect a device page displays. When the device is connected, a confirmation displays.



7. Return to the **Core > Services > Zebra** browser page.

8. In section two, click the **Complete Verification** button.

2 Verify that you have linked to the service.



After you have completed Step 1, click on the button below to complete the setup.  
If successful, you will see a message confirming the connection with Zebra's OTA service.

Complete Verification

9. A confirmation displays confirming successful enrollment with Zebra's OTA service, along with your email ID.

2 Verify that you have linked to the service.



After you have completed Step 1, click on the button below to complete the setup.  
If successful, you will see a message confirming the connection with Zebra's OTA service.



Enrollment Successful

Email ID: [redacted]@[redacted].com

Revoke

Cancel enrollment. Current credentials will be removed and policies linked to the service will be affected.

Refresh

Re-enroll with Zebra OTA. Policies currently linked to the service will remain intact.

After enrollment, you can enable the Zebra firmware policy (see ["Setting the firmware policy for Zebra devices" on page 468](#)) which the Mobile@Work client receives and applies to Zebra devices (running on Android version 8.0 or supported newer versions) in Work Managed Device (Device Owner) mode and Managed Device with Work Profile (COPE) mode. When the policy is applied, the firmware is downloaded and installed on the device as scheduled in the configuration.


## Re-enrolling with Zebra OTA

You can do re-enroll with Zebra OTA service and not lose your existing configurations. For example, in the Services > Zebra page, if you see "Enrollment status cannot be verified," then you need to refresh or re-enroll the Zebra OTA service.


## Procedure

1. Go to the **Services > Zebra** page.
2. In section two, click the **Refresh** button.

2 Verify that you have linked to the service.



3. Repeat the enrollment steps in ["Enrolling in the Zebra OTA \(Over The Air\) service"](#) on page 463.
4. The Zebra OTA Credential Refresh dialog box opens. Click **Complete Verification**.




## Revoking the Zebra OTA service

If you want to discontinue using Zebra OTA service, you can remove the Zebra OTA service credentials. The Revoke action removes all Zebra OTA configurations from the existing configurations.

## Procedure

1. Go to the **Services > Zebra** page.
2. In section two, click the **Revoke** button.

2 Verify that you have linked to the service.



3. Click **Confirm**.

To enroll again, you will need to start at the beginning of the enrollment process. See ["Enrolling in the Zebra OTA \(Over The Air\) service" on page 463](#).

## Next steps

["Setting the firmware policy for Zebra devices" below](#)

## Setting the firmware policy for Zebra devices

Administrators can limit device updates to Zebra OTA (Over The Air) firmware releases using this feature. While creating the firmware policy, the administrator needs to also configure the firmware with respect to the device models. When applying the label to the policy, the policy is pushed to all the devices that meets that label criteria.

The administrator can create and apply multiple policies to a single label. The policy with the highest priority is applied in case of conflicts between multiple policies.

## Before you begin

- Activate your Zebra OTA (Over The Air) service. See ["Enrolling in the Zebra OTA \(Over The Air\) service" on page 463](#).
- Verify that affected devices are running Mobile@Work version 10.6 or supported newer versions.

## Procedure

1. Log into the Admin Portal.
2. Go to **Policies & Configs > Policies**.
3. Click **Add New > Android > Firmware policy**. The Add Android Firmware Policy dialog box opens.
4. Enter a unique name for the policy in the **Name** field.
5. Select a **Status**.
  - **Active**: to turn on this policy.
  - **Inactive**: to turn off this policy.
6. Select **Priority** then select **Higher than** or **Lower than** to select an existing policy from the drop-down list.

This option is only available if there is more than one policy.

7. Enter a **Description** (optional).

8. Select the **Enable Zebra OTA Firmware Policy** check box. The section expands.

9. See the following table for a description of the fields in the Zebra firmware policy.

Item	Description
Device Model	Lists the model of the Zebra device(s), for example, TC51, TC52.
Current Build ID	Lists the Build ID currently on the selected Zebra device.
Device Count	Lists the number of Zebra devices with the current build ID and device model.
Action	<p>Leaving the selection to <b>None</b> indicates no action will be taken.</p> <p>Clicking the <b>None</b> link opens a drop-down box to choose:</p> <ul style="list-style-type: none"> <li>a <b>Full Upgrade</b> - Zebra Android Device firmware upgrade, from selected version to the next major version (for example, from version 1.0 to 2.0.) Includes Build ID, Security Patch Date, OS Version and Description of the firmware.</li> <li>b <b>Patch Upgrade</b> - Zebra Android Device firmware upgrade for patch releases, for example, from version 1.1 to 1.2. Includes Build ID, Security Patch Date, OS Version and Description of the firmware.</li> </ul>
Target Build ID	<p>Defines the build selected by the administrator for the firmware upgrade. Core only displays the firmware that is above the Current device build; device firmware downgrade is not supported.</p> <p>Administrator can click on the link of the target build and modify the selected version.</p>
Date	Defines the date when the firmware is released.
OS Version	Operating System version of the Zebra device.
Download over Metered Network	Disabled by default. Select to require the Zebra Firmware be downloaded over a metered network.
Require Charging	Enabled by default. Require the Zebra device be plugged in and charging at the time of the firmware download / upgrade.
Require Device Idle	Enabled by default. Require the Zebra device be idle / not being used at the time of the firmware download / upgrade.
Apply Schedule for Download	<p>Selecting the check box activates the section.</p> <p>Select the day(s) of the week, the Start Time and End Time of the download. The time referenced is the local time of the Zebra device.</p>

Item	Description
Apply Schedule for Update	Selecting the check box activates the section.  Select the Start Date, End Date, Start Time and End Time of the upgrade. The time referenced is the local time of the Zebra device.

10. Click **Save**.
11. Select the policy then select **Actions > Apply to Label**.
12. Select one or more labels.
13. Click **Apply**.

### Related topics

["Setting the firmware policy for Samsung devices" on page 508](#)

### Checking the Zebra device firmware download status

You can check the status of the system update for a Zebra Android device by going to the Device details page and viewing the values in the **Zebra Build Fingerprint**, **Zebra Device Build Id**, **Zebra Device System Update**, **Zebra OTA Capable**, and the **Zebra Patch Version** fields.

### Procedure

1. In the Admin portal, go to **Devices & Users > Devices**.
2. In the Advance search field, use the **Zebra Device System Update** option as part of your search criteria.
3. The following values can be returned (listed alphabetically):

Setting	Description
Available (Android 8 or Zebra devices)	A system update is currently available for this device.
Downloading (Zebra only)	System update is currently being downloaded to the Zebra device.
Pending (Zebra devices only)	The system update policy has been applied but the update has not been downloaded or applied.
Current	The most current update is installed (applicable for Zebra Android 8.0 or supported newer versions.)
Unknown	Not supported by client or OS version.



4. Alternately, you can expand a device and in the Device Details tab, scroll to the bottom to the **Zebra Device System Update** field.

# Azure Tenant

## Overview

This section contains information describing the process for setting up Core to Microsoft Azure Tenant.

A growing number of organizations are using Microsoft's productivity apps on mobile devices, such as Microsoft 365, OneDrive, etc. These kind of deployments give device users access to their organization's resources using various devices and apps from anywhere and using only their credentials. If the credentials get compromised, any unauthorized person can also login and get complete access to the organization's data. Just focusing on who can access the organization's resources is no longer sufficient; IT administrators must know how and from which device the organization's resource is accessed from. They have to make sure that data is accessed from the devices that meets the corporate compliance policy and have these corporate policies on each and every device. Administrators should also be able to block access to unauthorized devices by defining conditional access policies.

Using Microsoft's Intune device compliance APIs allow organizations to update the device compliance status in the Microsoft Azure Active Directory (AAD.) Using conditional access from AAD, if the device is non-compliant, administrators can block the device from accessing apps. By connecting Core to the AAD, administrators will be able to use the device compliance status of Core's managed devices for conditional access to Microsoft 365 apps.

## Requirements

### Microsoft

Core customers must have a valid subscription to Microsoft Intune and assign a Microsoft Intune license to device users supported by this integration.

For Microsoft licensing for Microsoft 365 App services, please see:

<https://www.microsoft.com/en-us/microsoft-365/enterprise/compare-office-365-plans>

### Core

- Core - Administrators will need Core version 11.0.0.0 or supported newer versions.



If you do not have a link to your Core instance, contact your Ivanti Customer Success Manager.

- 
- Mobile@Work for Android (client) – version 8.0 or supported newer versions.

### Supported OS versions

- Android 8.0 or supported newer versions

Note The Following:

- The Microsoft website states:
  - Office for Android (including Outlook for Android) can be installed on tablets and phones running any of the supported versions of Android and have an ARM-based or Intel x86 processor. Starting on July 1, 2019, support will be limited to only the last four major versions of Android.
  - For more information, see <https://www.microsoft.com/en-in/microsoft-365/microsoft-365-and-office-resources?rtc=1#coreui-heading-3b8v07b>

## Unsupported OS versions

Behavior if unsupported device OS versions is used:

- Device users can complete the device registration for AAD and are able to authenticate Microsoft apps (Outlook).

## Multiple Core support

If you have multiple Cores connected to the same Azure tenant, you should not disconnect from a single Core from Azure tenant. Your options are:

- Disconnect from all Cores
- Disable compliance policy for AAD compliance integration from a specific (single) Core so that it does not upload device data to Azure



Be sure to disable the compliance policy prior to disconnecting Core.

---

## Technical support

For additional help with this feature, contact Ivanti Technical Support.

## From the Core administrator's point of view

Below lists the process from the Core administrator's perspective.

1. Administrator applies Intune licenses to device users. See ["Apply the Intune license to device users" on the next page.](#)
2. Administrator logs into Azure Portal.
3. Administrator adds Core as an Azure compliance partner. See ["Adding Core as a compliance partner" on page 477.](#)
4. Administrator creates the Conditional Access policy for the apps. See ["Creating a conditional access policy in Microsoft Endpoint Manager" on page 480.](#)

5. Administrator sets up the connection between Core and Azure. This allows client devices to report compliance status to Azure. See ["Connecting Microsoft Azure to Core" on page 486](#).
6. Administrator creates the device compliance policy in Core. See ["Creating a partner device compliance policy" on page 492](#).
7. When the device checks in, the device compliance status is sent to the Azure portal.
8. The Conditional Access policy goes into effect. Depending upon whether the device is compliant or not, the access to the app(s) is granted or denied.
9. Administrator can disconnect from Azure. See ["De-provisioning of the Azure tenant" on page 494](#).



Ivanti recommends the administrator run tests on each and every Microsoft app: Outlook, Word, Excel, Powerpoint, OneDrive, etc.

---

## From the device user's point of view

Below lists the process from the device user's perspective.

1. Device user's device is enrolled with Mobile@Work. See ["Installing Mobile@Work for iOS and Android" on page 496](#).
2. Log into the AAD account. This requires the Authenticator app to be installed on the device (see ["Required client device user action and use cases" on page 496](#).)
  - If Authenticator is available on device, device user logs into AAD account using their Microsoft credentials.
  - If Authenticator is not installed on the device, device user is guided to install the Authenticator and then log in using their Microsoft credentials.

Note The Following:

- If the device is compliant, device user can access Microsoft 365 apps.
- If the device is not compliant, an error displays stating the app cannot be opened.

## Apply the Intune license to device users

Core customers must have a valid subscription to Microsoft Intune and assign a Microsoft Intune license to device users supported by this integration.

To bulk assign licenses to existing device users, follow the instructions listed below.

### Group based assignment

<https://docs.microsoft.com/en-us/azure/active-directory/users-groups-roles/licensing-groups-assign>

## Powershell based assignment


<https://docs.microsoft.com/en-us/microsoft-365/enterprise/assign-licenses-to-user-accounts-with-microsoft-365-powershell?view=o365-worldwide>

## Adding Core as a compliance partner


This section addresses adding Core as an Azure compliance partner.

### Procedure

1. Login into: <https://endpoint.microsoft.com>.
2. In the left panel of the Microsoft Endpoint Manager admin center page, click on **Tenant Administrator**. Click on **Connectors and Tokens > Partner Compliance Management**.




3. To the right of the Search field, click **+ Add compliance partner**.



The Create Compliance Partner page displays.

4. In the Basics tab, select **MobileIron Device Compliance On-prem** from the drop-down of the Compliance partner field.



5. In the Platform field, select iOS or Android and then click **Next**.
6. Click the **Assignments** tab. In the Assign to drop-down, select the user / group of device users the compliance status is for. Make sure to select the user / group that has the license.

The screenshot shows the 'Create Compliance Partner' wizard in the 'Assignments' tab. The breadcrumb navigation at the top reads 'Home > Connectors and tokens'. The wizard has three steps: 'Basics' (checked), 'Assignments' (active), and 'Review & create'. Under the 'Assignments' tab, there are sections for 'Included groups' and 'Excluded groups'. The 'Included groups' section has a label 'Assign to' and a dropdown menu. The dropdown menu is open, showing three options: 'Selected groups' (highlighted with a blue bar), 'Selected groups', and 'All users'. Below the dropdown, it says 'Selected groups' and 'No groups selected'. There is a link '+ Select groups to include'. The 'Excluded groups' section has a blue information box with a question mark icon and the text: 'When excluding groups, you cannot mix user and device groups across include and exclude. Click here to learn more.' Below this, it says 'Selected groups' and 'No groups selected', with a link '+ Select groups to exclude'.

7. Select **Next**.
8. Click the **Create** button.

9. The new compliance partner is created and displays on the Partner compliance management page under the appropriate OS system. Once the consent is provided by the administrator on the Core Admin portal, the partner status will change from "Pending" to "Active."

[Home](#) > [Tenant admin](#) > [Connectors and tokens](#)

## Connectors and tokens | Partner compliance management (preview)

partner c  [Add compliance partner](#) [Refresh](#)

**Windows**

- Microsoft Store for Business
- Microsoft Defender ATP
- Windows enterprise certificate
- Windows Symantec certificate

**Cross platform**

- Partner device management
- Partner compliance management...
- TeamViewer connector
- Certificate connectors
- Telecom expense management
- Derived Credentials

Intune compliance evaluates partner-managed devices in your organization. Set up the connection here.

A device must comply with the highest priority partner assigned to its user. Intune is the default compliance partner.

[Find out more about connecting compliance partners to Intune.](#)

### Android

Priority	Partner	Assigned
1	MobileIron Device Compliance On-prem	Yes
Default	Intune	N/A

### iOS

Priority	Partner	Assigned
1	MobileIron Device Compliance On-prem	Yes
Default	Intune	N/A

## Creating a conditional access policy in Microsoft Endpoint Manager


This section addresses defining the conditional access policy in Microsoft Endpoint Manager.

### Procedure

1. Log in to Microsoft Endpoint Manager <https://endpoint.microsoft.com>.
2. In the Microsoft Endpoint Manager admin center page, go to **Home > Endpoint Security > Conditional Access**.




3. Click on Policies and then click **+ New Policy**.



The New conditional access policy page opens.

4. Enter the Name of the conditional access policy.



5. In Assignments, click to assign the policy to users and groups.

Home > Endpoint security > Conditional Access >

## New


Conditional access policy

Control user access based on conditional access policy to bring signals together, to make decisions, and enforce organizational policies. [Learn more](#)


**Name \***

Example: "Device compliance app policy"

**Assignments**

Users and groups ⓘ  >

Specific users included

Cloud apps or actions ⓘ  >

No cloud apps or actions selected

Conditions ⓘ >

0 conditions selected

Control user access based on users and group assignment for all users, specific groups of users, directory roles, or external guest users. [Learn more](#)

**Include** Exclude

☐ None

☐ All users

☒ Select users and groups

☐ All guest and external users ⓘ

☐ Directory roles ⓘ

☐ Users and groups

6. In the New conditional access Policy page, click **Cloud apps or actions** and then click **Select**. Search for and select the apps that are required to be protected as part of this new policy.

Home » Endpoint security » Conditional Access »

## New

Conditional access policy

Control user access based on conditional access policy to bring signals together, to make decisions, and enforce organizational policies. [Learn more](#)

Name \*

Example: 'Device compliance app policy'

Assignments

Users and groups

0 users and groups selected

Cloud apps or actions

No cloud apps or actions selected

Conditions

Control user access based on all or specific cloud apps or actions. [Learn more](#)

Select what this policy applies to

Cloud apps User actions

Include Exclude

☐ None

☐ All cloud apps

☒ Select apps

Select

None

### Select

Cloud apps

Search

☒ Office 365

☐ Azure Active Directory

☐ Azure AD Connect

☐ Azure AD Graph API

☐ Azure AD Management

☐ Azure AD Reporting

☐ Azure AD Sync

Selected items

Office 365

7. In the New conditional access policy page, click on Conditions and then click on **Device Platform**. Select the appropriate device platforms.

Home | Endpoint security | Conditional Access

## New

Conditional access policy

Control user access based on conditional access policy to bring signals together, to make decisions, and enforce organizational policies. [Learn more](#)

**Name \***

Example: 'Device compliance app policy'

**Assignments**

Users and groups ⓘ  
0 users and groups selected

Cloud apps or actions ⓘ  
No cloud apps or actions selected

**Conditions ⓘ**  
0 conditions selected

**User risk (Preview)** ⓘ  
Not configured

**Sign-in risk** ⓘ  
Not configured

**Device platforms ⓘ**  
Not configured

**Locations** ⓘ  
Not configured

**Client apps** ⓘ  
Not configured

**Device Platform**

Apply policy  
[Learn more](#)

Configure  
Yes

**Include**

☐ Any

☒ Select

☐ All

☐ All

☐ All

☐ All

☐ All

8. In the **New conditional access policy page > Access controls**, click on **Grant** and make the access and block selections.

**Grant** ✕

Control user access enforcement to block or grant access. [Learn more](#)

☐ Block access

☒ Grant access

☐ Require multi-factor authentication ⓘ

☒ Require device to be marked as compliant ⓘ

☐ Require Hybrid Azure AD joined device ⓘ

☐ Require approved client app ⓘ  
[See list of approved client apps](#)

☐ Require app protection policy (Preview) ⓘ  
[See list of policy protected client apps](#)

☐ Require password change (Preview) ⓘ

For multiple controls

☒ Require all the selected controls

☐ Require one of the selected controls

9. To enable the new policy, click **On**.




10. Click the **Create** button. The new conditional access policy displays in the Conditional Access > Policies page.

## Connecting Microsoft Azure to Core

This section covers setting up Core to report the device compliance status to Microsoft Azure.


## Procedure

1. Log in to Core and go to **Settings**.
2. In the left navigational pane, click Microsoft Azure > Device Compliance for iOS. The Device Compliance for iOS & Android page opens.



3. Enter the information for the following fields:

- **Azure Domain ID** - This is the AAD Tenant ID.
  - **Enrollment URL** - (Optional) If the device is not MDM enrolled, device users will be pointed to this URL for enrollment. When configuring, use HTTPS format. If you host a page in your organization to redirect your device users for Enrollment information, add that link here. For example: <https://enroll.enterprise.com>. If this field is left empty, the device user will be directed to a default enrollment URL / page that is hosted by Core.
  - **Remediation URL** - (Optional) If the device is not in compliance, device users will be pointed to this URL for remediation. When configuring, use HTTPS format. If you host a page in your organization to redirect your device users for Remediation information, add that link here. For example: <https://remediation.enterprise.com>. If this field is left empty, the device user will be directed to a default enrollment URL / page that is hosted by Core.
4. Click **Connect Account**. The Connect Azure Account dialog box opens. You will need to provide consent on the Microsoft Azure portal.

A screenshot of a 'Connect Azure Account' dialog box. The title bar is light blue with the text 'Connect Azure Account'. Below the title bar is a large yellow box containing two steps of instructions. Step 1 says: 'Please follow this link to provide the consent on Azure Portal. Link will open in a new tab/window. Please provide consent and close the Tab/Window and return back here.' Step 2 says: 'Click on the "I have provided the consent" below and click "Confirm". If consent is not provided, Connection to Azure will fail.' Below the yellow box is a checkbox labeled 'I have provided the consent'. At the bottom right are two buttons: 'Cancel' (light blue) and 'Confirm' (blue).


5. Click **link**. A new browser tab opens.
6. **Log in** using your Azure credentials.



Only a minimum level of rights is needed for the Azure account login.



7. A Microsoft partnership page displays asking permission to connect Azure to Core. Review the permissions and then click **Accept**.




---

**i** If you log in and the page refreshes asking that you log in again, close the browser tab / window.

---

8. Return to Core. In the Connect Azure Account dialog box, select the **I have provided the consent** check box and then click **Confirm**.


9. The Device Compliance for iOS & Android page refreshes to display Status: Enabled and two new button options.



Note The Following:

- To edit the account, click **Edit Account**.

- To disconnect the account, see ["De-provisioning of the Azure tenant" on page 494](#).
  - To view the Azure information about the device, go to the Device Details page. See ["Advanced searching" on page 79](#) for definitions.
10. To make any changes or disconnect from Azure, click on the System Settings tab. In the Microsoft Azure tile, clicking the **Device Compliance for iOS & Android** link will open that page. See also ["De-provisioning of the Azure tenant" on page 494](#).



## What the device user sees

Device users may see screens that invite the device user to take action.

- How do I access Microsoft 365 apps on my device?
- Device out of compliance? Here's how to fix

Instructions for iOS and Android devices are provided on those pages for the device user to follow.

## Azure account activity recorded in the logs

All activity of adding, editing, and deactivating an account are recorded in the Logs.

► **App** (12)

► **Policy** (10)



**Compliance Action** (0)

	Preference Config Changes	Success	misystem	2020-10-13 ...
	Preference Config Changes	Success	misystem	2020-10-13 ...
	Admin Portal Sign In	Success	miadmin	2020-10-13 ...
	Wakeup	Success	miadmin	2020-10-13 ...

## Creating a partner device compliance policy

Create a partner device compliance policy on Core and apply the desired label. The partner compliance policy reports the device compliance status to Azure for conditional access. This is done through Microsoft Intune APIs. Once the policy is pushed to the device enrolled in Core and after the first check-in of the device, the device's compliance status will be reported to Azure. Thereafter, whenever there is a change in compliance status of the device - or once a week - the status will be reported. If there is no change in the compliance status, the status is reported to Intune once a week, as required by Microsoft. To view the Azure device compliance status, go to the Device Details page under the specific device.

### Before you begin

You must have an Azure Tenant ID set up. See ["Connecting Microsoft Azure to Core" on page 486](#).

### Procedure

1. In Core, go to **Policies & Configurations > Policies**.
2. Click **Add New > Partner Device Compliance**. The Add Partner Device Compliance Policy dialog box opens.
3. Use the below form to enter your settings:

Item	Description
Name	Enter a name for the policy.
Status	Select the relevant radio button to indicate whether the policy is <b>Active</b> or <b>Inactive</b> .  Only one active policy can be applied to a device.
Priority	Specifies the priority of this policy relative to the other custom policies of the same type. This priority determines which policy is applied if more than one policy is available.

Item	Description
	<p>Select <b>Higher than</b> or <b>Lower than</b>, then select an existing policy from the drop-down list.</p> <p>For example, to give Policy A higher priority than Policy B, you would select "Higher than" and "Policy B".</p>
Description	Enter an explanation of the purpose of this policy.
Report Device Compliance Status to Azure for iOS and Android devices	<p>Selected by default. If you do not see this field, you need to set up your Azure Tenant ID first. See <a href="#">"Connecting Microsoft Azure to Core" on page 486</a>.</p> <p>If the Report Device Compliance Status to Azure for iOS and Android devices check box is enabled, and the compliance policy is applied to the client, the client will display the option in Settings under "Microsoft 365 Access." The compliance status of the device will be then reported to Azure under the following conditions:</p> <ul style="list-style-type: none"> <li>• when device is out of compliance</li> <li>• when the device is compliant</li> <li>• when the device returns to compliance after being out of compliance</li> <li>• If there is no change in the status, a report is sent once a week / every seven days.</li> </ul>

4. Click **Save**.

## Device status reporting

For the following cases, Core reports device inventory and compliance status to Azure.

- On-device compliance state change
- On-device inventory change, for example, an OS upgrade
- Once a week, Core reports compliance and inventory status to Azure

Depending on the action chosen in the compliance policy, the following device status will be sent to Azure:

TABLE 1. ACTIONS IN COMPLIANCE POLICY

Action	What Core sends to Azure
Block Email, AppConnect Apps	Non-compliant to Azure
Send Alert	Compliant to Azure

For more information, see ["Compliance actions policy violations" on page 173](#).

# De-provisioning of the Azure tenant

This section covers how to disconnect or de-provision the Azure tenant.

If multiple Cores are enabled to use the same Azure tenant, do not de-provision from one Core; instead, de-provision from all Cores. If a single Core needs to stop using Azure, you can disable the partner compliance policy for that Core only.

If the administrator performs a disconnect on Core, then Core stops reporting the device inventory and compliance status to Azure.

## Procedure


### Microsoft

1. Log in to Microsoft Azure.
2. Go to **Intune > Conditional Access**. Make sure the conditional access policy is disabled.

### Core

1. Log in to Core and go to **System Settings**.
2. In the left navigational pane, click **Microsoft Azure > Device Compliance for iOS & Android**. The Device Compliance for iOS & Android page opens.

3. Click on **Disconnect Account**.



4. In the Disconnect Azure Account dialog box, click **Confirm**.

## Retiring a device from Azure

Upon device retirement, Core reports to Azure that the device is no longer under management and is non-compliant.

Azure deletes the retired device entry after 90 days.

## Installing Mobile@Work for iOS and Android

This section addresses Mobile@Work for iOS or Android can be installed onto devices.

### Installing Mobile@Work for iOS

The administrator needs to have Mobile@Work version 12.11.0 or supported newer versions connected to Core as a Mandatory Silent App and applied to devices.

The device user needs to follow the instructions below.

#### Procedure

1. Install Mobile@Work from the Apple Store.
2. Launch the Mobile@Work client and complete the Registration.

### Installing Mobile@Work for Android

The administrator needs to have Mobile@Work 11.0.0.0 or supported newer versions connected to Core as a Mandatory Silent App and applied to devices.

The device user needs to follow the instructions below.

#### Procedure

1. Install Mobile@Work from the Google Play Store.
2. Launch the Mobile@Work client and complete the Registration.
3. Device users are to follow instructions based on the device type:
  - On non-Samsung devices, device users will be prompted to update the latest Mobile@Work as part of the Mandatory Apps Manager.
  - On Samsung devices, Mobile@Work is installed silently.

## Required client device user action and use cases

This section lists the required action that a device user needs to take in the Mobile@Work client.

### Client device user action

Device users will see a notification in the Mobile@Work app.



## Android client

### Procedure

1. On the Android device, device user taps on the Mobile@Work icon to open the app.
2. Tap Settings.
3. Tap on the Microsoft 365 Access button.
4. Device user logs in.
  - If the Authenticator app is installed on the device – device user will be redirected to the Authenticator app to enter login credentials.
  - If the Authenticator app is not installed on the device – device user will be redirected to the Google Play Store to download the app before proceeding to next steps.
5. Once logged in, the Mobile@Work Home page displays.

## iOS client

### Procedure

1. On the iOS device, device user taps on the Mobile@Work icon to open the app.
2. Tap Settings. The Settings page opens.
3. Tap the Microsoft 365 Access button.
4. Device user logs in.

If Authenticator app is installed on device	If Authenticator app is NOT installed on device
<ol style="list-style-type: none"><li>1. The device user will be redirected to the Authenticator app to enter login credentials.</li><li>2. Device user signs in with username and password and then taps Register.</li><li>3. When registration is completed, the device user is returned to the Settings page with Microsoft 365 Access checked.</li></ol>	<ol style="list-style-type: none"><li>1. The device user will be redirected to the Apple App Store to download the app.</li><li>2. Once downloaded, open Mobile@Work and tap on Settings.</li><li>3. Tap on Microsoft 365 Access.</li><li>4. Device user is redirected to the Authenticator app to enter login credentials. Device user signs in with username and password and then taps Register.</li><li>5. When registration is completed, the device user is returned to the Settings page with Microsoft 365 Access checked.</li></ol>

# Samsung Knox Settings

This chapter includes the following topics:


- ["Android Samsung browser settings" below](#)
- ["Android Samsung Knox Container Settings" on the next page](#)
- ["Activating the Samsung firmware E-FOTA license " on page 506](#)
- ["Setting the system update policy for Android devices" on page 506](#)
- ["Setting the firmware policy for Samsung devices" on page 508](#)
- ["AppConnect for Samsung Knox devices" on page 509](#)
- ["Samsung Knox support" on page 509](#)

## Android Samsung browser settings

Go to **Policies & Configs > Configurations** and click **Add New > Android > Samsung Browser** to configure web browser options for Samsung KNOX devices (API 4.x). This setting also requires the **Samsung KNOX Container** configuration.


The following settings are available:

TABLE 1. SAMSUNG BROWSER OPTIONS

Setting	Description
Name	Enter a name for the Samsung browser setting.
Description	Enter an optional description of the new Samsung browser setting.
Enable Auto Fill	Select to enable automatic completion of web forms.
Allow Cookies	Select to allow use of cookies.
Enable Javascript	Select to enable Javascript.
Allow Pop-ups	Select to allow pop-ups.
Enable Show Security Warning	Select to display browser security warnings. <div> Not supported for Samsung Galaxy S4.</div>
Enable SmartCard Authentication	This feature is not supported.

# Android Samsung Knox Container Settings

A Samsung KNOX container configuration creates a secure container on Samsung KNOX devices (API 4.0+). Apps in the KNOX container cannot communicate with apps outside of the container. Data in the secure container cannot be sent outside of the container.

 Sharing Bluetooth data from within the KNOX Workspace is controlled by a device-level setting by the user. You must enable Bluetooth in the Lockdown policy by going to **Policy & Configs > Policies > Lockdown** and selecting the Bluetooth **Enable** radio button.

To configure the Samsung KNOX Workspace mode:

1. In the Admin Portal, go to **Policies & Configs > Configurations > Add New > Android > Samsung KNOX Container**. The New Samsung KNOX Container Setting dialog box opens.
2. In the **Authentication** section, enter the password rules and behavior you want to enforce.
3. In the **App Settings** section, use the drop-downs to select settings for Browser, Exchange, and VPN in the container.

See ["Samsung Knox support" on page 509](#) for information about configuring Samsung KNOX.

Use these settings to:

- specify requirements for the container password.
- specify which apps to install in the container.
- specify restrictions.
- select the Android Samsung browser configuration to use in the container.
- select the Exchange configuration to use in the container.
- select the VPN configuration to use in the container.

 Make sure only one Samsung KNOX container setting applies to each device.

TABLE 1. SAMSUNG KNOX CONTAINER SETTINGS

Item	Description
Name	Enter brief text that identifies this group of Samsung KNOX container settings.
Description	Enter additional text that clarifies the purpose of this group of Samsung KNOX container settings.
<i>Authentication</i>	

TABLE 1. SAMSUNG KNOX CONTAINER SETTINGS (CONT.)

Item	Description
Enforce Multi-Factor Authentication	<p>Select <b>On</b> to require the device user to enter both a password and a fingerprint to access the Samsung KNOX container.</p> <p>Therefore, the device user must create a fingerprint on the device.</p> <p>The default is <b>Off</b>.</p> <p>Enforcing multi-factor authentication requires the following on the device:</p> <ul style="list-style-type: none"> <li>• Mobile@Work 9.1 for Android</li> <li>• Samsung KNOX 2.2 or supported newer versions</li> </ul> <p><b>Important:</b> After multi-factor authentication has been enforced on a device, changing this setting to <b>Off</b> has no impact on the device. Multi-factor authentication is still enforced, as designed by Samsung.</p>
Password Type	<p>Select the kind of password to require:</p> <ul style="list-style-type: none"> <li>• Simple: (Supported only on devices with Mobile@Work 8.0 and KNOX version 2.0).</li> <li>• Alphanumeric: Must include at least one alphabetic and one numeric character.</li> <li>• Complex: Must include at least one alphabetic, one numeric, and one special character (i.e., a symbol).</li> </ul>
Min Password Length	Specify a minimum length for the password. Valid range is 4-16. The default value is 6.
Min Number of Complex Characters	<p>Specify the minimum number of complex characters for the passcode. Valid range is 0-10.</p> <p>For example, to require at least two complex characters in the passcode, enter 2.</p>
Max Character Occurrences	<p>Specify a limit for the number of times a specific character can occur in the passcode.</p> <p>For example, to prevent a specific character from occurring 3 or more times, enter 2.</p>
Max Character Sequence Length	<p>Specify a limit for the number of characters that can appear in sequence in a passcode.</p> <p>For example, to prevent <i>abc</i> from occurring in a passcode, enter 2.</p>

TABLE 1. SAMSUNG KNOX CONTAINER SETTINGS (CONT.)

Item	Description
Max Numeric Sequence Length	Specify a limit for the number of numeric characters that can appear in sequence in a passcode. For example, to prevent “123” from occurring in a passcode, enter 2.
Min Character Change Length	Specify a minimum number of characters that must change when the passcode is reset. For example, to ensure that at least 2 characters change, enter 2.
Forbidden Strings	Specify any strings that must not be present in the passcode. To add a string: Click + to add an entry. Click the “Name” placeholder in the new entry. Replace “Name” with the string you want to add. For example, to prevent the passcode from including the user’s email address or last name, enter \$EMAIL\$, \$LAST_NAME. Use the tool tip to see a list of substitution variables you can use here.
Max Inactivity Timeout	Specify the idle time duration after which the lock should be enabled. If the password is set, the user is prompted for a password when unlocking the container.
Max Password Age	Specify the number of days after which the password expires.
Stored Password History	Specify the number of previous passwords that are stored and cannot be used when setting a new password.
Max Number of Failed Attempts	Specify the maximum number of failed password attempts to allow. When this number is exceeded, the KNOX container is disabled.
Password Visible Option	Select <b>Off</b> to disable the “Make password visible” option.
<i>Apps</i>	
	Select the in-house apps to be installed in the container: Click the + button. Select an app from the <b>Name</b> list. The <b>Version</b> and <b>Identifier</b> fields are filled in automatically.
<i>Restrictions</i>	
Google Play Store	The default setting is <b>Off</b> . Select the <b>On</b> radio button to enable whitelisting Google accounts.

TABLE 1. SAMSUNG KNOX CONTAINER SETTINGS (CONT.)



Item	Description
Whitelist Google Accounts	Enter the domains of accounts that can be added in the KNOX container.
Allow Camera	<p>Select to allow the device user or third-party apps to use the photo camera, video camera, and video telephony features.</p> <hr/> <p> If the camera is allowed in the KNOX container restriction policy, but not allowed via the device lockdown policy, the camera does not function in the KNOX container.</p> <hr/>
Allow Content Sharing (i.e., Share Via)	Select to allow use of the Share Via List, which is displayed in certain apps that share content with other apps.
Allow Email Account Creation	Select to allow the user to create email accounts. By default, this is unselected and end users cannot create email accounts in the KNOX container.
Allow Non-Secure Keypad	Select to allow keyboards inside the container, regardless of whether they are pre-loaded or third-party keyboards.
Allow Samsung KNOX App Store	Select to allow device users to download apps from the Samsung KNOX app store ( <a href="http://www.samsungknox.com">www.samsungknox.com</a> ).
Allow Screen Capture	Select to allow user to take a screenshot to help with troubleshooting.
Allow Remote Control	Select to allow alternate provisioning of the KNOX container.
Allow NFC	Select to allow enrollment of the device using the NFC bump.
Allow USB	Select to allow so that apps that need USB access function properly.
Install all CA certificates inside KNOX workspace	Select to deploy CA certificates inside and outside of the KNOX container to secure traffic on apps inside the Work Profile mode with a self-signed or well-known certificate. If you deselect this option, CA certificates are only installed on the outside of the container and certificates installed on the inside of the container are removed.
<i>App Settings</i>	

TABLE 1. SAMSUNG KNOX CONTAINER SETTINGS (CONT.)

Item	Description
Browser	Specifies the Android Samsung Browser configuration to use in the KNOX container. You need to create the Samsung Browser configuration separately. Otherwise, this list will be empty.
Exchange	Specifies the Exchange configuration to use in the KNOX container. You need to create the Exchange configuration separately. Otherwise, this list will be empty.
VPN	<p>Specifies the VPN configuration to use for Samsung KNOX IPsec in the container. You need to create the configuration separately. Otherwise, this list will be empty.</p> <hr/> <p> The KNOX VPN client must be installed on the device <i>before</i> you push the KNOX VPN configuration.</p> <hr/> <ol style="list-style-type: none"> <li>1. Download the KNOX VPN client from the Samsung KNOX portal: <a href="https://www.samsungknox.com/en/resources/sdk/download-knox-vpn-client">https://www.samsungknox.com/en/resources/sdk/download-knox-vpn-client</a> Go to Resources -&gt; Tools (at the bottom) -&gt; Download KNOX VPN Client. To create a user ID in the Samsung KNOX portal, an active KNOX license key (trial or product) is required.</li> <li>2. Upload the KNOX VPN client to the <b>App Catalog</b>.</li> <li>3. Create a new VPN configuration with Samsung KNOX IPsec specified as the connection type (<b>Policies &amp; Configs &gt; Configurations &gt; Add New &gt; VPN</b>).</li> <li>4. Select the new VPN configuration in the Samsung KNOX container (go to <b>Policies &amp; Configs &gt; Configurations</b>, then click <b>Add New &gt; Android &gt; Samsung KNOX Container</b>).</li> </ol>

## Supported variables

You can use the following substitution variables in the Forbidden Strings field in the Samsung KNOX Container Setting:

- \$EMAIL\$
- \$USERID\$
- \$FIRST\_NAME\$
- \$LAST\_NAME\$
- \$DISPLAY\_NAME\$
- \$USER\_CUSTOM1\$
- \$USER\_CUSTOM2\$

- \$USER\_CUSTOM3\$
- \$USER\_CUSTOM4\$
- \$NULL\$

You can also enter strings, such as:

- 12345
- Example password

## Samsung Knox Dual Encryption (DualDAR) support

Using two layers of encryption, Dual Encryption (DualDAR) secures and protects sensitive data on devices - even when they are powered off or in an unauthenticated state. This reduces the possibility of enterprise work data becoming compromised. Samsung Knox includes a FIPS 140-2 certified encryption module within the inner layer. (FIPS (Federal Information Processing Standard Publication) 140-2 is a U.S. government computer security standard used to approve cryptographic modules.)

Within the workspace, there are two storage locations available to an app: Credential Encrypted (CE) storage and Device Encrypted (DE) storage. From an apps standpoint, the Workspace storage is DualDAR-protected and works as CE storage. For apps that do not have DualDAR protection, the Knox framework prevents any apps from writing data to any storage space.

DualDAR is applicable to Knox v3 on Android 8.0 or supported newer versions.

DualDAR is applicable to Android Enterprise:

- Work Profile mode
- Managed Device with Work Profile mode
- Work Profile on Company Owned Device mode

### Procedure

1. Edit the Android Enterprise configuration. The Android enterprise (all modes) Setting dialog box opens.
2. Select the **Enable DualDAR** check box. By default, this check box is de-selected.



DualDAR is only supported on Knox 3.3+ devices. DualDAR requires a special license that can be used instead of the Samsung General policy configurator.

---

3. Enter the Knox License key into the **Samsung DualDAR Version** field.
4. Click **Save**.



The Core server will push the new Samsung DualDAR report to the device upon device registration. If enabled, the Mobile@Work for Android client will report the Samsung DualDAR version in the Device Details page > Samsung KNOX Version field. If not enabled or the device is in Device Owner mode, "unsupported" will display in the Samsung KNOX Version field.

## Samsung KNOX Workspace support for Google Play

You can enable users to use Google Play inside the Samsung KNOX Workspace. Account whitelisting is supported for Google Play Services account types. Other account types, such as accounts defined by an application such as Gmail or Facebook, are not exempted by this whitelist as they are of a different account type. Therefore, it is important to avoid whitelisting applications that can allow undesired accounts into the KNOX Workspace.



Users are only permitted to download apps that are whitelisted for the Samsung KNOX Container, but they are still able to browse the entire contents of the Google Play Store.

---

To enable Samsung KNOX Workspace support for Google Play:

1. In the Admin Portal, go to **Policies & Configs > Configurations > Add New > Android > Samsung KNOX Container** to open the New Samsung KNOX Container Settings dialog box.
2. In the **Restrictions** section, select **Google Play Store: On** radio button to enable the Google Play Store. It is set to **Off** by default.
3. Optionally, in the **Whitelist Google Accounts** field, select the **Account** check box to enter the domain URL or wildcard domain. This specifies which Google accounts or wildcard domains may be used inside the KNOX Container.
4. **Save** your changes.

## Tunnel support in the Samsung Knox Workspace

You can configure Tunnel support on Android devices. For detailed information on support and setup for Tunnel in the Samsung KNOX container, see the *Tunnel for Android Guide*.

## On-Demand Support for Samsung Knox VPN connections

You can enable On-Demand for Samsung KNOX for VPN apps that support On-Demand connections.



On-Demand is not supported for container-wide VPN apps.

---

To enable On-Demand for Samsung KNOX:

1. In the Admin Portal, go to **Policies & Configs > Configurations > Add New > VPN**. The Add VPN Setting dialog box opens.

2. In the **Connection Type** drop-down menu, select the **Samsung KNOX IPSec** check box. This is a VPN app that supports On-Demand.
3. Enter the information for the Server, Username, and Password.
4. Select the **VPN on Demand** check box.
5. Select the **Per-app VPN Yes** radio button.
6. Click **Save**.

## Activating the Samsung firmware E-FOTA license

You can activate the Samsung firmware E-FOTA license for your devices that are capable of receiving system updates over the air when they are made available. To activate the system update policy:

1. Go to **Services > Samsung**
2. The **Samsung Firmware E-FOTA License Management** page is displayed.
3. Enter the Client ID using the following components:
  - MDM ID
  - Customer ID
  - License key
4. Enter the Client Secret.
5. Enter the Corporate ID.
6. Click **Activate**.

If you choose to click deactivate an existing E-FOTA management service the firmware update policy reverts back to consumer device behavior.

## Setting the system update policy for Android devices

Administrators can limit device users from managing system updates on Android 6.0 devices (or later releases that are supported by Ivanti). When multiple policies are applied to devices, you can select a priority for applying the policy to avoid conflicts.

The System update policy applicable to:

- Work Managed Device mode
- Managed Device with Work Profile (COPE) mode
- Work Profile on Company Owned Device mode

It is not applicable to Work Profile mode.


## Before you begin

- Verify that effected devices are running Android 6.0 (or later releases that are supported by Ivanti).

## Procedure

1. Log into the Admin Portal.
2. Go to **Policies & Configs > Policies**.
3. Click **Add New > Android > Firmware policy**.
4. Enter a unique name for the policy in the **Name** field.
5. Select a **Status**.
  - **Active**: to turn on this policy.
  - **Inactive**: to turn off this policy.
6. Select **Priority** then select **Higher than** or **Lower than** to select an existing policy from the drop-down list.
7. This option is only available if there is more than one priority.
8. Enter a **Description** (optional).
9. Select the **System Update Policy for Android 6.0 or higher** check box and enable the following options:
  - **Automatic**: silently apply the policy whenever new firmware is available.
  - **Update Window**: schedule a time period to silently apply the new firmware.
  - Select a start and end time to schedule the firmware update.
  - **Postpone**: this is hard-coded by the OS and skips any OS updates for up to 30 days after which it becomes automatic.
10. (Optional) In the **Freeze Period** section, click **+Add Freeze Date**. The Start Date and End Date fields display. The Freeze Period cannot be more than 90 days and the next Freeze Period can be selected only after 60 days from the previous calendar end date.

---



The Freeze Period spans the calendar year. It cannot span over two calendar years, for example, from December to January.

---

Click in the field or on the calendar icon. A calendar displays. Click on the desired date. You must have both a start date and end date entered.
11. Click **Save**.
12. Select the policy then select **Actions > Apply to Label**.

13. Select one or more labels.
14. Click **Apply**.

## Setting the firmware policy for Samsung devices

Administrators can limit device updates to specific firmware releases using this feature. If the device model and carrier code matches what is defined in the policy, the firmware is applied to the device to which the labels are applied. If the device model and the carrier code matches what is defined in the firmware, the label is applied to the device to which the labels is applied. Administrators can create and apply multiple policies to each device. The policy with the highest priority is applied in case of conflicts between multiple policies.

### Before you begin

- Activate your Samsung license
- Verify that effected devices are running Samsung Knox version 2.7.1 and above.

### Procedure

1. Log into the Admin Portal.
2. Go to **Policies & Configs > Policies**.
3. Click **Add New > Android > Firmware policy**. The Add Android Firmware Policy dialog box opens.
4. Enter a unique name for the policy in the **Name** field.
5. Select a **Status**.
  - **Active**: to turn on this policy.
  - **Inactive**: to turn off this policy.
6. Select **Priority** then select **Higher than** or **Lower than** to select an existing policy from the drop-down list.

This option is only available if there is more than one priority.
7. Enter a **Description** (optional).
8. Select the **Enable Samsung Firmware Policy** check box.
9. Click **Save**.
10. Select the policy then select **Actions > Apply to Label**.
11. Select one or more labels.
12. Click **Apply**.

### Related topics

["Setting the firmware policy for Zebra devices" on page 468](#)

## AppConnect for Samsung Knox devices

This feature is not supported on Windows 8.1 Phone devices.

This feature is not supported on iOS devices.

In Core deployments that use AppConnect, AppConnect for Knox is automatically used on Samsung devices that meet the following requirements:

- Device has Samsung Knox 2.1
- Device is running Mobile@Work 7.0 for Android or supported newer versions.
- A Samsung General Policy with a valid Samsung KLM license is applied to a label that is also applied to the device. The Samsung license is required to take advantage of any Knox-related feature.

No changes are required to AppConnect configurations on Core.

## About AppConnect for Knox

AppConnect is a Ivanti feature that containerizes apps to protect data on the device from unauthorized access. In AppConnect for Knox, Mobile@Work uses Samsung Knox Platform features to provide an added layer of security. Specifically:

- Knox SE for Android (Security Enhancements for Android)  
AppConnect uses an *SE for Android* container for an added layer of security for the container and AppConnect-enabled apps.  
Knox TIMA Keystore
- AppConnect's Secure Apps key is protected using the TIMA keystore.

No user interface changes in Mobile@Work or Core are associated with this feature.

The Samsung Knox container, known as the Knox Workspace, is not supported with AppConnect apps. Specifically:

- The Samsung Knox container does not support any AppConnect apps running inside the Knox container.
- Core does not support using both a Knox container and AppConnect container on the same device.

## Samsung Knox support

The Samsung Knox Container enables BYOD initiatives by creating a secure container for corporate apps within each device. This container secures access to corporate apps and data.

To configure support for the Samsung Knox Container:

1. Create a **Samsung Browser** configuration.

If you do not intend to specify browser behavior in the container, you can skip this step.

See ["Android Samsung browser settings" on page 498](#).

2. Create an **Exchange** configuration for the container.

If you do not intend to specify email client behavior in the container, you can skip this step.

3. Create a **Samsung Knox Container** configuration.

The Samsung Knox Container configuration will specify the **Samsung Browser** configuration and the **Exchange** configuration you created for the container.

See ["Android Samsung Knox Container Settings" on page 499](#).

4. Create one or more labels to identify the devices that will receive the Samsung Knox Container configuration.
5. Assign the **Samsung Knox Container** configuration to the appropriate labels.

Once the configuration is present on the device, then the device begins creating the container as specified.

## Disabling the container

To manually disable the Samsung Knox container:

1. Go to **Device & Users > Devices**. Select the devices that have received the **Samsung Knox Container** configuration.
2. Click **Actions > Android Only > Disable Samsung Knox Container**.
3. Choose the container you want to disable from the **Container** list.
4. Click **Disable Samsung Knox Container**.

The container remains disabled until you manually re-enable it.

## Re-enabling the container

A Samsung Knox container can be automatically disabled by policy, such as when the device user enters the container password incorrectly too many times. You can manually disable the container using the **Disable Samsung Knox Container** action.

To manually re-enable the Samsung Knox container:

1. Go to **Device & Users > Devices**. Select the devices on which the container has been disabled.
2. Click **Actions > Android Only > Enable Samsung Knox Container**.


3. Choose the container you want to enable from the **Container** list.
4. Click **Enable Samsung Knox Container**.

# Help@Work for Android

About Help@Work for Android .....	512
How Help@Work for Android works .....	513
Help@Work for Android setup overview .....	514
Installing TeamViewer on your desktop .....	514
Requesting a TeamViewer account .....	516
Creating a TeamViewer app .....	517
Enabling Help@Work in Core .....	520
Deploying the TeamViewer QuickSupport app .....	521
Starting a remote control session .....	522

## About Help@Work for Android

Help@Work for Android with TeamViewer is an integration that enables administrators to get remote control access to supported Android devices managed by Core. VPN is not required. After initiating a remote control session from the Admin Portal using FCM, administrators can configure Android devices and troubleshoot issues without having the devices in hand. The remote control session displays on the administrator’s desktop, enabling point-and-click navigation of the device.



## Prerequisites

Help@Work for Android requires:




- access to the Ivanti Customer Portal (<http://help.mobileiron.com>) during initial setup for one-time license activation
- a company email address (belonging to an organization rather than an individual) that can be used for the TeamViewer account
- appropriate firewall rules to support FCM (see the *On-Premise Installation Guide*)
- TeamViewer 10 Desktop edition

## Supported devices

For information on supported Android devices, go to <https://www.teamviewer.com/En/help/341-How-can-I-control-my-Android-device-with-TeamViewer.aspx>.

## How Help@Work for Android works

The following diagram illustrates how Help@Work for Android with TeamViewer establishes a remote control session.




1. Administrator selects a target device in the Admin Portal Devices > Devices.
2. Core contacts the TeamViewer Server to create a remote session and retrieve a session ID.
3. Core sends a command to Mobile@Work on the device to start a remote session using the session ID. Core also launches the TeamViewer software on your desktop with the session ID.
4. The Mobile@Work app sends a message (intent message object) containing the session ID to the TeamViewer app to start a remote session.

5. TeamViewer app connects to the TeamViewer Server.
6. Administrator takes remote control of the device.

## Help@Work for Android setup overview

The following diagram illustrates the setup process for Help@Work for Android:




## Installing TeamViewer on your desktop

This section explains how to install the TeamViewer full version software on your Windows or macOS computer.

1. Download the installation package for the TeamViewer full version for Windows or macOS from the following location:

<https://www.teamviewer.com/en/download/>


2. Launch the TeamViewer installation program.



3. Select **Basic Installation**.
4. Select **Company / Commercial use**.

5. Click **Accept - next**.


When the installation is complete, the following screen displays.



## Requesting a TeamViewer account

This section explains how to get a TeamViewer account.

1. Go to <https://login.teamviewer.com/LogOn#register>.




2. Click **Sign Up**.

3. Set a TeamViewer email address and password.
4. Check the email account for a TeamViewer activation email.

It might take several minutes for this email to arrive.

5. Complete the instructions in the email to activate your account.

When the account has been activated, the following page displays:




6. Bookmark this page for future reference.


## Creating a TeamViewer app

This section explains how to create a TeamViewer app for use with your Core.

1. If you are not already logged in after TeamViewer account activation, to the TeamViewer Home page you bookmarked in "Requesting a TeamViewer account" on page 516.



2. Click the **Apps** link at the bottom of the TeamViewer Home page (displayed after account activation).



3. Click **Create app**.

**Create app** [X]

☒ Add web API

☐ Add iOS/Android SDK

Name: MICInq  
Please enter at least 5 characters.

Description: [Empty text area]

Redirect URI: [Empty text field]

Access level: User

Account management: No access

User management: No access

Session management: Create, view own and edit own sessions

Group management: No access

Connection reporting: No access

Meetings: No access


Computers & Contacts: No access

☒ I accept the [App Developer Agreement](#)

Save Cancel

4. Select **Add web API**.
5. Enter at least 5 characters to use as the app name.  
Enter at least 5 characters to use as the app name.
6. For **Redirect URI**:  
Enter it in the form of `https://<mobileironcore>/mifs/teamViewerRedirect`, where `<mobileironcore>` is the URL of your Core installation.  
  
**Note:** Using a redirect URI is required.
7. For **Access level**, select **User**.
8. For **Session management**, select **Create, view own and edit own sessions**.
9. Select **I accept the App Developer Agreement**.

10. Click **Save**.



11. Copy the displayed Client ID and Client secret.  
You will need this information for ["Enabling Help@Work in Core" below](#).
12. Click **OK**.

## Enabling Help@Work in Core

This section explains how to enable Help@Work for Android and iOS in the Core Admin Portal.

1. Log into the Admin Portal.
2. Select **Settings > System Settings**.
3. Select **Additional Products > Licensed Products**.
4. Select **Help@Work for Android and iOS 10 and higher**.
5. Accept the displayed TeamViewer license agreement and to open the Help@Work wizard.
6. Paste the **Client ID** and **Client secret** values you copied in ["Creating a TeamViewer app" on page 517](#).
7. Click **Validate**.
8. In the displayed TeamViewer page, enter your TeamViewer email and password.
9. Click **Allow** to provide Core with session management permission for your TeamViewer app.
10. Click **Sign In**.
11. Click **Activate** in the wizard to open the Customer Support login screen:
12. Enter your Ivanti Customer Support credentials.



13. Click **Login**.
14. Enter the email address you used for your TeamViewer account.
15. Click **Submit**.




Though your license is now activated, your TeamViewer software will still display a notice about trial software. Your licensing applies to the session established using the integration, so the trial notice remains in the console.

## Deploying the TeamViewer QuickSupport app

This section explains how to deploy the TeamViewer QuickSupport app to Android devices managed by Core.

1. In the Admin Portal, go to **Apps > App Catalog**.
2. Click **Quick Import**.
3. Select **Google Play**.
4. In the **Application Name** field, enter teamviewer.
5. Click **Search**.



6. Find the app in the search results.
7. Click **Import**.
8. Dismiss the displayed message and the Google Play Store Search dialog.
9. Under **Apps > App Catalog**, select the app you just imported.
10. Select **Actions > Apply To Labels**.
11. Select labels that represent the devices that should have the app added to the app catalog.

12. Click **Apply**.
13. Instruct Android device users to install the app.
14. Instruct Android device users to launch the app.


If an add-on is available for the device, the device user will be prompted to install it.

15. Instruct device users to install the add-on if prompted to do so.

## Starting a remote control session

This section explains how to start a Help@Work for Android remote control session.


1. Ask the device user to install the TeamViewer QuickSupport app.  
It should be displayed in the Core app catalog on the device.
2. In the Admin Portal, go to **Devices & Users > Devices**.
3. In the Devices page, select the entry for the device.
4. Confirm that the device is supported by Help@Work for Android. See "[Help@Work for Android](#)" on [page 512](#)
5. Select **Actions > Android Only > Remote Control**.
6. If a page requesting a session ID displays, ignore it.




7. Launch the TeamViewer 10 application when prompted.
8. If your browser has pop-up blocking enabled, then allow pop-ups for your Core URL.

9. If the TeamViewer QuickSupport app does not launch on the device, ask the device user to tap the Mobile@Work icon.

The required session ID is automatically displayed on the device.




The device user should then see a prompt similar to the one below.



10. Ask the device user to tap **Allow**.


You should now see the remote control session displayed on your screen.



## To close a remote control session from the device

To close a remote control session from the desktop:

1. Tap the TeamViewer QuickSupport app icon.




2. Tap the X in the upper right corner of the TeamViewer QuickSupport app.


## To close a remote control session from the desktop

To close a remote control session from the desktop:

1. Launch the TeamViewer desktop.



2. Sign in using your TeamViewer credentials.




3. Select the session.
4. Click **Close**.

## For more information on using remote control

For information on how to use TeamViewer remote control, see <http://downloadus1.teamviewer.com/docs/en/v10/TeamViewer10-Manual-Remote-Control-en.pdf>


## If you accidentally close the session

If you close the session window on your desktop, you can re-establish the session using the URL displayed in the Launch TeamViewer Session dialog.





This dialog displays at the beginning of each session, but might be hidden behind other windows. Copy and paste the displayed URL in a browser window to regain access to the session. Make sure the session ID displayed in the dialog matches the one displayed in the TeamViewer app on the device.





# Language Support

This section addresses the language settings for Mobile@Work.

- ["Translated versions of client apps" below](#)
- ["Selecting languages for Core messages" below](#)
- ["Setting the system default language " on the next page](#)
- ["Changing language selection from the Admin Portal" on page 531](#)

## Translated versions of client apps

Ivanti client apps (Mobile@Work) are localized to a number of languages. A device's locale setting (or selected language) determines the language that the client app appears in on the device. If the device's locale is not supported, the app appears in English (United States) by default.

Once the device communicates a language change to Core, Core sends messages to the device in the selected language, assuming the language is supported and selected in Core's **Settings > System Settings > General > Language**.


Please refer to the Core release notes for each release to see which languages and locales are supported.

## Selecting languages for Core messages

You can enable or disable languages for the messages sent from Core to devices. For example, if you have only Japanese-speaking users, you might want to remove the other message templates from the Admin Portal.

To enable or disable languages:

1. Log into the System Manager.
2. Go to **Settings > System Settings > General > Language**.




3. Move the languages you want to support from **Disabled Languages** to **Enabled Languages**.
4. Click **Save**.

## Setting the system default language

The **System Default Language** setting under **Settings > System Settings > General > Language** determines what language to use if the locale of the device cannot be determined, or the corresponding language is not supported. It also determines the default language for the self-support user portal (SSP) pages. The languages available for this setting are derived from the languages in the **Enabled Languages** list.

FIGURE 1. SETTING THE SYSTEM DEFAULT LANGUAGE FOR CORE.



## Changing language selection from the Admin Portal

Administrators can manually change the language selection for devices that do not report their locale. In this case, language selection applies only to the messages sent from Core (e.g., Event Center alerts). If the device later reports a different locale, then Core honors the reported locale.

To change the language selection for a specific device:

1. In the Admin Portal, go to **Devices & Users > Devices**.
2. Select the check box next to the device.
3. Click **Actions > Change Language**.

The **Change Language** dialog appears.

4. From the **Set Language** drop-down, select the preferred language.
5. Click **Change Language**.

# Samsung Android Kiosk Support

- ["About Samsung Android kiosk" below](#)
- ["Setting up Samsung Android kiosk mode" on the next page](#)
- ["Samsung Android kiosk policy" on page 534](#)
- ["Creating a Samsung Android kiosk configuration for multiple-app mode" on page 538](#)
- ["Enabling and Disabling Samsung Android kiosk mode" on page 539](#)
- ["An example of Samsung Android kiosk mode" on page 540](#)
- ["Information about Samsung Android kiosk mode in device details" on page 541](#)
- ["Samsung Android kiosk mode deployment notes" on page 541](#)
- ["Setting kiosk policy for Android Managed devices" on page 542](#)

## About Samsung Android kiosk

The Samsung Android kiosk feature enables you to configure supported Samsung Android devices to use only specified apps. Samsung Android kiosk mode is intended for devices that serve very specific functions for an organization.

Examples include:

- A retail store might want to use tablets to provide one or two custom apps for customers to use while shopping.
- A school might want to distribute tablets that present only appropriate apps for the user who signs in.



Though the Samsung Android kiosk feature allows multiple users to log in on a given device, it does not represent full multi-user support. It is intended as a view filter for apps. The profiles on the device do not change when different users log in. Instead, a custom list of apps displays based on the current user.

---

The kiosk feature has two modes of operation:

- single-app mode, where only one app is allowed to run on the device
- multiple-app mode, where multiple designated apps are allowed to run on the device



AppConnect apps are supported only in multiple-app mode. They are not supported in single-app mode. Multiple-app mode support with AppConnect apps is not available prior to Mobile@Work 9.1 for Android.

---

## Requirements

- Samsung Android kiosk mode is available on Samsung KNOX devices.

## Setting up Samsung Android kiosk mode

To set up a Samsung Android kiosk device for single-app mode:

- Create an Android kiosk policy.

To set up a Samsung Android kiosk device in multiple-app mode:

1. Create an Android kiosk policy.
2. Create one Android kiosk configuration for each combination of LDAP group and accessible apps.

Device users must belong to the designated LDAP groups.

The *policy* specifies the kiosk type. The *configuration* specifies which apps to display to which users in multiple-app mode.

The following instructions assume that the apps are already installed on the devices. If an app specified in the kiosk setup is not installed on the device, that app is represented by a blank icon.

## Finding the package name for an Android app

For public apps available on the Google Play store:

1. Use a web browser to locate the app in Google Play.
2. Select the app.
3. Examine the URL displayed in the browser.

FIGURE 1. FINDING THE PACKAGE NAME FOR AN ANDROID APP

[https://play.google.com/store/apps/details?id=com.mobileiron&feature=search\\_result#?t=W251bGwsMSwyLDEsImNvbS55b2JpbGVpcm9uIl0.](https://play.google.com/store/apps/details?id=com.mobileiron&feature=search_result#?t=W251bGwsMSwyLDEsImNvbS55b2JpbGVpcm9uIl0.)

The package name is included in the URL, as shown in "Finding the package name for an Android app" above.

For in-house apps:

1. Open the .apk as a zip file.
2. Use a text editor to open AndroidManifest.xml.
3. Locate the "package manifest" entry.

This entry is set to the package name.

## Samsung Android kiosk policy

The Samsung Android kiosk policy defines the behavior of a kiosk device, determining if the kiosk mode is for a single app or for multiple apps.



Samsung kiosk mode is deprecated in Android 8.1 and above. You must implement Android kiosk mode instead. See ["Setting kiosk policy for Android Managed devices" on page 542](#).

## Setting up a single-app kiosk policy

A single-app kiosk policy specifies one app for use on the designated devices. For example, if the device is intended to run an in-house app for staff in a hospital recovery room, you can define a single-app kiosk policy to prevent users from accessing other apps and device resources on that device.

### Procedure

1. Go to **Policies & Configs > Policies**
2. Click **Add New > Android > Samsung Kiosk**. The New Android Kiosk Policy dialog box opens.  
**Single App** is selected by default.
3. Use ["Samsung Android kiosk policy" above](#) to complete remaining options.
4. Click **Save**.
5. Assign the policy to the appropriate label to push it to the target devices.

## Single-app kiosk policy

See the following table for a description of the fields in a single-app kiosk policy.

TABLE 1. SAMSUNG KIOSK SINGLE APP POLICY

Item	Description
Single App package name	<p>Enter the package name for the app. The typical package name has the following format:</p> <p>com.company.app</p> <p>Important: Do not add the Mobile@Work package name here. The device must already have Mobile@Work installed and be registered with Core when it receives the kiosk policy.</p>
<i>Enable Android functions</i>	
System bar	System bars are screen areas dedicated to navigation and the display of notifications and status. Clear this option if you want to hide the system bar when the device is acting as a single-app kiosk.
Task manager	The task manager enables device users to open an app that is currently running on the device. Select this option if you want device users to be able to access the built-in task manager on the device.
Notification bar expansion	The notification bar typically displays at the top of the device. Swiping down expands the bar to the full size of the screen so that the device user can see notification details. Select this option if you want device users to be able to expand the notification bar.
Navigation bar	<p>For Android 4.0, the navigation bar is present only on devices that don't have the traditional hardware keys. It contains the Back, Home, and Recents controls. Select this option to allow device users to access the navigation bar.</p> <p>Note: For tablets, the status and navigation bars are combined into a single bar at the bottom of the screen.</p>
Status bar	<p>The status bar displays pending notifications, and status such as time, battery level, or signal strength.</p> <p>Note: For tablets, the status and navigation bars are combined into a single bar at the bottom of the screen.</p>
Share via	When "Share via" is enabled, the user can share data from apps that offer data sharing. Select this option to allow data sharing.

## Setting up a multiple-apps kiosk policy

A multiple-app kiosk policy specifies behavior for a device that will run multiple apps. You must also define at least one Android kiosk configuration to specify the permitted apps.

The multiple-app Kiosk Policy provides these additional options:

- multiple user login support
- inactivity logout interval
- administrative access to exit kiosk mode
- branding options for the kiosk launcher/desktop

To specify a multiple-app kiosk policy:

1. Go to **Policies & Configs > Policies**
2. Click **Add New > Android > Samsung Kiosk**. The New Android Kiosk Policy dialog box opens.
3. In the Android (Samsung Safe) section select the **Multiple Apps** radio button.
4. Use ["Samsung Android kiosk policy" on page 534](#) to complete the remaining options.
5. Click **Save**.
6. Assign the policy to the appropriate label to push it to the target devices.
7. Create an Android kiosk configuration to specify the apps to be used.

## Multiple-apps kiosk policy

See the following table for a description of the fields in a multi-app kiosk policy.

TABLE 2. MULTIPLE-APPS KIOSK POLICY

Item	Description
Kiosk multi-user login	Enable this option to allow different users to log in. Device users enter their Core credentials to access the kiosk. The credentials entered determine who is recorded as the current user, the apps to display, and whether that user has permission to exit kiosk mode from the device.  Note: The credentials entered do not affect the profiles installed on the device.
Inactivity logout	Select the duration of inactivity after which the user will be signed out. This option applies to multiple-user kiosks only.
Administrative access to exit Kiosk mode	If you want to specify users who have permission to disable kiosk mode from the device, specify the corresponding LDAP groups for those users.  You can choose from the LDAP groups that you specified in <b>Services &gt; LDAP</b> for each LDAP server.



TABLE 2. MULTIPLE-APPS KIOSK POLICY (CONT.)

Item	Description
<i>Branding</i>	
Background Color	Enter the hexadecimal triplet for the color you want to apply to the kiosk display background.
Banner Color	Enter the hexadecimal triplet for the color you want to apply to the banner at the top of the kiosk display.
Banner Text Color	Enter the hexadecimal triplet for the color you want to apply to the text in the banner at the top of the kiosk display.
Banner Text	Enter the text you want to display in the banner at the top of the kiosk display.
Banner Logo	<p>Click <b>Browse</b> to select a logo. The logo must be a JPEG or PNG graphic.</p> <p>Image pixel size: Image sizes vary for different devices. For most smaller screened devices, 120x120 pixels is appropriate. For most tablets or larger screens, 180x180 pixels is appropriate .</p> <p>Image file size: must be smaller than 100 KB.</p>
<i>Enable Android functions</i>	
System bar	System bars are screen areas dedicated to navigation and the display of notifications and status. Clear this option to hide the system bar.
Task manager	The task manager enables device users to open an app that is currently running on the device. Select this option if you want device users to be able to access the built-in task manager on the device.
Notification bar expansion	The notification bar typically displays at the top of the device. Swiping down expands the bar to the full size of the screen so that the device user can see notification details. Select this option if you want device users to be able to expand the notification bar.
Multi Window	Multi window is a Samsung feature that enables users to multitask by viewing two apps at the same time. Select this option to allow the multi window feature.
Navigation bar	For Android 4.0, the navigation bar is present only on devices that don't have the traditional hardware keys. It contains the Back, Home, and Recents controls. Select this option to allow device users to access the navigation bar.

TABLE 2. MULTIPLE-APPS KIOSK POLICY (CONT.)

Item	Description
	Note: For tablets, the status and navigation bars are combined into a single bar at the bottom of the screen.
Status bar	<p>The status bar displays pending notifications, and status such as time, battery level, or signal strength.</p> <p>Note: For tablets, the status and navigation bars are combined into a single bar at the bottom of the screen.</p>
Share via	When “Share via” is enabled, the user can share data from apps that offer data sharing. Select this option to allow data sharing.

## Creating a Samsung Android kiosk configuration for multiple-app mode

The Samsung Android kiosk configuration has the following functions:

- specifies the apps to be displayed for multiple-app devices
- specifies which LDAP groups, (and, therefore, which users) have access to those apps

You can apply more than one kiosk configuration to a single device. The union of the configurations determines which apps to display.



The LDAP group access specified in the configuration would effectively disable the specified apps on a single-app mode device.

**WARNING:** Do not add the Mobile@Work app to an Android Kiosk Configuration. This usage is not supported and can cause errors.

### Procedure

1. Go to **Policies & Configs > Configurations**.
2. Click **Add New > Android > Samsung Kiosk**.

The **New Android Kiosk App Setting** dialog box opens.

3. If you intend to use LDAP groups to restrict access to apps on kiosk devices, then select the LDAP groups you want to allow. You can choose from the LDAP groups that you specified in **Services > LDAP** for each LDAP server.

These users will have access to the specified apps on kiosk devices, that is, those devices that have a kiosk policy applied.

To enable all kiosk users to have access to all specified apps, do not select any LDAP groups.

The available LDAP groups are based on the last sync between Core and the LDAP server. If you made a recent change to LDAP data, it will not be reflected until the next sync (scheduled or manual).

4. Select the apps you want to make accessible for kiosk devices that receive this configuration.

Note that the name displayed is the common name for the app. The package name is the unique identifier determined by the app developer.

Do not add the Mobile@Work app to an Android Kiosk Configuration. This usage is not supported and can cause errors.

5. Click **Save**.
6. Assign the configuration to the appropriate label to push it to the target devices. One or more kiosk configurations may be applied to a single device.

## Enabling and Disabling Samsung Android kiosk mode

The first time the necessary policy and configuration are pushed to the device, a kiosk item displays in the Apps@Work screen on the device. Tap **Kiosk Mode** to initiate kiosk mode.

Afterwards, you can enable and disable Android kiosk mode from the Admin Portal. Users with assigned privileges can also disable kiosk mode on a kiosk device.

- ["Enabling Samsung Android kiosk mode from the Admin Portal " below](#)
- ["Disabling Samsung Android kiosk mode from the Admin Portal" on the next page](#)
- ["Enabling Samsung Android kiosk mode from the device" on the next page](#)
- ["Disabling Samsung Android kiosk mode from the device" on the next page](#)

## Enabling Samsung Android kiosk mode from the Admin Portal



Samsung kiosk mode is deprecated in Android 8.1 and above. You must implement Android kiosk mode instead. See ["Setting kiosk policy for Android Managed devices" on page 542](#).

1. Select the device in the **Device & Users > Devices** page.
2. Click **Actions > Android Only > Enable Kiosk**.

# Disabling Samsung Android kiosk mode from the Admin Portal

- 1. Select the device in the **Device & Users > Devices** page.
- 2. Click **Actions > Android Only > Disable Kiosk**.

# Enabling Samsung Android kiosk mode from the device

- 1. Start the Mobile@Work app.
- 2. Tap **Kiosk Mode**.

 Kiosk Mode displays only if the kiosk policy has been configured and sent to the device.

# Disabling Samsung Android kiosk mode from the device

Only users configured for administrative access in the kiosk policy can disable kiosk mode from the device. The kiosk must be configured to support multiple apps and multiple users.

## Procedure

- 1. Log in as a kiosk administrator.
- 2. Tap the **Exit Kiosk** icon at the top of the screen.

# An example of Samsung Android kiosk mode

 Samsung kiosk mode is deprecated in Android 8.1 and above. You must implement Android kiosk mode instead. See ["Setting kiosk policy for Android Managed devices"](#) on page 542.

Consider a school that wants to install the followings apps on several tablets. Although all the apps are installed on each tablet, the apps that are displayed depend on which user has logged in.

This section covers the apps and the LDAP groups that should have access to them.

TABLE 1. ANDROID KIOSK MODE EXAMPLE: LDAP GROUPS AND APPS

LDAP Groups	Apps			
	View	Update	Send 2 Parents	Send 2 Teachers
Teachers	yes	yes	yes	yes
Tutors	yes	yes		yes
Students	yes			

The following table shows one way to implement this scenario.

TABLE 2. ANDROID KIOSK MODE EXAMPLE: ANDROID CONFIGURATIONS WITH LDAP GROUPS AND APPS

Android Kiosk configurations	LDAP Groups	Apps			
		View	Update	Send 2 Parents	Send 2 Teachers
KioskTeachers	Teachers	yes	yes	yes	yes
KioskTutors	Tutors	yes	yes		yes
KioskStudents	Students	yes			

## Information about Samsung Android kiosk mode in device details

The **Device Details** pane in the Admin Portal displays the following information about kiosk mode:

- whether kiosk mode has been enabled
- the device user currently logged in on the device.

To view device details:

1. Go to **Device & Users > Devices**
2. Expand device details by clicking the caret next to the check box for the device of interest.
3. Look for the kiosk attributes in the Device Details tab.

## Samsung Android kiosk mode deployment notes

- Samsung kiosk mode is deprecated in Android 8.1 and above. You must implement Android kiosk mode instead. See ["Setting kiosk policy for Android Managed devices" on the next page.](#)
- Samsung Android kiosk mode is a viewing filter only
  - Kiosk mode is not an app blocking feature. It only restricts the viewing of apps which can be launched.
  - Apps must be installed on the device for them to launch from the kiosk.
- Distribute apps with the silent install option enabled to ease the deployment process.

- Configuring which apps to run
  - Single app mode uses the **Android Samsung Kiosk policy** on the **Policies** page.
  - Multiple app mode uses the **Android Samsung Kiosk policy** on the **Policies** page, and one or more **Android Samsung Kiosk configurations** on the **Configurations** page.
  - Apps defined in kiosk configurations with no LDAP groups selected apply to ALL kiosk users.
  - For multiple app mode, the union of all kiosk configurations applicable for a kiosk user (based on their LDAP group membership) determines the list of apps to display, and whether or not they are allowed to bypass kiosk mode.
- If the device loses its connection to Core, then kiosk mode cannot be disabled. You must do a factory reset.
- After a Samsung kiosk policy and Samsung kiosk configuration (for multi-app kiosk mode) have been pushed to a device, press the Home button on the device or restart the device. These actions avoid Android OS issues which leave the Android home screen available. Similarly, press the Home button or restart the device when kiosk mode is re-entered after having been exited due to administrator action or device maintenance.

## Setting kiosk policy for Android Managed devices

As a Space or Global admin you can set up a policy to customize the look of the Android Kiosk as well as the apps which it contains. In addition, you can select to switch to the Kiosk mode automatically. This feature is supported on devices in Device Owner mode with Android Enterprise.

1. Go to **Policies & Configs > Policies**
2. Select **Add New > Android > Android Kiosk Mode** to display the New Android Kiosk App Setting Policy dialog box.  
If a Kiosk App policy exists, the Edit Android Kiosk App Setting Policy page opens.
3. Enter a **Name** for the new policy.
4. Ensure the Status field is set to **Active**.
5. In the Kiosk Branding section, customize the kiosk with a banner, background color or background

image.

6. In the Kiosk Settings section, select the appropriate check boxes for your implementation:

Field	Definition	Enabled by default?
<b>Enable Lock Task Mode</b>	Enables the Lock Task Mode on the Android Enterprise devices connected to Android Kiosk to increase the level of security on the user devices in kiosk mode by limiting access to white listed kiosk and system apps. When a device user swipes away from an app, they will only have access to the white listed and system apps. This feature is only applicable to Android 9 devices in Device Owner (DO) mode.	Yes
System Info (Android 9+ only)	When selected, displays the date / time, connectivity, battery, and vibration mode in the status bar.	No
Keyguard (Android 9+ only)	Enables the keyguard in lock task mode.	Yes
Global Actions (Android 9+ only)	Enables the menu that is displayed when the user long-presses the power button. If this option is disabled, the user may not be able to power off the device.	Yes
Home button (Android 9+ only)	When enabled, displays the following sub-options: <ul style="list-style-type: none"> <li>Overview - Enables the Overview button and the Overview screen during lock task mode.</li> <li>Notifications - Enables notifications during lock task mode. This includes notification icons on the status bar, heads-up. notifications, and the expandable notification shade. Note: These options are only applicable for Android 9 devices.</li> </ul>	No



Field	Definition	Enabled by default?
<b>Disable Quick Settings</b>	Select so that the device will not display the system notification drop-down menu at the top of the screen. If the following settings are enabled, the settings will be display as kiosk Settings menu items. The user can customize each of the settings for use in the kiosk.	No
<b>Allow User to Access Wi-Fi Settings</b>	Select to permit the device user to access Wi-Fi settings.	No
<b>Allow User to Access Bluetooth Settings</b>	Select to permit the device user to access Bluetooth settings.	No
<b>Allow User to Access Location Settings</b>	Select to permit the device user to access Location settings.	No
<b>Enter Kiosk Mode Immediately on Registration</b>	The device will enter Kiosk mode automatically on registration.	No
<b>Kiosk Exit Pin</b>	Enter a 4 - 6 digit PIN into the field. If the Kiosk Exit PIN field is left blank, it disables the ability to exit Kiosk mode. The user will not be able to exit Kiosk mode without a Kiosk exit PIN.	No

7. In the **Choose Apps** section, optionally choose to

- allow any third -party phone or camera app by manually adding the package name (ID).

The built-in apps must be enabled in Device Owner mode. This may not be the case with all manufacturers.

- Set the apps allowed in Kiosk Mode Allowed Apps
- Add apps from the App Catalog Apps
- Add apps manually by entering a Package ID in the **Manually Add Apps with Package ID** field and click **+Add**.

After an app has been installed and is listed in the **Kiosk Mode Allowed Apps** section of the **Edit Android Kiosk App Setting Policy** page, it can be dragged up or down to change the order of appearance in the kiosk.

8. Optionally, hide an app. Select an app in the **Kiosk Mode Allowed Apps** section and click the eye icon to hide the app.

Note The Following:

- When an app is hidden it can be used by other apps, but not available to launch in the kiosk. For example, a browser can be added to the kiosk but hidden so that it can be used to open URLs from an email app.
- The Kiosk itself does not install any app. You need to install any app that you include in the kiosk using Apps@Work or other method.

# The SMS Archive Feature

- ["About the SMS & Call Log Archive feature" below](#)
- ["Monitoring the SMS & Call Log archive" on page 550](#)

## About the SMS & Call Log Archive feature

The optional SMS & Call Log Archive feature enables organizations to:

- address regulatory requirements for archiving inbound and outbound SMS messages and calls.
- encrypt SMS and call logs

## Supported devices

- The SMS archive feature is supported for Samsung Knox devices.
- The call log archive feature is supported for all Android devices.

## Setting Up the SMS & Call Log Archive feature

Complete the following steps to set up the SMS & Call Log Archive feature.

### Procedure

1. In the Admin Portal, go to **Settings > System Settings**.
2. Go to **Android > SMS & Call Log Archive**.
3. Select the type of archive:
  - Email
  - Splunk
  - Store and Forward to Internal Server
  - Do not archive to turn off the feature

4. If you select **Email**, use the following guidelines to complete the settings in **Email Configuration**:

Setting	Description
Default From Address	Enter the email address to include in the From field of the emails generated for archiving the SMS and call log messages.
Destination Email Addresses	Enter the email addresses for the archival systems to which the generated emails are being sent. Separate the email addresses with commas (,).
Host/IP Addresses	Enter the host name or IP address of each SMTP server to use for relaying the email to the SMS archival destinations. You may specify the same SMTP server that you specified when you configured Core. If you specify multiple addresses, then Core attempts to connect to each in the order specified until a successful connection is established.
TLS Enabled	Select Yes if you want to enable TLS for communication with the SMTP relay server.
STARTTLS Required	If you selected Yes for the TLS Enabled option, indicate whether the STARTTLS protocol is required for the specified SMTP servers.
Check SMTP Connection	Click this option to confirm SMTP access.

- Because most archival systems are designed for archiving email (and, therefore, parsing SMTP content), the Core SMS & Call Log Archive feature can forward SMS content and other data via email. MMS data is not captured as part of this feature.
5. If you select **Splunk Forwarder**, make sure that Splunk Forwarder is configured in System Manager (see Core System Manager Guide for details).

6. If you select **Store and Forward to Internal Server**, use the following guidelines to complete the settings in **Server Configuration**:

Setting	Description
Forward using	Select either SFTP or SCP as the protocol
Host/IP	Host name or IP address of the server (required)
Port Number	22 (default port number on the server)
Username	Username of user associated with the server
Password	Password for user specified in Username
Confirm Password	Enter the password again to confirm
Server Path	Path to the server
Check Server Connection	Click to test the connection to the specified server

7. If you requested encryption of the logs, click **Upload Encryption Certificate** to upload the certificate.
8. In **Archive Settings**, enter the number of hours that Core should wait before forwarding collected messages to their archival destinations. The default value is 4.
9. (Optional) Click **Send Now** to immediately archive all currently collected messages.
10. Click **Save**.

## Setting up encrypted SMS and call log archive encryption

Core privacy policies specify whether SMS and call log content is encrypted. These policies impact whether SMS and call log content is archived as well.

### Procedure

1. Go to **Policies & Configs > Policies**.
2. Locate and select the privacy policy intended for supporting SMS and call log archive devices.
3. Click **Edit**. The Modify Privacy Policy dialog box opens.
4. Set the **SMS Log** option to:
  - **Sync Content- Clear Text** to specify the logs are not to be encrypted
  - **Sync Content - Encrypted** to specify the logs are to be encrypted
  - **None** to stop archiving SMS messages.

5. Set the **Call Log** option to:
  - **Sync Content - Clear Text** to specify the logs are not to be encrypted
  - **Sync Content - Encrypted** to specify the logs are to be encrypted
  - **None** to stop archiving SMS messages.
6. Click **Save**.
7. If the policy has not already been applied to the SMS or call log archive devices, apply the policy to the proper labels (click **Actions** > **Apply To Label**).

## Monitoring the SMS & Call Log archive

You can monitor:

- the number of messages queued for delivery
- the health of the SMS & Call Log Archive feature using Events

## Overriding the SMS and call log delivery interval

When you set up the SMS & Call Log Archive feature, you specify the **SMS Delivery Interval**, which determines how often Core forwards the collected messages to the archival destinations.

### Procedure

1. Go to **Settings** > **System Settings** > **Android** > **SMS & Call Log Archive**.
2. Click **Send Now**.



Note that **Send Now** is enabled only if there are queued SMS or call log messages.

---

## Checking the number of delivered SMS and call log messages

Core keeps a perpetual count of the SMS and call log messages delivered to archival destinations.

### Procedure

1. Go to **Policies & Configs** > **Policies**.
2. Select and open the privacy policy that supports the SMS & Call Log Archive feature.

The details for the policy are displayed to the right of the policy list.
3. Note the number of messages listed in **Call Logs** and **SMS Logs** at the bottom of the section.

## Event Center options

The following Event Center options are available to help manage the health of the SMS Archive feature:

- SMTP Relay server is unreachable
- SMTP Relay server error
- SMS Message archive queue is full

See "[System event settings](#)" on page 388 for information on these events.

# Self-service User Portal

This section addresses device registration and its related components.

- ["Device management with the user portal" on page 559](#)
- ["Assigning user portal device management roles" on page 559](#)
- ["Requiring user portal password change" on page 567](#)
- ["Configuring help desk contact information" on page 571](#)
- ["User portal information for your users" on page 572](#)

## User portal overview

The Core Mobile@Work self-service user portal (SSP) is a platform whereby device users can manage their own devices. This section addresses the settings an administrator can create and maintain a self-service user portal.

- ["Benefits of the user portal" on the next page](#)
- ["Impacts of using the user portal" on page 554](#)
- ["User portal authentication options" on page 554](#)
- ["About registering devices in the user portal" on page 554](#)
- ["About changing device ownership in the user portal" on page 556](#)
- ["Associating a certificate with a user-provided certificate enrollment setting" on page 557](#)
- ["About generating a one-time PIN for resetting a secure apps passcode" on page 558](#)
- ["About getting Entrust derived credentials" on page 559](#)

The user portal allows your users to:

- Access Core device management actions such as wipe and lock
- View their device audit/history logs
- View details of their registered devices
- Register devices, including QR code and SMS/email options, and requesting derived credentials
- Reset the user PIN
- Change device ownership from company-owned to user-owned or the reverse
- Upload, as well as view, replace, and delete user-provided certificates

These certificates are used, for example, for S/MIME or for authenticating to internal servers.



- Generate a one-time PIN for resetting a forgotten secure apps passcode
- Designate their device as "Untrusted" in risky public spaces and redesignate them as "Trusted" when in a safe area again.

One of your decisions when you distribute Core management is whether or not to enable your users to manage one or more device actions such as locking or unlocking a device. Your users access the actions you assign them through the user portal.

To enable users to manage their devices, you assign them roles to perform any or all of the following actions:

- Wipe their device
- Lock their device
- Unlock their device

Note The Following:

- The unlock feature works with Managed Device with Work Profile (COPE) mode (Android versions 8-10.) Upon upgrade to Android 11, administrators do not have the ability to unlock the device.
- Unlock devices does not work for Work Profile devices starting from Android 7 and higher.
- Locate their device
- Retire their device
- Register their device
- Change device ownership
- Reset their secure apps passcode



The **Trust** and **unTrust** options do not require a role. Registered devices are Trusted devices by default.

---

The **Device Registration** role replaces the **MyPhone@Work Registration** role. The **MyPhone@Work Registration** role is removed. The old user portal, MyPhone@Work, was available only through Core 8.0.1.

## Benefits of the user portal

Giving users the ability to perform device management tasks:

- Distributes mobile device management
- Gives your users more control of their devices
- Adds efficiency to device registration by saving administrators' time as well as wait time that device users might experience

## Impacts of using the user portal

When you enable users to manage their own devices, you need to:

- Define which users have access to which device management actions
- Provide your users with the information they need to use the user portal
- Consider how changing device ownership from company-owned to employee-owned or vice-versa may impact:
  - The policies and configurations that are applied to the device.
  - The apps that are available through Apps@Work.
  - iBooks that are available on the device.

Devices are impacted when they check-in with Core depending on the labels to which company-owned or employee-owned devices are applied.

## User portal authentication options

You can allow device users to authenticate to the user portal with:

- A user name and password

These are the credentials a device user uses to register a device with Core.

- An identity certificate from a smart card

This authentication method is supported only on desktop computers. It is not supported with:

- Mobile devices
- Firefox

You can allow one or both of these authentication mechanisms. You make your selection in the *Core System Manager Guide*. For information about how to configure the user portal authentication options, see "Advanced: Portal authentication" in the *Core System Manager Guide*.

## About registering devices in the user portal

To allow device users to register devices in the user portal, you must assign those users the **Device Registration** role in the Admin Portal in **Devices & Users > Users**.

## Configuring the Per-User Device limit

You can configure a global per-user device limit, and optionally, custom device limits for specific LDAP Groups. Users will be limited to register only the number of devices specified in **Settings > System Settings > Users & Devices > Registration > Per-User Device Limit**.

## Per-User Device Limit

Standard device limit takes precedence over LDAP membership specific device limit to all applicable users

Per-User Device Limit (1-50, or none)

### LDAP group specific device limit

LDAP SERVER	LDAP GROUP	DEVICE LI...	ACTIONS
No records to display			

Note: Standard device limit will apply to LDAP groups that are not mentioned above.

Add+

- Device limit precedence setting
- ☒ Standard device limit takes precedence over LDAP membership specific device limit to all applicable users
  - ☐ LDAP group specific device limit takes precedence over standard device limit to all applicable users

## Procedure

To configure standard device limits and LDAP group-specific device limits, follow these steps:

1. In the first drop-down menu, select a default per-user device limit of **1-50**, or **none**.
2. If you would like to create different per-user device limits for selected LDAP groups, click **Add+**. The **Add LDAP Group Specific Device Limit** menu opens.
3. From the **Select LDAP Server** drop-down menu, select the LDAP server that contains the LDAP group you want to include.
4. From the **Select LDAP Group** drop-down menu, select the Group to include.
5. From the **Select Device Limit Per User** drop-down menu, select the per-user device limit for that LDAP group.
6. Click **Add** to save your changes.
7. The LDAP group you selected appears in the LDAP group specific device limit table, where you can copy, edit, or delete it.

## Registration PIN

Users who can register devices can also request and receive device registration PINs. To allow users to request a registration PIN, PIN-based registration must be selected in **Settings > System Settings > Users & Devices > Device Registration**. Any option that includes Registration PIN will enable device users to obtain a PIN in the user portal.

## Device Registration

Cancel

Save

☐ Enable Server Name Lookup

☐ Allow registration when password change is required

In-App Registration Requirement

☐ Password

☒ Registration PIN

☐ Password and Registration PIN

☐ Allow silent in-app registration only once. (iOS only)

Silent in-app registration time limit (minutes). (iOS only)

Within  minutes

Apple Web-based Registration Requirement

☒ Password

☐ Registration PIN

☐ Password and Registration PIN

☐ User and Registration PIN

Zero Touch and Samsung Knox Mobile Enrollment

☐ Password

☒ Registration PIN

☐ Password and Registration PIN

Managed Devices / Device Owner (afw#, QR code, NFC)

☐ Password

☒ Registration PIN

☐ Password and Registration PIN

Note the following about registration PIN:

- Even though a PIN is generated, device users will not be prompted to enter a PIN if the device platform does not require PIN for registration.

## Password and Registration PIN

Users who can register devices can also request and receive device passwords and registration PINs. To allow managed Android device users to request a password and registration PIN, the **Password and Registration PIN** radio buttons for Zero Touch and Samsung Knox Mobile Enrollment OR Managed Devices / Device Owner (afw#, QR code, NFC) fields must be selected in **Settings > System Settings > Users & Devices > Device Registration**.

## About changing device ownership in the user portal

To allow device users to change device ownership through the user portal, you must assign those users the **Change Device Ownership** role in the Admin Portal in **Devices & Users > Users**.

Users cannot assign ownership of a device during device registration in the user portal. Device ownership is automatically set to company-owned. Once users have registered their devices through the user portal, they can change the ownership of the device from company-owned to user-owned or the reverse.

## Associating a certificate with a user-provided certificate enrollment setting

When the user uploads a certificate, the user chooses a configuration to associate with the certificate. The configuration refers to a user-provided certificate enrollment setting that you configured. When you configure a user-provided certificate enrollment setting, you specify a display name. The user portal presents the display name in its list of configurations for the user to choose.

For example, you might create a user-provided certificate enrollment setting for S/MIME signing, another for S/MIME encryption, and another for server authentication. Each setting has a display name:

- S/MIME signing
- S/MIME encryption
- Authentication

When the user uploads a certificate, they see these display names as configurations, and they choose the one for the certificate. The user can upload the same certificate or different certificates for each configuration.

If you have not created at least one user-provided certificate enrollment setting, the user portal disables the option for the user to upload a certificate.

### See also:

- ["Certificate Enrollment settings" on page 333](#)

## About uploading certificates in the user portal

On a desktop computer, device users can upload their own certificates in the user portal. They can use these certificates for different purposes, such as:

- S/MIME signing
- S/MIME encryption
- Authenticating to servers, such as internal servers that support apps.

From Core release 10.8.0.0 or supported newer versions, users can upload files with multiple aliases and friendly names.



This capability is available in the user portal on desktop computers, but not on mobile devices.

---

## About generating a one-time PIN for resetting a secure apps passcode

On the AppConnect global policy, you can configure Core to allow Android device users to reset their secure apps (AppConnect) passcode when they forget it. When you have configured this option, device users who registered with Core using a user name and *password* can enter those credentials in the Secure Apps Manager to authenticate themselves and then reset their secure apps passcode. However, device users who registered with Core using a *registration PIN* need a different mechanism for authenticating themselves.

This mechanism involves these steps:

1. The user generates a one-time PIN on the user portal. The one-time PIN is valid for 24 hours.
2. In the Secure Apps Manager on a device, the user follows the instructions for resetting a forgotten secure apps passcode.
3. When prompted for his user credentials, the user enters his user name and the one-time PIN.
4. The user resets his secure apps passcode.

## Configuration requirements to allow the user portal to generate a one-time PIN

The user portal displays the option to generate a one-time PIN only if you have configured all of the following in the Admin Portal:

- The user portal role that allows the user to reset their secure apps passcode
- A license for AppConnect third-party and in-house apps, Docs@Work, or Web@Work
- An AppConnect global policy for the device that allows users to recover their AppConnect passcodes.

## Configuring the user portal to generate a one-time PIN

Configure the following in the Admin Portal to allow the user portal to generate a one-time PIN:

1. In **Devices & Users > Users**, select the user.
2. Select **Actions > Assign Roles**.
3. In the Assign Role(s) dialog box, select **Reset Secure Apps Passcode**.
4. Click **Save**.
5. In **Settings > System Settings > Additional Products > Licensed Products**, select at least one of the following:
  - **AppConnect for Third-party and In-house Apps**
  - **Docs@Work**
  - **Web@Work**
6. In **Policies & Configurations > Policies**, select the AppConnect global policy for the device.

7. In the Policy Details panel, click Edit. The Modify AppConnect Global Policy dialog box opens
8. In the **AppConnect passcode** section, select **Passcode is required for Android devices**.
9. Select **Allow Android users to recover their passcode**.
10. Click **Save**.

## About getting Entrust derived credentials

When using certificate authentication to the user portal, you can set up Core so that Android users can get their Entrust derived credentials when they get their Core registration PIN. Specifically, in the System Manager, you provide Core with the Entrust IdentityGuard Self-Service Module (SSM) URL. This URL is a deep link that points directly to the page on the Entrust self-service portal where a user can get a derived credential.

When the user requests a derived credential on the user portal, the user portal redirects the user to the URL you provided. The user interacts with the Entrust self-service portal to get a derived credential, after which the Entrust self-service portal redirects the user back to the Core user portal. The user uses the PIV-D Entrust app on a device to activate the derived credential.

For information about how to enable the user to get a derived credential on the user portal, see "Advanced: Portal authentication" in the *Core System Manager Guide*.

## Device management with the user portal

This section addresses the settings your users need to use the user portal.

- ["Logging in to the user portal with user name and password" on page 573](#)
- ["Logging in to the user portal on a desktop computer with a certificate" on page 574](#)
- ["What users see after they login" on page 574](#)
- ["Uploading certificates in the user portal on a desktop computer" on page 583](#)
- ["Viewing, replacing, and deleting certificates in the user portal" on page 583](#)
- ["When a user-provided certificate is deleted" on page 584](#)

## Assigning user portal device management roles

The Core user portal provides several device management options for your users. You give them access to these management tasks by assigning them roles in the Admin Portal.

Note The Following:

- The **Trust** and **unTrust** options do not require a role. Registered devices are Trusted devices by default.

## Procedure

1. In Admin Portal, go to **Devices & Users**.
2. Select the users receiving device management privileges.
3. From **Actions**, select **Assign Roles**.
4. Check **User Portal**.
5. Check one or more roles to assign the corresponding management actions to the selected users.
6. User roles include:
  - Wipe Device
  - Lock Device
  - Unlock Device (See following Note)
  - Locate Device
  - Retire Device
  - Register Device
  - Change Device Ownership
  - Reset PIN
  - Reset Secure Apps Passcode
  - Use Google Device Account (for Android Enterprise devices only)
  - Enable Auth Only Role

Note The Following:

- The unlock feature works with Managed Device with Work Profile (COPE) mode (Android versions 8-10.) Upon upgrade to Android 11, administrators do not have the ability to unlock the device.
- Unlock devices does not work for Work Profile devices starting from Android 7 and higher.

7. Click **Save**.

## Customizing the self-service user portal

The self-service user portal can easily be customized to reflect your company branding, messaging, and layout. The following elements can be customized:

- Company name
- Company logo
- Login page message



- Background color
- Cascading stylesheet (CSS)

## Procedure


1. From the Admin portal, navigate to **Settings > System Settings > General > Self-Service Portal**. The Self-Service Portal page opens.


System Settings   Templates \*

### Self-Service Portal

Cancel   Save

Company Name

File : Uploaded File 

Company Logo 

Note: Images in .jpg & .png format accepted. Image dimensions should not exceed 250 pixels in width and 50 pixels in height


Login Page Message

Note: This message will appear on the Self-Service portal's login page. 1000 characters maximum.

2. **Company Name:** Enter a customized company name.
3. **Company Logo:** Upload a customized company logo. Images can be JPG or PNG format, and must not exceed 250 by 50 pixels.
4. **Login Page Message:** Modify or replace the existing message that displays on the Self-Service Portal's log in page, up to 1,000 characters.

5. **Background color:**

- a. Check **Enable customized background color** and either:
- Type in a HEX color value, or
  - Open the **Background color** menu.



- b. Select or enter a value for the background color.



Based on your choice of background color, Core will automatically determine the highest-contrast text color (black or white) for that color.

- c. Click **OK** to exit the menu.

6. **CSS:** By default, your message is formatted using the default cascading style sheet (CSS) supplied by Core. You can import and edit a custom CSS file, modify the default CSS file, or leave the default.



Options are:

- **Import a CSS file:** Click to browse to a valid CSS file on your local drive. Select the file and click **Open**. The CSS file opens in the edit window. You will be asked to confirm the change.  
Invalid CSS files will not be imported, and an error message will display.
  - **Reset:** Click to reset the style sheet to the default values. You will be asked to confirm the reset.
  - **Preview:** Click to see a preview of your message as users will see it.
  - **Download:** Downloads a copy of the default CSS file to your browser's Download folder for you to keep and modify. Alternately, you can copy and paste the default CSS file into the **CSS** text window.
7. **Show View Activity in SSP Portal:** This option is enabled by default, and allows your device users to see their activity logs from the View Activity page in the SSP. To hide activity logs on the SSP, see ["Disabling device history logs in the self-service user portal" on page 586](#).
  8. When all of your changes are made, click **Save** (at the top of the page) to keep your options. A confirmation message displays.
  9. Verify the new custom portal page on Core by substituting your Core hostname and SSP user name:  
`https://<hostname>/mifs/<user>`

## User portal default stylesheet

You can copy-and-paste the following default stylesheet into the CSS text window and modify it for your needs.

```
.backgroundColor {
background:#33ccff!important;
}
.foregroundColor > p,label,div,.user-accessibility-color * {
color: #000066!important;
}
.white-bg,.light-gray {
background:#33ccff!important;
}
.pbl,.big-font,.x-form-display-field-default {
color: #000066!important;
}
.x-menu-default,.x-menu-body-default,.link-menu-item-blue span{
Background:#e6f9ff!important;
}
.btn-new-color,.x-btn-accessblue-medium {
background:#000066!important
}
.link-menu-item-blue span {
line-height: 16px;
font-size: 14px;
font-family: Helvetica,Arial,sans-serif;
margin-left: 5px;
color: #2d70b5;
}
.x-menu-item-text-default {
font: normal 11px helvetica,arial,sans-serif;
line-height: 21px;
padding-top: 1px;
color: #222;
cursor: pointer;
}
.x-btn-inner-accesswhite-medium {
font: normal 12px/24px arial,verdana,sans-serif;
color: #2d70b5;
padding: 0 10px;
max-width: 100%;
```

```

}
.x-btn-inner {
display: inline-block;
vertical-align: middle;
overflow: hidden;
text-overflow: ellipsis;
}
.x-autocontainer-innerCt {
display: table-cell;
height: 100%;
vertical-align: top;
}
.x-autocontainer-outerCt {
display: table;
}
.x-grid-empty {
padding: 10px;
color: gray;
background-color: white;
font: normal 12px helvetica,arial,sans-serif;
}
.x-grid-header-ct {
background-color: #edf0f2;
}
.x-grid-header-ct {
border: 1px solid #d0d0d0;
border-bottom-color: #a0a7ad;
background-color: #a0a7ad;
}
.x-column-header-inner {
padding: 8px 8px 6px 8px;
}
.x-leaf-column-header {
height: 100%;
}
.x-column-header-inner {
white-space: nowrap;
position: relative;
overflow: hidden;
}
.x-column-header-text {
background-repeat: no-repeat;

```

```

display: block;
overflow: hidden;
text-overflow: ellipsis;
white-space: nowrap;
}
.x-grid-item-container {
min-height: 1px;
position: relative;
}
.x-panel-default {
border-color: #d0d0d0;
padding: 0;
}

```

## Configuring an end user Terms of Service agreement


Device users must sign a Terms of Service (ToS) agreement to use Mobile@Work. You can create custom ToS agreements to align with your user languages and countries. When a user accepts the agreement, an audit email is automatically sent to the admin user identified in the **EMail ID** field.

### Procedure

1. From the Admin portal, navigate to **Settings > System Settings > Users & Devices > Registration page > End User Terms of Service**.
2. Click **Add+**. The **Add End User Terms of Service agreement** window opens.

3. In the **Language** drop-down, select the language for the agreement.

4. In the **Country / Region** drop-down, select the primary country or region.
5. In the **Type** drop-down, select the type of agreement:
  - a. **System** - Select for iOS, macOS and Android devices.
  - b. **AAD enrollment** - Select for Windows devices.
6. In the **Agreement Content** text box, enter your agreement text. The text field permits basic formatting.
7. In the **Email ID** field, enter an email address to receive confirmation emails when the users accept the agreement.
8. Click **Save**. Your new agreement appears in the End User Terms of Service table.



LANGUAGE	EUTS.TYPE	LAST MODIFIED	ACTIONS
Chinese	SYSTEM	2020-06-09 01:21:54 PM IST	<a href="#">Edit</a> <a href="#">Preview</a> <a href="#">Delete</a>
English (Default)	SYSTEM	2020-06-04 08:58:03 PM IST	<a href="#">Edit</a> <a href="#">Preview</a> <a href="#">Delete</a>

## Admin notification email

The notification email consists of a message and identifying client information: "The following user has accepted device registration terms and has attempted to enroll a new device:"


- User name
- Display name
- Email address
- Date and time
- IP address
- Platform
- Employee owned (true/false)

## Requiring user portal password change

You can require local users to change their user portal password the next time the device checks in with Core. This feature is not available for LDAP users.

To require a local user to change their user portal password:

1. In Admin Portal, go to **Devices & Users**.
2. Click **Users**.
3. Select one or more local users you want to change their user portal passwords the next time they check in with Core.
4. Click **Actions**.



5. Select **Require Password Change**.  
Core prompts you to confirm the requirement.
6. Click **Yes** to require the selected users to create a new password at the next check in.

## Limiting devices per user by LDAP group membership

You can limit the number of allowed devices per user, using LDAP group membership as the conditional limiter. You can:

- Select a global device limit of 0-50 devices per user
- Add LDAP user groups to the LDAP group-specific device limit table
- Edit LDAP user groups
- Delete LDAP user groups from the device limit table



- Set the device limit precedence setting: you can choose whether the standard device limit takes precedence over LDAP membership-specific device limits, or LDAP group-specific device limits take precedence over the standard device limit (for all applicable users)

For example, you could set a global device limit of four devices, but restrict members of specific LDAP groups to one or two devices.

## Before you begin

You must have previously configured an LDAP server to support LDAP groups before you can set per-user device limits.

## Procedure

1. From the Admin Portal, go to **Settings > System Settings > Users & Devices > Registration** page
2. In the **Per-User Device Limit** section, enter the following information:

**Per-User Device Limit**

Standard device limit takes precedence over LDAP membership specific device limit to all applicable users

Per-User Device Limit (1-50, or none)

**LDAP group specific device limit**

LDAP SERVER	LDAP GROUP	DEVICE LI...	ACTIONS
No records to display			

Note: Standard device limit will apply to LDAP groups that are not mentioned above.

[Add+](#)


Device limit precedence setting

☒ Standard device limit takes precedence over LDAP membership specific device limit to all applicable users

☐ LDAP group specific device limit takes precedence over standard device limit to all applicable users

3. **Per-User Device Limit (1-50, or none):** Set the default number of devices each user can register with Core. This is the "standard" device limit, that by default takes precedence over LDAP membership-specific device limits. You can change this priority by selecting a device limit precedence setting (step 5).

4. **LDAP group specific device limit:** This setting allows you to create LDAP group-specific device limits that vary from the default device limit you set as the per-user device limit.
  - a. From below the LDAP group table, click **Add+**. The Add LDAP Group Specific Device Limit dialog opens.



The dialog box is titled "Add LDAP Group Specific Device Limit" with a close button (X) in the top right corner. It contains three fields: "Select LDAP Server" with a dropdown menu showing "ldaps://domino-func2.qa.yourcompany.co", "Select LDAP Group" with a dropdown menu showing "AutoGroup49463574", and "Select device limit (1-50)" with a text input field containing "3" and a small up/down arrow icon to its right. At the bottom right, there are two buttons: "Cancel" and "Add".

- b. Select a configurable LDAP server from the **Select LDAP Server** drop-down.
    - c. Select a group from the **LDAP Group** drop-down.
    - d. Select the device limit (1-50) from the **Select device limit** field.
    - e. Click **Add**.
5. Select a device limit precedence setting:
  - a. Standard device limit takes precedence over LDAP membership-specific device limit for all applicable users.
  - b. LDAP group-specific device limit takes precedence over standard device limit for all applicable users.
6. Click **Add** to save your changes.

# Editing or Deleting an LDAP group-specific device limit

You can modify or delete your LDAP group-specific device limits from the LDAP group-specific device limit table.

## Procedure

1. Locate the LDAP group that you want to edit or delete in the LDAP group-specific device limit table.

Per-User Device Limit

Standard device limit takes precedence over LDAP membership specific device limit to all applicable users

Per-User Device Limit (1-50, or none)

LDAP group specific device limit

LDAP SERVER	LDAP GROUP	DEVICE LI...	ACTIONS
ldaps://domino-func2.qa.mobi...	AutoGroup2821488	4	<div>EditDelete</div>

2. Click **Edit** to re-open the Add LDAP Group Specific Device Limit dialog.
3. Click **Delete** to delete the LDAP group-specific device limit.

# Configuring help desk contact information

Core administrators with **Manage settings and services** permission can configure the help desk contact information to display in the self-service user portal.

## Procedure

1. In the Core Admin Portal, go to **Settings > General > Helpdesk**.
2. Enter the following information:

Item	Description
Name	Enter a name for the configuration.
Description	Enter a brief description for the configuration. Maximum characters allowed is 100.
Contact(s)	Enter one or more phone numbers. Valid number strings include: <ul style="list-style-type: none"><li>• Up to 24 digits for numbers beginning with the + symbol.</li><li>• Up to 22 digits for numbers without the + symbol.</li></ul> If you are entering multiple phone numbers, enter a comma-separated list.
Email(s)	Enter one or more email addresses. If you are entering multiple email addresses, enter a comma-separated list.



Either a phone number or an email address is required.

## Related topics

["Viewing the help desk contact information" on page 584.](#)

## User portal information for your users

This section presents the information that your users need to use the user portal.

The user portal displays:

- Icons for each device management action the user is allowed to perform.
- User and device information, including:
  - device type (iPod touch, 4th gen in the example)
  - status (Active, for example)
  - last check-in (example, 2 hours ago)
  - phone number
  - OS and version (to 3 digits, iOS 7.1.1, for example)
  - carrier (for example, AT&T)
  - IMEI value, if applicable
  - manufacturer
  - date the device was registered with Core
- Accounts settings and certificates uploaded by the device user.
- Helpdesk contact information configured by the Core administrator.

FIGURE 1. USER PORTAL SHOWING USER'S DEVICE INFORMATION



## Logging in to the user portal with user name and password

Device users can log in to the user portal to register and manage their devices.

## Procedure

1. Go to <https://<MobileIron server>>, where *<MobileIron server>* is the address of your MobileIron server.

Contact your administrator if you do not have this address.

2. If you are not logged in, provide your user name and password, when prompted, and then select **Sign In with Password**.

The user portal displays on your device. You can:

- click the icon for one of the available device management actions available to you.
- view your device information.

## Logging in to the user portal on a desktop computer with a certificate

If set up by the Core administrator, device users can log in to the user portal on a desktop computer using an identity certificate on a smart card.

## Procedure

1. Attach your smart card reader with your smart card to a USB port on the desktop computer.

If your computer has a built-in smart card reader, insert your smart card.

2. Go to <https://<MobileIron server>>, where *<MobileIron server>* is the address of your Core server.

Contact your administrator if you do not have this address.

3. If you are not logged in, select **Sign In with Certificate**.

A prompt appears to select your certificate

4. Select the certificate from the smart card.

5. If prompted, enter the password of the private key of the identity certificate on your smart card.

The user portal displays. You can:

- Select the icon for one of the available device management actions available to you.
- View your device information.

## What users see after they login

Depending on the user portal role enabled, device users may have a different view of the user portal.

## Welcome menu

The Welcome menu is in the top-right of the user portal. From this menu, you can perform the following actions:

- **View Activity** - See a list of all device activity. See "[Viewing device history logs from the self-service user portal](#)" on page 585.
- **Helpdesk** - Configure the help desk contact information to display in the user portal. See "[Configuring help desk contact information](#)" on page 571.
- **Settings** - View user portal settings.
- **Sign Out** - Sign out of the self-service user portal.

## If Register Device role is enabled

If the **Register Device** role is enabled, device users will be able to send an invitation from the user portal to register their device.

FIGURE 2. SEND INVITATION TO REGISTER

← Back

### Send Invitation

Provide information about your device to receive a SMS message with the registration instructions. You will also receive a registration email in your company email inbox.

Platform  
Send Platform

Device Language  
English

☒ My device has no phone number

Device ownership ☐ Company ☒ Employee

☐ Notify User By SMS

Cancel Send Invitation

Need to register another device?

Send registration instructions via SMS message and email to register a new device.

Send Invitation


On your mobile device, visit  
<https://wcc005.auto.com/app>

Or, click on the button below to generate a QR code version of this URL, that you can scan with any code scanning app.

Generate QR Code


After the invitation is sent, the device status is seen as **Pending**.

FIGURE 3. REGISTRATION PENDING FOR DEVICE



Device users can complete the registration on their mobile device at [https://<Core\\_Server\\_FQDN>/go](https://<Core_Server_FQDN>/go).


FIGURE 4. COMPLETE DEVICE REGISTRATION



After registration is completed on the mobile device, the status for the device is changed to **Active**.



FIGURE 5. ACTIVE DEVICE STATUS




## Registration instructions

On Android devices, users can follow the prompts to download Mobile@Work and complete the registration.

### If PIN-based registration is enabled

If PIN-based registration is enabled, device users will see **Request Registration PIN**. Clicking on **Request Registration PIN** allows device users to send an invitation for registration as well as generate a PIN.

FIGURE 6. REGISTRATION WITH PIN



Device users can complete the registration on their mobile device at [https://<Core\\_Server\\_FQDN>/go](https://<Core_Server_FQDN>/go). They will have to enter the PIN if prompted.

### If QR-code registration is enabled

If Quick Response (QR) code-based registration is enabled, device users will see **Generate QR Code**. Clicking on **Generate QR Code** allows device users to complete the device registration process.


When users log into the Self-service portal (SSP) home page, they can click one of two registration buttons:

- Send Invitation – Receive registration information by SMS message and email.
- Generate QR Code – Scan to be redirected to the appropriate registration page.

Users scan the QR code and are redirected to a browser to enter their pin or password:

- iOS users: Once authenticated, iReg profile installation starts, completing device registration.
- Android users: Once authenticated, the user is redirected to Google Play to download the registration app. Users open the app to complete device registration.


FIGURE 7. REGISTRATION WITH QR CODE



## If getting an Entrust derived credential is enabled

If you enabled getting an Entrust derived credential in the System Manager, device users will see **Request Derived Credential** when they receive their registration PIN for a device. Before using the registration PIN to register Mobile@Work to Core, the device user should request a derived credential.

FIGURE 8. REQUEST DERIVED CREDENTIALS



To get a derived credential:

1. Click **Request Derived Credential**.

The user is directed to the Entrust IdentityGuard self-service module URL that you specified in the System Manager.

2. The user interacts with the Entrust self-service portal to get a derived credential, including naming the derived credential.

The Entrust self-service portal provides a Derived Mobile Smart Credential Activation Password.

**Important:** The user must record this password for later use in activating the derived credential.

3. After recording the password, the user follows directions to indicate he is done.

The user is directed back to the user portal. A brief message indicates whether getting the derived credential was successful. If it was successful, **Request Derived Credential** is disabled.


The user then does the following:

1. Use Mobile@Work to register the device to Core.
2. Use the PIV-D Entrust app on the device to activate the derived credential.

### **If Change Device Ownership role is enabled**


If the **Change Device Ownership** role is enabled, device users will see the option to change the device ownership.

FIGURE 9. CHANGE DEVICE OWNERSHIP OPTION



Clicking on **Change Ownership** allows the user to change the device ownership.


FIGURE 10. CHANGE DEVICE OWNERSHIP SETTINGS



### If generating a one-time PIN for resetting the secure apps passcode is enabled

If you have configured Core as described in ["About generating a one-time PIN for resetting a secure apps passcode" on page 558](#), the device user sees the option **Reset Secure Apps Passcode**. This option is among the device management actions presented to the user for iOS and Android devices.

FIGURE 11. RESET SECURE APPS PASSCODE



### Procedure

1. Click **Reset Secure Apps Passcode**.
2. On the next screen, click the button **Reset Secure Apps Passcode**.
3. A dialog box displays containing the one-time PIN.
4. In Mobile@Work on an iOS device, or in the Secure Apps Manager on an Android device, follow the instructions for resetting a forgotten secure apps passcode.
5. When prompted for user credentials, enter the user name and the one-time PIN.
6. Follow the instructions to create a new secure apps passcode.

### Trust and Untrust options

Two device management actions that all client users can access from the SSP Devices page are the **Trust** and **UnTrust** options.

FIGURE 12. TRUST AND UNTRUST OPTIONS IN SSP



- **UnTrust:** Select this option to temporarily remove confidential information and applications from your device. Use this option before entering a location where device security may be at higher than normal risk, such as in airports.
- **Trust:** Select this option to restore confidential information and applications on your device. Use this option when no unusual device security risks exist.


## Uploading certificates in the user portal on a desktop computer

Device users can upload a certificate in the user portal on a desktop computer (available only if at least one user-provided certificate enrollment setting has been created).

### Procedure

1. Go to `https://<Core_Server_FQDN>/user`.
2. Click on the device user's name in the top right corner.
3. Click on **Settings** in the drop down menu.

FIGURE 13. USER PROVIDED CERTIFICATE MANAGEMENT



4. Click **Upload New Certificate**.
5. In the **Configuration** field, select a value from the drop-down list that corresponds with how you want to use the certificate.

NOTE: If you select a configuration for which you have already uploaded a certificate, the previously uploaded certificate will be replaced.

6. Click **Browse** next to the **User-Provided Certificate File** field.
7. Select a PKCS 12 file to upload. You can use an alias or "friendly name" for the files.
8. If a **Password** field displays, enter the password of the certificate's private key.

## Viewing, replacing, and deleting certificates in the user portal

Device users can view, replace, or delete certificates in the user portal.

### Procedure

1. Go to `https://<Core_Server_FQDN>/user`.
2. Click on the device user's name in the top right corner.

3. Click on **Settings** in the drop down menu.  
The **User-Provided Certificate Management** page appears.
4. To view information about an uploaded certificate, click the "i" next to the certificate.
5. To replace a certificate, click the edit icon next to the certificate.
6. To delete a certificate, click the delete icon next to the certificate.

## When a user-provided certificate is deleted

The user can delete the private key from the PKCS 12 file, and password if provided, from the Core file system using the user portal. A web services API is also available to delete them. Whether you want the private key and password deleted from Core depends on your security requirements.

**WARNING:** This action means that the certificate and private key in the PKCS 12 file (and password if provided) *are still available and usable on existing devices that already had received them from Core*. Because the private key was deleted from the Core file system, the certificate is **not** available to newly registered devices or to re-provisioned devices.

Because the certificate without the private key is still available on Core, you can view information about the certificate, such as its expiration date. This information can help you manage devices still using the certificate.

## Viewing the help desk contact information

If the help desk contact information is configured in the Core Admin Portal, device users can view the contact information in the self-service user portal.

For information about configuring the help desk contact information see, ["Configuring help desk contact information" on page 571](#)

### Procedure

1. Go to `https://<Core_Server_FQDN>/user`.
2. Click on the device user's name in the top right corner.



3. Click **Helpdesk** in the drop down menu.  
The **Helpdesk** page appears.

FIGURE 14. HELPDESK CONTACT INFORMATION

NAME	PHONE NUMBER(S)	E-MAIL(S)	DESCRIPTION
Support Administrator		admin@company.com	

Need to register another device?

Send registration instructions via SMS message and email to register a new device.

[Send Invitation](#)

On your mobile device, visit

## Viewing device history logs from the self-service user portal

Mobile@Work users can access their audit/device history logs from the self-service user portal. From the user portal **Welcome** drop-down menu, select **View Activity**. The device activity page opens, displaying search tools and a scrolling table of log entries. Users can access this page from their laptop and mobile devices.

### Procedure

1. From the user portal **Welcome** drop-down menu, select **View Activity**.

FIGURE 1. SELECT VIEW ACTIVITY FROM THE WELCOME MENU



2. The Device Activity page opens, displaying search tools and a scrolling table of log entries.

FIGURE 2. USER DEVICE LOGS FROM SELF-SERVICE USER PORTAL

The screenshot displays the MobileIron self-service user portal interface. At the top, the MobileIron logo is visible. Below it, there are search filters for 'User by Personalization', 'Device by Details', and 'Search by Device ID/Accession'. A 'Completed At' dropdown menu is also present. The main section is titled 'Activities' and contains a table of log entries. To the right, there is a prompt asking 'Need to register another device?' with a 'Send Invitation' button and instructions to visit a URL for registration.

ACTION	COMPLETED AT	PERFORMED ON	DETAILS	STATE
RETIRE	2020-07-22 02:50:39 PM I...	Lakshmi (Android - PDA 3)	Request for Retire on th...	Success
SEND_MESSAGE	2020-07-22 02:50:29 PM I...	Lakshmi (Android - PDA 3)	Message to notify regist...	Success
SEND_MESSAGE	2020-07-22 02:50:29 PM I...	Lakshmi (Android - PDA 3)	Message to notify regist...	Initiated
REGISTER_DEVICE	2020-07-22 02:50:27 PM I...	Lakshmi (Android - PDA 3)	Created a client profile f...	Success
USER_PORTAL_SIGN_IN	2020-07-22 02:50:07 PM I...	User Portal - 10.120.21.243	Successfully Signed In	Success
USER_PORTAL_SIGN_IN	2020-07-22 02:37:25 PM I...	User Portal - 10.121.23.66	Successfully Signed In	Success
USER_PORTAL_SIGN_IN	2020-07-22 02:34:46 PM I...	User Portal - 10.121.23.66	Successfully Signed In	Success
USER_PORTAL_SIGN_IN	2020-07-22 02:31:44 PM I...	User Portal - 10.121.23.66	Successfully Signed In	Success
USER_PORTAL_SIGN_IN	2020-07-22 02:25:08 PM I...	User Portal - 10.121.23.66	Successfully Signed In	Success
USER_PORTAL_SIGN_IN	2020-07-22 01:47:24 PM I...	User Portal - 10.121.23.66	Successfully Signed In	Success
USER_PORTAL_SIGN_IN	2020-07-22 01:28:01 PM I...	User Portal - 10.121.23.66	Successfully Signed In	Success
USER_PORTAL_SIGN_IN	2020-07-22 01:27:56 PM I...	User Portal - 157.49.168.21	Successfully Signed In	Success
USER_PORTAL_SIGN_IN	2020-07-22 12:27:11 PM IST	User Portal - 157.49.112.231	Successfully Signed In	Success
USER_PORTAL_SIGN_IN	2020-07-22 12:17:50 PM I...	User Portal - 157.49.112.231	Successfully Signed In	Success

Users can access this page from their laptop and mobile devices.

## Disabling device history logs in the self-service user portal

When users log into the Ivanti self-service portal (SSP), they can view their activity log by default. If your organization prefers not to show users the View Activity page, an administrator can disable the feature from the **Self-Service Portal** page of the Core Admin portal.

### Procedure

1. Go to **Settings > System Settings > General > Self-Service Portal** page, and scroll to the bottom.
2. Deselect **Show View Activity in SSP Portal** by clicking it.
3. Click **Save**.

### Related topics

To disable the QR code and authentication URL for device registration, see ["Disabling the QR code and registration URL" on page 77](#).

# Setting up Android Enterprise with the alternative method

The alternative method enables you to use Android Enterprise and requires sharing your user information with Google and binding your domain with Google. Each of your end users must have a Google account. However, Ivanti recommends setting up your Android Enterprise account *without* binding your domain with Google as described in ["Enabling Android Enterprise" on page 16](#).

- ["Using the alternative method to set up Android Enterprise" below](#)
- ["Managing users for Android Enterprise" on page 592](#)

## Using the alternative method to set up Android Enterprise

The alternative setup method consists of the following steps:

- ["Step 1: Sign up for Android Enterprise with Google and get the EMM Token" below](#): in the Google Admin Console.
- ["Step 2: Create a Google service account and get a JSON file" on the next page](#): in the Google Admin Console
- ["Step 3: Generate the JSON enrollment file" on page 589](#): from the Ivanti Support site
- ["Step 4: Bind Core with Android Enterprise" on page 590](#): in Core
- ["Step 5: Authorize Core to view and manage your Google users" on page 590](#): in Core
- ["Step 6: Create the Android Enterprise setting" on page 591](#): in Core

After completing these steps, continue to ["Managing users for Android Enterprise" on page 592](#).

## Step 1: Sign up for Android Enterprise with Google and get the EMM Token

Follow Google's set up instructions to sign up for Android Enterprise, and then receive the EMM Token.

Prerequisite:

- Your company has a corporate Google Account or will create one following Google's instructions

You will need:

- access to your company's Google Admin account



This step is performed on Google's website and is subject to change by Google.

---

In a web browser:

1. Go to Google's Android Enterprise sign up page:  
"Sign up for Android Enterprise"  
[https://www.google.com/a/signup/u/0/?enterprise\\_product=ANDROID\\_WORK](https://www.google.com/a/signup/u/0/?enterprise_product=ANDROID_WORK)
2. Follow Google's instructions
  - Your setup may involve several steps, depending on whether or not your domain is already a Google Apps customer.
  - You may need to verify ownership of your domain with Google.
  - You may be directed to create a service account. The instructions for the service account are in Step 2.

You will need to set up a service account, because it authenticates interactions between Core in your domain and the Google EMM Play API. Follow Google's instructions to do so here:  
"Setup with a third-party EMM provider"

<https://support.google.com/work/android/answer/6174046>

Next, generate an EMM Token.

1. Sign in to the Google Admin Console ([admin.google.com](https://admin.google.com)) with your super administrator credentials.
2. Navigate to **Security > Android enterprise Settings**. The page shows a token if one was generated in the last 30 days, or a button to generate a new token.
3. Copy this token (as text) to use in Step 3.

## Step 2: Create a Google service account and get a JSON file

In this step, you create a Google project and a service account with the EMM API enabled. You then receive a JSON file that holds a public/private key pair used to authorize interactions between apps on your domain and Google APIs.



This step is performed on Google's website and is subject to change by Google. These instructions are based on: "Setup with a third-party EMM provider"  
<https://support.google.com/work/android/answer/6174046>

---



You will need access to your company's Google Admin account

---

In a web browser:

1. Go to Google's Developers Console: <https://console.developers.google.com>
2. Log in with your Google Admin account credentials.
3. Create a new project.
4. With the dashboard showing the new project, click "Enable and manage APIs".
5. Search for "Google Play EMM API". Click the search result to select the API.

6. Click "Enable" to enable Google Play EMM API for your project.
7. Click "Credentials" in the left navigation pane.
8. Click "Create credentials" and choose "Service account key".
9. For "Service account", select "New service account" and type in a name.
10. Select "Furnish a new private key"
11. For "Key type", select JSON.
12. Click "Create".

The JSON file will be downloaded to your computer. Check that the download file is given the name as indicated in the confirmation dialog with a ".json" extension, as some browsers may use a generic filename.

Important: Store this file securely.

### Step 3: Generate the JSON enrollment file

In this step, you will use the EMM Token and JSON file you obtained from Google to receive the **ActivateAfWForCore.json** enrollment file from the Ivanti Support portal. You can use the same enrollment file to enroll or re-enroll any number of Core instances that run on your domain.

You will need:

- your company's login account for the Ivanti Support site at <https://help.mobileiron.com>.
- To get a login account, go to <https://info.mobileiron.com/LoginRequest.html>.
- administrator access to Core
- the EMM Token from Step 1
- the Google JSON file from Step 2

In Core:

1. Log in to the support portal at <https://help.mobileiron.com>.
2. Select **Android enterprise Enrollments**.
3. Click **Create New Android enterprise Enrollment**.
4. Click **Use Alternate Setup** to fill out the dialog with your EMM Token and domain URL.
5. Click **Choose file** to upload the Google JSON file from "Step 2: Create a Google service account and get a JSON file" on the previous page.
6. Click **Submit**.  
The enrollment file will be generated.
7. Click **Download Google JSON Enrollment file**.

8. The **ActivateAfWForCore.json** enrollment file is downloaded to your computer.

Some browsers may save the enrollment file with another name. Rename the file to *ActivateAfWForCore.json* before continuing.

IMPORTANT: Store the *ActivateAfWForCore.json* file securely.

You can use the same *ActivateAfWForCore.json* file to enable Android Enterprise on multiple Core instances that belong to the same domain. You can also reuse the same file if you remove Android Enterprise from Core, and then want to re-enroll it following the next steps again.

When this step completes successfully, Ivanti will be your Unified Endpoint Management (UEM) provider for Android Enterprise, and will appear in the Security > Android Enterprise settings on admin.google.com,

## Step 4: Bind Core with Android Enterprise

In this step, you upload the enrollment file from Step 3 to Core, in order to bind Core with your domain's Android Enterprise account.

You will need:

- administrator access to Core
- the *ActivateAfWForCore.json* file from Step 3

In Core:

1. Go to **Services > Google**.
2. Click **Browse** in the **Android Enterprise** section, in the box labeled "2".
3. Select the **ActivateAfWForCore.json** file you collected in Step 3.
4. Click **Connect**.
5. When the Google Account is connected successfully, box 2 will show a confirmation including **Status: Connected**.

## Step 5: Authorize Core to view and manage your Google users

In this step, you give Core permission to read Android Enterprise user IDs from existing Google user accounts. Users with Google user accounts are eligible to use Android Enterprise.

By default, Core uses the substitution value \$EMAIL\$ as the Google user account name. You can change this value to match your environment. You make this change by modifying the **User Sync Variable** field in this step. You can use any Core substitution variables along with hard-coded strings, as long as the format of the string after variable substitution has the format of a Google email address.

The following table gives some examples:

TABLE 1. EXAMPLES OF CORE SUBSTITUTION VARIABLES FOR THE GOOGLE USER ACCOUNT NAME

User Sync Variable value	Use this value when...
\$USER_CUSTOM1\$	<p>You have set \$USER_CUSTOM1\$ in your LDAP setting in the Admin Portal (at <b>Services &gt; LDAP</b>) to be the Google email address of an LDAP user.</p> <p>For example, after substitution: jdoe@someComany.com</p>
\$USERID\$@someCompany.com	<p>\$USERID\$ of an LDAP user is the same as the user name part of the user's Google email address.</p> <p>For example, after substitution: jdoe@someCompany.com</p>
\$USERID\$\$@USER_CUSTOM2\$ \$USERID\$@someSubDomain.\$USER_CUSTOM2\$	<ul style="list-style-type: none"> <li>The Google account domain has a subdomain.</li> <li>\$USERID\$ of an LDAP user is the same as the user name part of the user's Google email address.</li> <li>You have set \$USER_CUSTOM2\$ in your LDAP setting in the Admin Portal (at <b>Services &gt; LDAP</b>) to the LDAP user domain.</li> </ul> <p>For example, after substitution: jdoe@someSubDomain.someCompany.com</p>

You will need:

- Steps 1 -4 completed

In Core:

1. Go to **Services > Google**.
2. Change \$EMAIL\$ in the **User Sync Variable** field if \$EMAIL\$ is not the Google user account name that you have set up for your users.

NOTE: Changing the User Sync Variable later requires you to remove the Android Enterprise account as described in ["Removing the Android Enterprise account in Core" on page 26](#).

3. Click **Authorize** in the **Android Enterprise** section, in the box labeled "3".

When authorization completes successfully, the Android Enterprise section replaces the three steps with your account settings.

## Step 6: Create the Android Enterprise setting

In this step, you create the Android Enterprise setting in Core. This setting must be applied to each Android Enterprise-capable device in order for the device to have Android Enterprise functionality.

In the Core Admin Portal:

1. Go to **Policies & Configs > Configurations**
2. Click **Add New > Android > Android enterprise**. The New Android enterprise (all modes) Setting dialog box opens.
3. Type a name for this setting (for example, "Android Enterprise enabled")
4. Click **Save**.
5. Apply it to a label that is also applied to Android Enterprise-capable devices.  
Important Recommendation: Apply this setting to the built-in **Android** label, or a custom label that is defined using the filter "android.afw\_capable = true". For more details, refer to the Getting Started with MobileIron Core.

## Impact of Android Enterprise setting to devices that are not Android Enterprise-capable

There is no impact to devices that are not Android Enterprise-capable to have the Android Enterprise setting applied. Some devices might become Android Enterprise-capable in the future, if the carrier upgrades the device's firmware.

To view the status of the Android Enterprise setting for a device:

- Go to **Devices & Users > Devices**.
- Open the device details for the device.
- Click the **Configurations** tab.
- Look for the Android Enterprise setting. The **Status** column will show:
  - **Pending**: The device has not yet confirmed that it has received the setting.
  - **Applied**: the setting is applied.
  - **Sent**: the device is not Android Enterprise-capable; the setting is ignored by Mobile@Work.

## Managing users for Android Enterprise

User accounts in Core that are meant for Android Enterprise use are added, edited, and deleted in the same way as any Core user accounts. However, when you bind your user domain with Google, a user can register an Android Enterprise device only if the user is added as a user in your corporate Google Account.

Core automatically syncs with your corporate Google Account to enable Android Enterprise for eligible users.



## Syncing Google user accounts with Core

When you enabled Android Enterprise on Core, you provided Core with access to view your corporate Google Account including the list of users. Core has read-only access to the Google user accounts, which means Core cannot add or modify your users' Google accounts.

Therefore, Core keeps a list of which of its users have Google user accounts, thereby linking each Core user account with its corresponding Google user account.

Core automatically syncs the users in Core with the users in your corporate Google Account. However, the sync behavior depends on whether you use \$EMAIL\$ for the Google user accounts, as specified in the user sync variable.



Removing a Google account for Core causes any Android Enterprise devices to retire when they check in.

TABLE 1. CORE BEHAVIOR AND THE USER SYNC VARIABLE

Sync time	User sync variable is \$EMAIL\$	User sync variable is NOT \$EMAIL
Upon authorizing Core to view the Google Account, when first enabling Android Enterprise	Core <b>adds</b> users to its list of Google user accounts if the user is in Google's list.	No action.
On periodic intervals (approximately every 15 hours; subject to change)	Core <b>adds</b> users to and <b>deletes</b> users from its list of Google user accounts based on Google's list.	Core <b>deletes</b> users from its list of Google user accounts based on Google's list.
On demand when a new user is added in Core	No action.	No action.
On demand when a user registers a device to Core	Core <b>adds</b> the user to its list of Google user accounts if the user is in Google's list.	Core <b>adds</b> the user to its list of Google user accounts if the user is in Google's list.

**Note:** Core ignores Google user accounts that have no corresponding user account in Core.










## Adding a new user in Core

For the Core administrator, there are no differences to the process for adding new users when working with Android Enterprise. Users can be added as local users, or automatically through LDAP, as usual.

## Using Android Enterprise on a device

To be eligible to use Android Enterprise on a device, the user must have a Google account. This feature is applicable to Work Profile mode, Work managed device mode, and Managed device with work profile mode.

When the Google Play authentication token expires or changes were made (password, permissions, etc) requiring re-authorization, Mobile@Work will inform Core to reissue a new authorization token. This triggers Core to send a new authorization token to Mobile@Work in order to reauthorize Google Play. Mobile@Work can make up to 10 reauthorization requests within a 24-hour period. Upon the 11th request, an error message displays on the device, the device will be considered non-compliant and retired. In the Dashboard, a non-compliant icon displays next to the device to indicate to the administrator that there is a problem. The administrator should retire the device instance. It is recommended that all devices associated to that Google user ID to resync with Core. The device user will need to re-register with Google Play. Below is a log showing the client reauthorization requests and eventual revocation of token.

	Client requested Googl...	Success	miadmin	2019-05-09 03:56:50...
	Client	Client requested Google re-authorization token		2019-05-09 03:55:50...
	Client requested Googl...	Success	miadmin	2019-05-09 03:55:44...
	Client requested Googl...	Success	miadmin	2019-05-09 03:54:36...
	Client requested Googl...	Success	miadmin	2019-05-09 03:53:48...
	Client requested Googl...	Success	miadmin	2019-05-09 03:53:37...
	Client requested Googl...	Success	miadmin	2019-05-09 03:53:33...
	Client requested Googl...	Success	miadmin	2019-05-09 03:52:53...
	Revoking Google User ...	Success	miadmin	2019-05-09 03:36:44...

Additional information on Android Enterprise apps and related settings can be found in the *Core Apps@Work Guide*.

## **Google account method for Android Enterprise profile provisioning**

On the Google Admin Console, you can enforce EMM policies on Android devices. If enforced, when a device user adds a managed Google account to a device, such as from Settings, Mobile@Work is automatically downloaded and launched. Once the user has registered Mobile@Work with Core and the work profile is created, the account is automatically added to the work profile.

On work managed devices, after factory reset, when the device user logs in with the managed Google account, Mobile@Work is automatically downloaded and launched. Once the user has registered Mobile@Work with Core, the device is enrolled with Core as a work managed device.