



User Workspace Manager

# Server Configuration Portal Scripting Guide

Version 2018.3 SP1

## Contents

|  |    |
|--|----|
| Introduction.....  | 4  |
| Limitations .....  | 5  |
| Prerequisites.....                                       | 6  |
| Installing Windows PowerShell.....                       | 6  |
| Starting Windows PowerShell.....                         | 6  |
| Checking the Version of Windows PowerShell.....          | 6  |
| Getting Help.....  | 7  |
| Help Available in Windows PowerShell .....               | 7  |
| Listing User Workspace Manager Modules and Cmdlets ..... | 7  |
| Further Resources .....                                  | 8  |
| Getting Started with Windows PowerShell .....            | 8  |
| Windows PowerShell Core About Topics .....               | 8  |
| Product Instances.....                                   | 9  |
| Listing available Product Instances .....                | 9  |
| Loading SCP cmdlets for a Product Instance.....          | 10 |
| Viewing the currently loaded Product Instance .....      | 11 |
| Server Installation.....                                 | 12 |
| Installing Prerequisites.....                            | 12 |
| Setting Up a New Server and Database.....                | 12 |
| Upgrading an existing Server and Database.....           | 15 |
| Cloning an existing Server.....                          | 16 |
| Server Configuration Portal Cmdlets.....                 | 17 |
| Database Management.....                                 | 19 |
| View Database Connection details.....                    | 19 |
| Update Database Connection details .....                 | 19 |
| Viewing Product Database Scripts .....                   | 20 |
| Exporting Database Creation Scripts .....                | 20 |
| Exporting Database Upgrade Scripts .....                 | 21 |
| Connecting a Server to a Database .....                  | 21 |

---

---

|   |    |
|---|----|
| Server Management.....                              | 22 |
| View Server details .....                           | 22 |
| Resetting a Server to an out of box state .....     | 23 |
| Starting or Stopping a Server .....                 | 23 |
| Changing Website .....                              | 23 |
| Viewing and Fixing Variances.....                   | 24 |
| Enabling or Disabling Logging .....                 | 24 |
| Scripting Multiple/Remote Servers .....             | 25 |
| Enabling Remoting .....                             | 25 |
| Enabling CredSSP .....                              | 25 |
| Working with PowerShell Sessions .....              | 26 |
| Script Examples .....                               | 27 |
| Complete Server Configuration .....                 | 27 |
| Clone Multiple Servers from the Current Server..... | 27 |
| Return Variances from Multiple Servers .....        | 28 |

## Introduction

This guide assists Ivanti administrators to automate the configuration of Ivanti product servers, such as Management Server and Personalization Server, using Windows PowerShell.

Ivanti product servers are shipped with Server Configuration Portal (SCP) cmdlets – a set of Windows PowerShell cmdlets that allow administrators to easily automate tasks such as:

- Initial configuration of a server
- Creating databases or exporting database scripts
- Starting or stopping a server
- Checking the operation of a server
- Enabling or disable logging



### Note

When following examples in this document, enter only the part after the Windows PowerShell prompt. For example, if the example shows:

```
PS C:\> $credential = Get-Credential
```

Enter the following in the Windows PowerShell console:

```
$credential = Get-Credential
```

## Limitations

The following limitations apply to the SCP cmdlets:

A new PowerShell session is required for the configuration of each Ivanti product server. Once an Import-ApsInstanceModule operation has been invoked the PowerShell session can only be used to configure that specific server instance.

---

## Prerequisites

### Installing Windows PowerShell

SCP cmdlets require Windows PowerShell 3.0 to be installed before use. To install Windows PowerShell:

- Windows Server 2012 or 2012 R2 – Windows PowerShell is installed as standard on Windows Server 2012
- Windows Server 2008 SP2 or 2008 R2 SP1 – Download Windows Management Framework 3.0 from the Microsoft Download Center:

<http://www.microsoft.com/en-gb/download/details.aspx?id=34595>



#### Note

For more information refer to *Installing Windows PowerShell* on Microsoft MSDN:

<https://msdn.microsoft.com/en-us/powershell/scripting/setup/installing-windows-powershell>

### Starting Windows PowerShell

Use either of the following methods to launch a Windows PowerShell console:

- Click **Start**, type PowerShell. Right-click Windows PowerShell and select **Run as administrator**.
- On the taskbar, right-click Windows PowerShell and select **Run as administrator**.



#### Note

For more information refer to *Starting Windows PowerShell on Windows Server* on Microsoft MSDN:

<https://msdn.microsoft.com/powershell/scripting/setup/starting-windows-powershell>

### Checking the Version of Windows PowerShell

The `$PSVersionTable` variable should be used to confirm that either `PSVersion` is 3.0 or later, or `PSCompatibleVersions` contains 3.0.

```
PS C:\> $PSVersionTable
```

| Name                      | Value           |
|---------------------------|-----------------|
| -----                     | -----           |
| PSVersion                 | 3.0             |
| WSManStackVersion         | 3.0             |
| SerializationVersion      | 1.1.0.1         |
| CLRVersion                | 4.0.30319.18047 |
| BuildVersion              | 6.2.9200.16481  |
| PSCompatibleVersions      | {1.0, 2.0, 3.0} |
| PSRemotingProtocolVersion | 2.2             |

---

## Getting Help

### Help Available in Windows PowerShell

Help for all SCP cmdlets are available in Windows PowerShell using the Get-Help cmdlet:

```
PS C:\> Get-Help Get-ApsInstance
```

NAME

Get-ApsInstance

SYNOPSIS

Gets the product instances that are installed.

...

Examples and further details can be obtained using the -full parameter:

```
PS C:\> Get-Help Get-ApsInstance -Full
```

### Listing User Workspace Manager Modules and Cmdlets

To list modules:

```
PS C:\> Get-Module -Name AppSense* | Format-List
```

```
Name           : AppSense.ServerConfiguration.PowerShell
Path           : C:\Program Files\AppSense\Environment Manager\Personalizatio
                n Server\bin\AppSense.ServerConfiguration.PowerShell.dll
Description    :
ModuleType     : Binary
Version       : 13.0.0.0
NestedModules  : {}
ExportedFunctions :
ExportedCmdlets : {Get-ApsDatabaseVersion, Disable-ApsLogging,
                  Export-ApsDatabaseScript, Export-ApsServerImage...}
...
```

To list cmdlets:

```
PS C:\> Get-Command -Module AppSense*
```

| CommandType      | Name                     | ModuleName          |
|------------------|--------------------------|---------------------|
| Cmdlet           | Disable-ApsLogging       | AppSense....        |
| Cmdlet           | Enable-ApsLogging        | AppSense....        |
| Cmdlet           | Export-ApsDatabaseScript | AppSense....        |
| Cmdlet           | Export-ApsServerImage    | AppSense....        |
| Cmdlet           | Get-ApsCurrentInstance   | AppSense....        |
| Cmdlet           | Get-ApsDatabaseDetail    | AppSense....        |
| Cmdlet           | Get-ApsDatabaseScript    | AppSense....        |
| Cmdlet           | Get-ApsDatabaseVersion   | AppSense....        |
| Cmdlet           | Get-ApsInstance          | AppSenseI...        |
| Cmdlet           | Get-ApsPrerequisite      | AppSense....        |
| Cmdlet           | Get-ApsServerDetail      | AppSense....        |
| Cmdlet           | Get-ApsVariance          | AppSense....        |
| Cmdlet           | Import-ApsInstanceModule | AppSenseI...        |
| Cmdlet           | Initialize-ApsDatabase   | AppSense....        |
| Cmdlet           | Initialize-ApsServer     | AppSense....        |
| Cmdlet           | Install-ApsPrerequisite  | AppSense....        |
| Cmdlet           | Repair-ApsVariance       | AppSense....        |
| Cmdlet           | Reset-ApsServer          | AppSense....        |
| Cmdlet           | Set-ApsServerDatabase    | AppSense....        |
| Cmdlet           | Set-ApsWebSite           | AppSense....        |
| Cmdlet           | Start-ApsServer          | AppSense....        |
| Cmdlet           | Stop-ApsServer           | AppSense.... Cmdlet |
| Update-ApsServer |                          | AppSense....        |

## Further Resources

For more information about Windows PowerShell refer to the following resources on Microsoft MSDN and Microsoft TechNet:

### Getting Started with Windows PowerShell

<https://msdn.microsoft.com/powershell/scripting/getting-started/getting-started-with-windows-powershell>

### Windows PowerShell Core About Topics

<http://technet.microsoft.com/en-us/library/hh847856.aspx>



## Product Instances

Multiple Ivanti product servers can be installed simultaneously on a machine. For example, a machine can run up to 17 instances of the Ivanti Management Server and up to 17 instances of the Ivanti Personalization Server. Each different product server is referred to as an instance.

To allow administrators to manage different instances on the same machine a set of cmdlets known as AppSenseInstances is installed by Ivanti product servers. Use AppSenseInstances to:

- List installed product instances
- Load the appropriate set of SCP cmdlets for a product instance

Windows PowerShell automatically loads the AppSenseInstances cmdlets for you when launched – you don't need to load these cmdlets manually.



### Note

You can only load the SCP cmdlets for one product instance into each Windows PowerShell session. If you need to work with multiple instances in the same script refer to [Scripting Multiple/Remote Servers](#).

## Listing available Product Instances

Use the Get-ApsInstance cmdlet to list available product instances. For example:

```
PS C:\> Get-ApsInstance
```

```
Name                : DEFAULT
InstanceId           : 935bfcca-23d0-4a08-93e4-064025b91d7b
ProductCode         : 05aa1fcd-7e88-408d-992b-4c96926bdd22
OriginalUpgradeCode : 935bfcca-23d0-4a08-93e4-064025b91d7b
OriginalProductCode : 05aa1fcd-7e88-408d-992b-4c96926bdd22
Version             : 10.0.604.0
InstallPath         : C:\Program Files\AppSense\Management Center\Server\Bin\
CmdletPath          : C:\Program Files\AppSense\Server Configuration
                    Portal\Bin\AppSense.ServerConfiguration.PowerShell.dll;
                    C:\Program Files\AppSense\Management Center\Server\Bin\
                    AppSense.ManagementServer.PowerShell\
                    AppSense.Management
                    Server.PowerShell.dll;C:\Program Files\AppSense\Management
                    Center\Server\Bin\
                    AppSense.ManagementServer.PowerShell\
                    AppSense.ManagementServer.PowerShell.psd1
ProductName         : AppSense Management Server 10.0
IsDefault           : True
Status              : Unknown
LoggingStatus       : Undefined
DisplayName         : AppSense Management Server 10.0 (DEFAULT)
```

You can also specify filter and optional parameters including:

- -InstanceId –The GUID that uniquely identifies this product instance on the machine. For example, f321d748-8600-4cd1-beb9-8f1fc6dd0b85 would identify the above product instance.
- -Name –The full name associated with a product instance on the machine. This parameter is case insensitive. The default instance is always named “DEFAULT”.
- -ProductName – The part of the product name associated with a product instance on the machine. This parameter is case sensitive.
- -IsDefault – Returns details on the default instance.
- -AsJson – Returns the instance in json format

### Loading SCP cmdlets for a Product Instance

Before using the SCP cmdlets, you must specify the instance you want to manage using the Import-ApsInstanceModule cmdlets. For example:

```
PS C:\> Import-ApsInstanceModule -ProductName "Personalization Server" -IsDefault
```

You can specify:

- No parameters – loads the SCP cmdlets for the only product instance installed on the machine as long as there is only a single product instance installed
- -InstanceId – loads the SCP cmdlets for the specified product instance
- Any combination of -Name, -ProductName loads the SCP cmdlets for the matched product instance as long as there is only a single product instance installed that matches the specified parameters.

The following example loads the cmdlets for a Personalization Server named ‘Instance1’:

```
PS C:\> Import-ApsInstanceModule -ProductName "Personalization Server" -Name Instance1
```

---

## Viewing the currently loaded Product Instance

After loading cmdlets for a product instance you can use the `Get-ApsCurrentInstance` cmdlet to see which instance is loaded. For example:

```
PS C:\> Get-ApsCurrentInstance

Name                : DEFAULT
InstanceId           : 935bfcca-23d0-4a08-93e4-064025b91d7b
ProductCode         : 05aa1fcd-7e88-408d-992b-4c96926bdd22
OriginalUpgradeCode : 935bfcca-23d0-4a08-93e4-064025b91d7b
OriginalProductCode : 05aa1fcd-7e88-408d-992b-4c96926bdd22
Version             : 10.0.604.0
InstallPath         : C:\Program Files\AppSense\Management Center\Server\Bin\
CmdletPath          : C:\Program Files\AppSense\Server Configuration
                    Portal\Bin\AppSense.ServerConfiguration.PowerShell.dll;
                    C:\Program Files\AppSense\Management Center\Server\Bin\
                    AppSense.ManagementServer.PowerShell\AppSense.Management
                    Server.PowerShell.dll;C:\Program Files\AppSense\Management
                    Center\Server\Bin\AppSense.ManagementServer.PowerShell\
                    AppSense.ManagementServer.PowerShell.psd1
ProductName         : AppSense Management Server 10.0
IsDefault           : True
Status              : Unknown
LoggingStatus       : Undefined
DisplayName         : Get-ApsCurrentInstance
                    Management Server 10.0 (DEFAULT)
```

---

## Server Installation

Completing installation of an Ivanti product server involves:

- Installing any missing prerequisites
- Creating a database
- Initializing the product server and connecting to the database

### Installing Prerequisites

Each Ivanti product server specifies its own list of prerequisites. This list normally includes:

- IIS
- ASP.NET

To view missing prerequisites use the `Get-ApsPrerequisite` cmdlet. For example, to list missing prerequisites:

```
PS C:\> Get-ApsPrerequisite
```

Missing prerequisites can be installed using the `Install-ApsPrerequisite` cmdlet. For example, to install all missing prerequisites:

```
PS C:\> Install-ApsPrerequisite -All
```

You can also specify a subset/individual prerequisite using the `Where-Object` cmdlet. For example, to install the BITS prerequisite only:

```
PS C:\> $prerequisite = Get-ApsPrerequisite | Where-Object { $_.Name -like "*BITS*" }  
PS C:\> Install-ApsPrerequisite -Prerequisite $prerequisite
```

### Setting Up a New Server and Database

During the creation of product databases and configuration of product servers various credentials are required:

- `-ConfigurerCredential` – specifies the credentials that will be used to connect to the SQL Server during database creation and schema modification. This can be a dbo account or another user with appropriate privileges. This parameter defaults to the current logged in user
- `-ServiceCredential` – specifies the credentials that will be used by the product server to connect to the database during normal operation. This parameter is required during database creation to allow the database roles for the specified credentials to be created/mapped

Use `Get-Credential` to create a credential object for configurer/service credentials:

```
PS C:\> $credential = Get-Credential
```

```
cmdlet Get-Credential at command pipeline position 1  
Supply values for the following parameters:  
Credential
```

Use the Initialize-ApsDatabase cmdlet to create a product database:

```
PS C:\> Initialize-ApsDatabase -DatabaseServer "SQLSERVER\Instance" -DatabaseName
ManagementServer -ConfigurerCredential $configurerAccount -ServiceCredential
$serviceAccount -DatabaseConnection "NewConnection" -Verbose

VERBOSE: Starting Initialize-ApsDatabase
VERBOSE: DatabaseServer: SQLSERVER\Instance
VERBOSE: DatabaseName: ManagementServer
VERBOSE: DatabaseConnection: NewConnection
VERBOSE: Initialize-ApsDatabase: Connecting to database 'ManagementServer'
VERBOSE: Initialize-ApsDatabase: Applying latest database schema
VERBOSE: Initialize-ApsDatabase: Applying default configuration to database
'ManagementServer'
VERBOSE: Initialize-ApsDatabase: Creating database login 'serviceAccount' of type
'Impersonate' for web directory and Windows services access
VERBOSE: Initialize-ApsDatabase: Setting web directories to use new database login
VERBOSE: Completed Initialize-ApsDatabase
```



**Note** If the `-ConfigurerCredential` is not supplied then `Initialize-ApsDatabase` cmdlet will default to using Windows Impersonation. On completion the `DatabaseConnection.xml` will not contain the configurer credentials. This can be fixed within the Server Configuration Portal.

Once a database has been created, then the server can be created using the `Initialize-ApsServer` cmdlet. The `DatabaseServer`, `DatabaseName`, `ConfigurerCredential`, and `ServiceAccount` parameters can all be specified again, or instead, the `DatabaseConnection` parameter can be used by specifying the name of the `DatabaseConnection` created during the `Initialize-ApsDatabase` step.

```
PS C:\> Initialize-ApsServer -DatabaseConnection "NewConnection" -Verbose

VERBOSE: Starting Initialize-ApsServer
VERBOSE: WebsiteName: Management
VERBOSE: WebsiteAuthentication: Windows
VERBOSE: DatabaseServer: SQLSERVER\Instance
VERBOSE: DatabaseName: ManagementServer
VERBOSE: DatabaseConnection: NewConnection
VERBOSE: ConnectionString:
VERBOSE: InstallMode:
VERBOSE: Initialize-ApsServer: Loading recommendations
VERBOSE: Initialize-ApsServer: Creating application pools
VERBOSE: Initialize-ApsServer: Applying application pool defaults
VERBOSE: Initialize-ApsServer: Creating and initializing IIS directories
VERBOSE: Initialize-ApsServer: Applying web directory defaults
VERBOSE: Initialize-ApsServer: Creating database login 'serviceAccount' of type
'Impersonate' for web directory and Windows services access
VERBOSE: Initialize-ApsServer: Setting web directories to use new database login
VERBOSE: Initialize-ApsServer: Registering and starting Windows services
VERBOSE: Initialize-ApsServer: Applying service defaults
VERBOSE: Initialize-ApsServer: Setup complete
VERBOSE: Completed Initialize-ApsServer
```

In addition to the parameters specified above, Initialize-ApsServer can be supplied with the following parameters:

- **WebSiteName** – the name of the website this server will be placed on. The website must already exist.
- **WebsiteAuthentication** – comma separated list of authentication types to be applied to the server. A website will only apply authentication types configured as allowable.
- **InstallModes**
- **ConnectionString** – the additional parameters to add to the default connection string. If you have configured SQL AlwaysOn with Availability Group Multi-Subnet Failovers, you must handle the MultiSubnetFailover value in the database connection string. See the example below.
- **HostName** – the custom IIS Website binding host name
- **HostPort** – the custom IIS Website binding port number
- **Port** – the local IIS Website binding port number

The following example sets MultiSubnetFailover=true on the connection string:

```
$db = "ms0425"
$sql = "gw-sql\mssql12012"
import-apsinstancemodule
$p="password"|convertto-securestring -asplaintext -force;
$c=new-object system.management.automation.pscredential("amc_service",$p)
$p2="password"|convertto-securestring -asplaintext -force;
$c2=new-object system.management.automation.pscredential("DEVELOPMENT\amc_admin",$p2)
initialize-apsdatabase -databaseconnection db1 -databaseserver $sql -databasename $db -
servicecredential $c -servicesqlauthentication -configurercredential $c2 -connectionstring
'MultiSubnetFailover=True;'
initialize-apsserver -databaseconnection db1
```

---

## Upgrading an existing Server and Database

To upgrade a product instance:

- Install the product server update – install the appropriate MSI or MSP file from the product server release, available from the Ivanti community website (<https://community.ivanti.com/community/appsense>).
- Upgrade the database – Use Initialize-ApsDatabase with the same parameters to upgrade the database to the version needed for the installed product server

Use Get-Credential to create a credential object for configure or service credentials:

```
PS C:\> $credential = Get-Credential
```

```
cmdlet Get-Credential at command pipeline position 1
Supply values for the following parameters:
Credential
```

If upgrading from 8.x, pass in the same parameters used to initially create the database.

```
PS C:\> Initialize-ApsDatabase -DatabaseServer "SQLSERVER\Instance" -DatabaseName
ManagementServer -ConfigurerCredential $configurerAccount -ServiceCredential
$serviceAccount -Verbose
VERBOSE: Starting Initialize-ApsDatabase
VERBOSE: DatabaseServer: SQLSERVER\Instance
VERBOSE: DatabaseName: ManagementServer
```

Database Upgrade

Database 'ManagementServer' is out of date and requires upgrading. Clients will not be able to connect to this server until the database has been upgraded.

Upgrade Database?

[Y] Yes [N] No [S] Suspend [?] Help (default is "Y"):y

```
VERBOSE: Initialize-ApsDatabase: Creating database
```

```
VERBOSE: Initialize-ApsDatabase: Connecting to database
'ManagementServer'
```

```
VERBOSE: Initialize-ApsDatabase: Applying latest database schema
```

```
VERBOSE: Initialize-ApsDatabase: Applying default configuration to database
'ManagementServer'
```

```
VERBOSE: Completed Initialize-ApsDatabase
```

If upgrading from 10.x, a database connection parameter can be specified instead:

```
PS C:\> Initialize-ApsDatabase -DatabaseConnection 'NewConnection' -Verbose
```

You can use the ReportOnly option in Initialize-ApsDatabase to find out beforehand what the command is going to upgrade:

```
PS C:\> Initialize-ApsDatabase -DatabaseServer "SQLSERVER\Instance" -DatabaseName
ManagementServer -ConfigurerCredential $configurerAccount -ServiceCredential
$serviceAccount -ReportOnly
```

---

```
Existing database "ManagementServer" on server "SQLSERVER\Instance" to be upgraded from
Server Configuration version 13.2.0 to version 13.3.0
```

```
Existing database "ManagementServer" on server "SQLSERVER\Instance" to be upgraded from
version 10.0.0 to version 10.1.0
```

Upgrade details:

```
10.1.0      Upgrade from earlier major version
10.1.0      Create/replace [dbo].[Machine_Create]
10.1.0      Create/replace [dbo].[DiscoveredMachines_Create]
```

## Cloning an existing Server

The SCP cmdlets provide the ability to export and import server configuration settings. This allows the entire configuration of a product server to be cloned between machines. The configuration is stored as an XML file and information within the file is encrypted using a password when the configuration is exported. This password must be specified when configuring a server using the configuration file.

To export configuration settings, use the Export-ApsServerImage cmdlet:

```
Export-ApsServerImage -Path "PersonalizationServer.xml" -Password "password"
```

To configure a server using a configuration file use the Initialize-ApsServer cmdlet with the -Path and -Password parameters:

```
Initialize-ApsServer -Path "PersonalizationServer.xml" -Password "password"
```



## Server Configuration Portal Cmdlets

The SCP comes with a new PowerShell module to support operations provided by the new web interface. The cmdlets defined within this module can be accessed via a standard Import-Module:

```
Import-Module AppSense.ServerConfigurationPortal.PowerShell
```

After successfully importing, the following addition cmdlets will be available within the PowerShell session:

- Get-ApsDatabaseConnection
- Get-ApsServerInstance
- Get-ApsServerInstanceDetail
- Remove-ApsDatabaseConnection

Use the Get-ApsDatabaseConnection to obtain the list of all DatabaseConnections local to the installed SCP:

```
PS C:\Windows\system32> Get-ApsDatabaseConnection

ConnectionId      : b4e1cd90-5431-41f4-821e-f033396cfaf9
ServerType        : 935bfcca-23d0-4a08-93e4-064025b91d7b
FriendlyName      : AMC-Conn
SqlInstance       : SQLSERVER\Instance
DatabaseName      : ManagementServer
ConnectionString   :
ServiceCredential : ServerConfig.ConnectionCredential
ConfigurerCredential : ServerConfig.ConnectionCredential
UpgradeStarted    :
IsUpgrading       : False
```

The Get-ApsServerInstance cmdlet is used by the SCP to build its tree view and is a lightweight version of Get-ApsInstance.

```
PS C:\Windows\system32> Get-ApsServerInstance

ServerType      : Management
InstanceId       : 935bfcca-23d0-4a08-93e4-064025b91d7b
InstanceName    : DEFAULT
Local           : True
HostName       : VMM-2012R2
```

The Get-ApsServerInstanceDetail cmdlet is used by the SCP to provide information on a specific instance.

```
PS C:\> Get-ApsServerInstanceDetail -InstanceId 935bfcca-23d0-4a08-93e4-064025b91d7b
```

```
ServerType           : Management
InstanceId           : 935bfcca-23d0-4a08-93e4-064025b91d7b
InstanceName        : DEFAULT
Local                : True
HostName             :
WebSite              : Management
HostNameBinding      : Management.DesktopNow.AppSense
HostPort             : 80
LocalPort            : 7751
AuthTypes            : {Windows}
SupportedAuthTypes  : {Anonymous, Windows}
DatabaseSettingsName :
DatabaseName         :
DatabaseInstance    :
BindingInfo          :
{AppSense.ServerConfiguration.PowerShell.Model.ApsServerBindingDetails,
AppSense.ServerConfiguration.PowerShell.Model.ApsServerBindingDetails}
Status               : Unconfigured
Logging              : Undefined
Variances            : {}
ConfigurationBindings :
{AppSense.ServerConfiguration.PowerShell.Model.ApsServerBindingDetails,
AppSense.ServerConfiguration.PowerShell.Model.ApsServerBindingDetails}
```

You can specify:

- -InstanceId – returns information on the specified instance
- -InstanceName – returns information on the specified instance
- -HostName – returns information for all instances on a given host

The Remove-ApsDatabaseConnection cmdlet is used by the SCP to remove DatabaseConnections local to the SCP.

```
PS C:\> Remove-ApsDatabaseConnection -DatabaseConnection "NewConn" -Type Management
```

You can specify:

- -DatabaseConnection – The name of the DatabaseConnection to remove
- -Type – The DatabaseConnection type, either Management or Personalization.

---

## Database Management

### View Database Connection details

Use the Get-ApsDatabaseDetails cmdlet to display details of the current instances DatabaseConnection:

```
PS C:\> Get-ApsDatabaseDetail
```

```
DatabaseConnection : PS-Database-Conn
ServerName          : SQLSERVER\Instance
SqlDbName           : ManagementServer
ConnectionString    :
ServiceAccount      : ServiceCredentials
ServiceAuthType     : Impersonate
ServicePassword     : System.Security.SecureString
DatabaseState       : UpToDate
CurrentVersion      : 10.0.0.0
LatestVersion       : 10.0.0.0
```

### Update Database Connection details

Use the Update-ApsDatabase cmdlet to perform either a Schema upgrade and/or a Data Upgrade of an existing out of date database:

```
PS C:\> Update-ApsDatabase -DatabaseConnection "AMC-Database-Conn"
```

## Viewing Product Database Scripts

Use the Get-ApsDatabaseScript cmdlet to display the database scripts for a product:

```
PS C:\> Get-ApsDatabaseScript
```

| Name                | Description         | ScriptType         | AppliesTo |
|---------------------|---------------------|--------------------|-----------|
| Create Database     | Database creation   | CreateDatabase     | 10.1      |
| Get Version         | Version retrieva... | GetDatabaseVersion | 10.1      |
| IsDbEmpty           | Checks If Databa... | IsDatabaseEmpty    | 10.1      |
| Create Login        | Creates a Login ... | CreateLogins       | 10.1      |
| Purge Events        | Purges all event... | BatchJobs          | 10.1      |
| Create Schema       | Create Schema       | CreateSchema       | 10.1      |
| Upgrade Schema 7... | Upgrade Schema 7... | UpgradeSchema      | 7.0       |
| Upgrade Schema 7... | Upgrade Schema 7... | UpgradeSchema      | 7.1       |
| Upgrade Schema 7... | Upgrade Schema 7... | UpgradeSchema      | 7.2       |
| Upgrade Schema 8... | Upgrade Schema 8... | UpgradeSchema      | 8.0       |
| Upgrade Schema 8... | Upgrade Schema 8... | UpgradeSchema      | 8.1       |
| Upgrade Schema 8... | Upgrade Schema 8... | UpgradeSchema      | 8.2       |
| Upgrade Schema 8... | Upgrade Schema 8... | UpgradeSchema      | 8.3       |
| Upgrade Schema 8... | Upgrade Schema 8... | UpgradeSchema      | 8.4       |
| Upgrade Schema 8... | Upgrade Schema 8... | UpgradeSchema      | 8.5       |
| Upgrade Schema 8... | Upgrade Schema 8... | UpgradeSchema      | 8.6       |
| Upgrade Schema 8... | Upgrade Schema 8... | UpgradeSchema      | 8.7       |
| Upgrade Schema 8... | Upgrade Schema 1... | UpgradeSchema      | 10.0      |

## Exporting Database Creation Scripts

Use the Export-ApsDatabaseScript cmdlet to export database scripts

```
PS C:\> Export-ApsDatabaseScript -ScriptType "CreateDatabase, CreateSchema, CreateLogins"
-Path C:\Scripts
PS C:\> Get-ChildItem C:\Scripts
```

Directory: C:\Scripts

| Mode  | LastWriteTime    | Length | Name                |
|-------|------------------|--------|---------------------|
| -a--- | 17/07/2013 17:36 | 2281   | Create_Database.sql |
| -a--- | 17/07/2013 17:36 | 4501   | Create_Login.sql    |
| -a--- | 17/07/2013 17:36 | 349344 | Create_Schema.sql   |

## Exporting Database Upgrade Scripts

Use the `Get-ApsDatabaseVersion` to get the version of a database:

```
PS C:\> $version = Get-ApsDatabaseVersion
```

Use the version from `Get-ApsDatabaseVersion` to retrieve the appropriate upgrade script:

```
PS C:\> Export-ApsDatabaseScript -ScriptType UpgradeSchema -AppliesTo $version | Out-File "UpgradeSchema.sql"
```

## Connecting a Server to a Database

Use the `Set-ApsServerDatabase` cmdlet to quickly switch a server to use a different database. You must have previously used `Initialize-ApsServer` to ensure the server has completed initial configuration.

To switch a server to use a database for which a `DatabaseConnection` exists, use the `-DatabaseConnection` parameter.

For example:

```
PS C:\> Set-ApsServerDatabase -DatabaseConnection "PS-Database-Conn" -Verbose
```

To switch a server to use a database where no existing `DatabaseConnection` exists, specify the required parameters.

For example:

```
PS C:\> Set-ApsServerDatabase -DatabaseServer "SQLSERVER\Instance" -DatabaseName "PersonalizationServerNew" -ServiceCredential $credential -Verbose
```

## Server Management

### View Server details

Use the Get-ApsServerDetail cmdlet to display details of the current instances website:

```
PS C:\> Get-ApsServerDetail

WebSite           : Management
HostName          : Management.DesktopNow.AppSense
HostPort         : 7751
LocalPort        : 80
AuthTypes        : {Windows}
SupportedAuthTypes : {Anonymous, Windows}
DatabaseSettingsName : NewConn
DatabaseName     : ManagementServer
DatabaseInstance : SQLSERVER\Instance
Status           : Started
Logging          : Disabled
Variances        : {}
BindingInfo      :
{AppSense.ServerConfiguration.PowerShell.Model.ApsServerBindingDetails,
AppSense.ServerConfiguration.PowerShell.Model.ApsServerBindingDetails}
ConfigurationBindingInfo :
{AppSense.ServerConfiguration.PowerShell.Model.ApsServerBindingDetails,
AppSense.ServerConfiguration.PowerShell.Model.ApsServerBindingDetails}
OriginalUpgradeCode : 935bfcca-23d0-4a08-93e4-064025b91d7b
InstanceId         : 935bfcca-23d0-4a08-93e4-064025b91d7b
InstanceName      : DEFAULT
```

The full set of binding information for the website is contained within the BindingInfo array. To access this array use the following commands:

```
PS C:\> $serverDetails = Get-ApsServerDetail
PS C:\> $serverDetails.BindingInfo.Count
2

PS C:\> $serverDetails.BindingInfo[0] | Format-List

IpAddress : *
Host      :
Port     : 8081
Protocol : http

PS C:\> $serverDetails.BindingInfo[1] | Format-List
```

```
IpAddress : *  
Host      : MyHostHeader  
Port      : 9091  
Protocol  : http
```

## Resetting a Server to an out of box state

The Reset-ApsServer cmdlet can be used to reset a server to an out of box state. During a reset:

- All services and application pools are stopped/removed
- All web directories are removed
- The product configuration is deleted
- The server stops running

For example:

```
PS C:\> Reset-ApsServer
```

## Starting or Stopping a Server

The Start-ApsServer and Stop-ApsServer cmdlets can be used to start or stop a product server. Starting or stopping a product server starts/stops all services and application pools associated with the product server. Product consoles may display an error message to users if they attempt to connect or perform any actions whilst a server is stopped.

To stop a server use the Stop-ApsServer cmdlet. For example:

```
PS C:\> Stop-ApsServer
```

To start a server use the Start-ApsServer cmdlet. For example:

```
PS C:\> Start-ApsServer
```

The current state of a server can be determined using the Get-ApsCurrentInstance cmdlet. For example:

```
PS C:\> Get-ApsCurrentInstance
```

Review the status field to determine if a server is started, stopped or unconfigured.

## Changing Website

The Set-ApsWebSite cmdlet allows a configured server instance to migrate from its current website to a new one. For example:

```
PS C:\> Set-ApsWebSite -WebSiteName "NewWebSite"
```

If the website name specified by the `-WebSiteName` parameter does not exist, it will be created. If it does exist, the website will be used. The old website will be stopped.

## Viewing and Fixing Variances

If a server is encountering problems use the `Get-ApsVariance` cmdlet to highlight known issues:

```
PS C:\> Get-ApsVariance
```

Many variances can be fixed automatically. Use the `Repair-ApsVariance` cmdlet to attempt to repair variances:

```
PS C:\> Repair-ApsVariance -All
```

You can also limit the variances that will be repaired using the `Where-Object` cmdlet. For example:

```
PS C:\> $variance = Get-ApsVariance | Where-Object { $_.Name -eq "" }  
PS C:\> Repair-ApsVariance -Variance $variance
```

## Enabling or Disabling Logging

Logging can be enabled/disabled using the `Enable-ApsLogging` and `Disable-ApsLogging` cmdlets. Enabling logging creates log files in product server installation directory:

```
PS C:\> Enable-ApsLogging
```

Once an issue requiring logging has been resolved, use the `Disable-ApsLogging` cmdlets to disable logging:

```
PS C:\> Disable-ApsLogging
```



## Scripting Multiple/Remote Servers

### Enabling Remoting

Windows PowerShell remoting allows scripts to communicate with and run Windows PowerShell cmdlets on remote machines. No configuration is required to enable a computer to send remote commands. However, to receive remote commands, Windows PowerShell remoting must be enabled on the machine.

Windows PowerShell remoting is enabled on Windows Server 2012 by default. On all other systems, use the `Enable-PSRemoting` cmdlet to enable it. You can also use the `Enable-PSRemoting` cmdlet to re-enable remoting on Windows Server 21012 if it is disabled.

To enable remoting, open a Windows PowerShell console as an administrator and enter:

```
PS C:\> Enable-PSRemoting
```



#### Note

For more information refer to *Enable-PSRemoting* on Microsoft TechNet:

<http://technet.microsoft.com/en-us/library/hh849694.aspx>

### Enabling CredSSP

CredSSP allows credentials to be passed to a secondary machine on the network. This allows the SCP cmdlets to:

- Connect to SQL server databases using the current user
- Read server images (used for cloning servers) from a network share

Whilst CredSSP is not required, if it is not used you must specify the `-ConfigurerCredential` parameter wherever it is used.

Enabling CredSSP requires changes on both server and client machines:

- On a server machine, to allow CredSSP connections, use:

```
Enable-WSManCredSSP Server
```

Select Yes when prompted to allow CredSSP connections

- On client machines, to allow outbound CredSSP connections to specified servers, use:

```
Enable-WSManCredSSP Client -DelegateComputer @"server1.domain", "server2.domain")
```

Select Yes when prompted to allow CredSSP connections



#### Note

For more information refer to *Enable-WSManCredSS* on Microsoft TechNet:

<http://technet.microsoft.com/en-us/library/hh849872.aspx>.

---

## Working with PowerShell Sessions

Windows PowerShell allows for the concept of sessions, each of which may load in a separate copy of the SCP cmdlets. You can use Invoke-Command to create a temporary session and run cmdlets, or create a session that can be re-used using New-PSSession.

**Note**

For more information refer to *about\_PSSessions* on Microsoft Technet:  
<http://technet.microsoft.com/en-us/library/hh847839.aspx>.

## Script Examples

### Complete Server Configuration

```

$ProductName = "Personalization Server"
$ConfigurerUsername = "DOMAIN\AppSensePersonalizationServerConfigurer"
$ConfigurerPassword = "password"
$ServiceUsername = "DOMAIN\AppSensePersonalizationServerService"
$ServicePassword = "password"
$DatabaseServer = "SQLSERVER\Instance"
$DatabaseName = "AppSensePersonalizationServer"
$DatabaseConnection = "PS-Database-Conn"

# Load cmdlets for appropriate product
Import-Module AppSenseInstances
Import-ApsInstanceModule -ProductName $ProductName -IsDefault

# Create configurer credential object
$SecurePassword = ConvertTo-SecureString -AsPlainText $ConfigurerPassword -Force
$ConfigurerCredential = New-Object System.Management.Automation.PSCredential
($ConfigurerUsername, $SecurePassword)

# Create service credential object
$SecurePassword = ConvertTo-SecureString -AsPlainText $ServicePassword -Force
$ServiceCredential = New-Object System.Management.Automation.PSCredential
($ServiceUsername, $SecurePassword)

# Install/fix all prerequisites
Get-ApsPrerequisite | Install-ApsPrerequisite

# Create database
Initialize-ApsDatabase -DatabaseServer $DatabaseServer -DatabaseName $DatabaseName -
ConfigurerCredential $ConfigurerCredential -ServiceCredential $ServiceCredential -
DatabaseConnection $DatabaseConnection

# Configure server
Initialize-ApsServer -DatabaseConnection $DatabaseConnection
  
```

### Clone Multiple Servers from the Current Server

```

$Credential = Get-Credential
$ProductName = "Personalization Server"
$Path = "\\server\share\ServerImage.xml"
$Password = "password"
$ComputerName = @("server1.domain", "server2.domain")

Import-ApsInstanceModule -ProductName $ProductName -IsDefault
Export-ApsServerImage -Path $Path -Password $Password

Invoke-Command -ComputerName $ComputerName -ScriptBlock {
    Param($ProductName, $Path, $Password)
    Import-ApsInstanceModule -ProductName $ProductName -IsDefault
    Initialize-ApsServer -Path $Path -Password $Password
} -ArgumentList ($ProductName, $Path, $Password) -Authentication Credssp -Credential
$Credential
  
```

## Return Variances from Multiple Servers

```
$Credential = Get-Credential
$ProductName = "Personalization Server"
$ComputerName = @("server1.domain", "server2.domain")

Invoke-Command -ComputerName $ComputerName -ScriptBlock {
    Param($ProductName, $Path, $Password)
    Import-ApsInstanceModule -ProductName $ProductName -IsDefault
    Get-ApsVariance
} -ArgumentList ($ProductName, $Path, $Password) -Authentication Credssp -Credential
$Credential
```