# ivanti

**Pulse Secure Virtual Traffic Manager: REST API Guide** 

#### **Copyright Notice**

This document is provided strictly as a guide. No guarantees can be provided or expected. This document contains the confidential information and/or proprietary property of Ivanti, Inc. and its affiliates (referred to collectively as "Ivanti") and may not be disclosed or copied without prior written consent of Ivanti.

Ivanti retains the right to make changes to this document or related product specifications and descriptions, at any time, without notice. Ivanti makes no warranty for the use of this document and assumes no responsibility for any errors that can appear in the document nor does it make a commitment to update the information contained herein. For the most current product information, please visit www.Ivanti.com.

Copyright © 2022, Ivanti. All rights reserved.

Protected by patents, see <a href="https://www.ivanti.com/patents">https://www.ivanti.com/patents</a>.

# **Contents**

Preface	<b>7</b>
Document conventions	7
Text formatting conventions	7
Command syntax conventions	7
Notes and Warnings	8
Requesting Technical Support	8
Self-Help Online Tools and Resources	9
Opening a Case with PSGSC	9
Introducing REST	10
Why use a REST API	. 11
A REST-Based Architecture	. 11
Scope of This Release	12
Typical Usage in the Traffic Manager	. 14
The Resource Model	14
Sections	15
Data Types	15
Resource URI Patterns	18
Configuration Resources	18
Counter and Information Resources	. 19
Traversing the Tree	19
The Traffic Manager REST Service	. 23
The Pulse Secure Virtual Web Application Firewall REST Interface	23
Authentication	. 24
Supported HTTP Methods	. 24
Requesting a Resource	25
Setting Configuration for a Resource	26
Removing Resources	. 26
Further Aspects of the Resource Model	27
Enumerated Types	27
Uploading Files	27
Custom Configuration Sets	27
Errors	28
Configuration Backups	29
Traffic Manager UI Features	33
Enabling and Disabling the API	33
Controlling Timeout Events	. 33
Configuring the IP Addresses That the REST API Listens On	34
Restricting Access to Trusted Users	. 35
Log Messages in the Traffic Manager	35
Examples and Use-Cases	. 37
Typical Usage	37
Listing Running Virtual Servers	38

Adding a Node to a Pool	40
Resource Model Reference	
About the Resource Model Reference	43
Getting Information About the Structure of Resources	43
Configuration Resources	44
Action Program	44
Admin SSL Trusted Certificate	44
Alerting Action	45
Aptimizer Application Scope	50
BGP Neighbor	51
Bandwidth Class	53
Cloud Credentials	54
Custom configuration set	56
DNS Zone	56
DNS Zone File	57
Event Type	57
Extra File	64
GLB Service	64
Global Settings	
Kerberos Configuration File	126
Kerberos Keytab	126
Kerberos Principal	127
License	
Location	
Log Export	
Monitor	131
Monitor Program	
NAT Configuration	139
Pool	
Protection Class	166
Pulse Secure Virtual Web Application Firewall	171
Rate Shaping Class	
Rule	
SLM Class	
SSL Client Key Pair	
SSL Key Pair	
SSL Ticket Key	
SSL Trusted Certificate	
Security Settings	
Service Discovery Plugins	
Session Persistence Class	
Traffic IP Group	
Traffic Manager	
TrafficScript Authenticator	207

Trusted SAML Identity Provider	210
User Authenticator	211
User Group	219
Virtual Server	221
Web Accelerator Profile	269
SNMP Counter Values	271
Actions	271
Asp session cache	271
Bandwidth	272
Cloud api credentials	273
Connection rate limit	274
Events	275
Glb services	275
Globals	276
Ip gateway	287
lp session cache	
J2ee session cache	290
Listen ips	291
Locations	292
Network interface	292
Node	293
Node inet46	
Per location service	298
Per node service level	300
Per node service level inet46	301
Per pool node	302
Pools	
Rule authenticators	
Rules	
Service level monitors	
Service protection	
Ssl cache	
Ssl ocsp stapling	
Ssl session cache	
Traffic ip	
Traffic ip inet46	
Uni session cache	
User counters 32	
User counters 64	
Virtual servers	
Web cache	
System Information Resources	
Backups	
Information	336

State	336
Handling Updates to the REST API	339
REST API Support in the Traffic Manager	339
Updating Your Applications to Use a New Version of the API	340
Changes Involving a Minor API Update	340
Changes Involving a Major API Update	340
REST API Change History	341
Changes in Version 8.3	341
Changes in Version 8.2	341
Changes in Version 8.1	341
Changes in Version 8.0	342
Changes in Version 7.1	342
Changes in Version 7.0	342
Changes in Version 6.2	343
Changes in Version 6.1	344
Changes in Version 6.0	345
Changes in Version 5.2	365
Changes in Version 5.1	366
Changes in Version 5.0	367
Changes in Version 4.0	374
Changes in Version 3.11	377
Changes in Version 3.10	378
Changes in Version 3.9	379
Changes in Version 3.8	382
Changes in Version 3.7	383
Changes in Version 3.6	384
Changes in Version 3.5	385
Changes in Version 3.4	387
Changes in Version 3.3	388
Changes in Version 3.2	389
Changes in Version 3.1	391
Changes in Version 3.0	302

# **Preface**

# **Document conventions**

The document conventions describe text formatting conventions, command syntax conventions, and important notice formats used in Ivanti technical documentation.

# **Text formatting conventions**

Text formatting conventions such as boldface, italic, or Courier font may be used in the flow of the text to highlight specific words or phrases.

Format	Description	
bold text	Identifies command names	
	Identifies keywords and operands	
	Identifies the names of user-manipulated GUI elements	
	Identifies text to enter at the GUI	
italic text	Identifies emphasis	
	Identifies variables	
	Identifies document titles	
Courier Font	Identifies command output	
	Identifies command syntax examples	

# **Command syntax conventions**

Bold and italic text identify command syntax components. Delimiters and operators define groupings of parameters and their logical relationships.

Convention	Description
bold text	Identifies command names, keywords, and command options.

Convention	Description
italic text	Identifies a variable.
[]	Syntax components displayed within square brackets are optional.
	Default responses to system prompts are enclosed in square brackets.
{ x   y   z }	A choice of required parameters is enclosed in curly brackets separated by vertical bars. You must select one of the options.
x   y	A vertical bar separates mutually exclusive elements.
< >	Non-printing characters, for example, passwords, are enclosed in angle brackets.
	Repeat the previous element, for example, member[member].
\	Indicates a "soft" line break in command examples. If a backslash separates two lines of a command input, enter the entire command at the prompt without the backslash.

# **Notes and Warnings**

Note, Attention, and Caution statements might be used in this document.



A Note provides a tip, guidance, or advice, emphasizes important information, or provides a reference to related information.

#### **ATTENTION**

An Attention statement indicates a stronger note, for example, to alert you when traffic might be interrupted or the device might reboot.

#### **CAUTION**

A Caution statement alerts you to situations that can be potentially hazardous to you or cause damage to hardware, firmware, software, or data.

# **Requesting Technical Support**

Technical product support is available through the Ivanti Global Support Center (PSGSC). If you have a support contract, file a ticket with PSGSC.

 Product warranties—For product warranty information, visit https://support.pulsesecure.net/product-service-policies/

# **Self-Help Online Tools and Resources**

For quick and easy problem resolution, Ivanti provides an online self-service portal called the Customer Support Center (CSC) that provides you with the following features:

- Find CSC offerings: https://support.pulsesecure.net
- Search for known bugs: <a href="https://support.pulsesecure.net">https://support.pulsesecure.net</a>
- Find product documentation: https://www.ivanti.com/support/product-documentation
- Download the latest versions of software and review release notes: https://support.pulsesecure.net
- Open a case online in the CSC Case Management tool: https://support.pulsesecure.net
- To verify service entitlement by product serial number, use our Serial Number Entitlement (SNE)
   Tool: <a href="https://support.pulsesecure.net">https://support.pulsesecure.net</a>

For important product notices, technical articles, and to ask advice:

- Search the Pulse Secure Knowledge Center for technical bulletins and security advisories: https://kb.pulsesecure.net
- Ask questions and find solutions at the Pulse Community online forum: <a href="https://community.pulsesecure.net">https://community.pulsesecure.net</a>

# **Opening a Case with PSGSC**

You can open a case with PSGSC on the Web or by telephone.

- Use the Case Management tool in the PSGSC at https://support.pulsesecure.net.
- Call 1-844 751 7629 (Toll Free, US).

For international or direct-dial options in countries without toll-free numbers, see https://support.pulsesecure.net/support/support-contacts/

# **Introducing REST**

REST (REpresentational State Transfer) is a framework for API design. It is based on generic facilities of the standard HTTP protocol, including the six basic HTTP methods (GET, POST, PUT, DELETE, HEAD, INFO) and the full range of HTTP return codes.

A REST interface partitions the API into a series of "resources," each of which can be accessed using one or more HTTP methods. (In the Traffic Manager, only the GET, PUT, and DELETE methods are used; HEAD, POST and INFO are not currently implemented). Each method operates in the Traffic Manager as follows:

- **GET**: Obtain a representation of the resource, without modifying server state (except perhaps for logging purposes).
- PUT: Create a new resource or apply some change to a resource. Where the resource exists,
  only those properties specified in the request are modified; all others remain unchanged. If a
  resource object does not exist, a new one is created.
- DELETE: Delete an existing resource.

Importantly, each resource is uniquely identified with an address, or URI (Uniform Resource Identifier). In other words, if you know the URI you can access the resource (subject to the normal authorization/authentication processes associated with accessing the administrative systems of the Traffic Manager).

Since all resources have URIs, resources can point to other resources by embedding the URIs of related resources within their representations.

In the Traffic Manager, all resources are represented and stored as JSON (JavaScript Object Notation) structures. Requests and responses that interact with the Traffic Manager through the REST API must adopt the same format.

The full range of HTTP return codes is available in REST, although in practice a useful subset can be identified and applied consistently. So, for example, it should be evident from the response itself whether a request has succeeded or not, without any need for parsing the body of the response. However, the Traffic Manager always attempts to provide extra information regarding a failure into the response body. For more details, see Errors.


# Why use a REST API

REST interfaces have become popular in public APIs because of their inherent simplicity. An API can focus on available resources, with details regarding updating and deleting of each resource delegated to the appropriate HTTP method in predictable ways.

The purpose of implementing a REST API is not primarily to add functionality but to add structure. Because of the inherent similarity of all REST APIs (by virtue of their underlying HTTP structure), familiarity with any REST API brings familiarity with all of them. In many cases it is just as easy to implement to a REST design as it is to use a more ad hoc API design, while reaping the benefits that come with well-understood REST conventions.

Finally, the availability of return codes is another example of leveraging known semantics when building a useful API. Without a meaningful return code it becomes necessary to parse every response to find out whether it worked or not. In addition, most modern browsers and Web programming frameworks expect that specific HTTP error codes are set in the event of error and respond differently depending on the code. This is especially apparent in the case of AJAX requests, which are often handled differently by many modern Javascript frameworks depending on the status code returned from the server.

#### A REST-Based Architecture



Management Station

A cluster of Traffic Managers is typically managed through the web-based administration user interface (Admin UI) on one of the cluster members. The Traffic Manager's REST API provides an alternative means to remotely administer, configure, and monitor a Traffic Manager cluster.

The REST service is enabled by default for new Traffic Manager instances. To toggle the REST service between enabled and disabled, see Enabling and Disabling the API.



For Traffic Managers running version 11.0 or earlier, the REST service is disabled by default. To preserve the integrity of your configuration, the REST service state is unchanged during an upgrade to a Traffic Manager version later than 11.0.

The Traffic Manager REST API can be used by any HTTP client or application environment that supports HTTP services.

A management application can issue a REST request to any one of the Traffic Managers in a cluster. The application may be running on a stand-alone management server, one of the server nodes, or even on one of the Traffic Managers. All Traffic Managers in the cluster automatically synchronize their configuration, so a configuration change sent to one machine is automatically replicated across the cluster.

#### **ATTENTION**

When upgrading your Traffic Manager cluster to the latest software version, do not attempt to use the REST API until all cluster members have been successfully upgraded. As configuration is automatically synchronized across all cluster members, only one Traffic Manager should be used to update the entire cluster at a time. Use of the REST API on a cluster in a mixed-version state can result in unexpected behavior. For more information on upgrading, see the Pulse Secure Virtual Traffic Manager: Installation and Getting Started Guide applicable to your product variant.

#### **ATTENTION**

Due to the nature of the REST API's ability to access and modify your Traffic Manager configuration, it is strongly recommended that you disallow access to this service from outside of your trusted network.

# **Scope of This Release**

This document describes the features and capabilities of the REST API for the Pulse Secure Virtual Traffic Manager 21.4 release. The REST API version referred to in this document is 8.3.

The API performs basic type checking, although Ivanti recommends that your client applications provide suitable validation to ensure the suitability of the configuration data being provided to the Traffic Manager.

All defined users in the system have the ability to authenticate a connection through the Traffic Manager REST API. However, you cannot modify the users configuration file in any way, so it is not possible to add, edit, or delete users through the API.

A full list of specific features, capabilities, and API versions supported by this release can be found in the release notes supplied with your product variant.

# **Typical Usage in the Traffic Manager**

This chapter describes the usage, syntax, and structure of the Traffic Manager REST API.

#### The Resource Model

The Traffic Manager REST API is made up of a hierarchy of resources that are manipulated using standard HTTP calls to a listener service running along side the Traffic Manager. HTTP URIs are used to address the resources in the system.

There are three resource types:

- Configuration: to represent Traffic Manager configuration objects.
- Counters: for reporting through SNMP counters.
- Information: for system information.

Counters and Information resources are read-only, whereas Configuration resources are fully interactive and map directly to the native Traffic Manager configuration system. Each concept, such as pools, virtual servers, TrafficScript rules, or Service Level Monitoring classes, has an associated configuration resource model.

All resources are represented as JSON structures (MIME type application/json), and objects of each resource type are captured in this format.

Typically, a configuration resource follows this format:

```
"properties": {
    "sectionname": {
        "key1": "stringvalue1",
        "key2": numericvalue2,
        "key3": booleanvalue3
    }
}
```

A single instance of a resource, for example a virtual server, contains a primary group entitled "properties". This contains all configuration keys attributable to this resource type.

Counter resources contain dynamically generated data to correspond to SNMP counters in the Traffic Manager.

#### **Sections**

Sections are designed to contain properties (or "keys") that have a commonality of purpose or perhaps apply in certain circumstances. For example, monitor classes may have keys that apply only to monitors of particular types.

In a configuration resource, the properties group contains several sections, one for each logical set of keys. There is always a section entitled "basic," containing common configuration items, followed by one or more additional sections according to the specification of the resource.

A counter resource contains a single section, "statistics," listing the SNMP counters associated with the resource. Similarly, an information resource contains a single section, "information," listing the system information properties applicable to this Traffic Manager.

# **Data Types**

Each key:value pair is then presented as a comma-separated list within each section, according to the specification shown throughout this guide. Key names are always delimited by quotes, with the values according to the following rules:

Туре	Value
Boolean	A value of true or false (case-sensitive).
	For example:
	"key1": true, "key2": false
Int	A numeric positive or negative value with no decimal point.
	For example:
	"key1": 1024, "key2": -10
Unsigned Int	A numeric positive value with no decimal point.
	For example:

Туре	Value
	"key1": 0, "key2": 50
Float	A numeric positive or negative value that can have a decimal point.
	For example:
	"key1": 1.0, "key2": -1024.111
	A set of alpha-numeric characters that may not include new-lines. Non-alpha characters must use correct character escapes.
String	For example:
String	"key1": "Hello world", "key2": "", "key3": "Hello y\'all"
Freeform	A set of alpha-numeric characters that can contain new-lines. Non-alpha characters must use correct character escapes, and a newline must be represented by a \n.
String	For example:
	"key1": "Multi-line\nString",
	A string that cannot be read, only written to. When read, it is displayed as a structure that indicates if the password has been set (is non-empty).
	For example, when reading the key:
	"key1": { "password_set": false },
Password	"key2": { "password_set": true }
	When writing to the key, the structure can be unchanged, or a new password can be set:
	<pre>"key2": { "password_set": true }, "key1": "secret123"</pre>
Time	Times are represented as strings in ISO8601 time format, including a time zone designator.

Туре	Value
	For example:
	{Year}-{Month}-{Day}T{Hour}:{Minute}:{Second}{Time Zone}
	This is a collection of unique unordered items of a particular type, stored as an array.
Set	For consistency, a set is rendered in alpha-numeric order.
	For example:
	"key": [ "Item A", "Item B", "Item D" ]
	This is a collection of ordered items of a particular type. It may contain duplicates and is stored as a standard array.
List	For example:
	"key": [ "Item A", "Item C", "Item A" ]
Tables	This is a special type designed to allow nested data within a single config key. In some circumstances, you might wish to specify a list or array of data items, such as a list of pool nodes, where each item has one or more extra pieces of configuration data to be attached to it.
	Each one of these nested list entries expects a value known as the "primary key", used to identify it. Each sub-key value should then be specified in the same way.
	For example:
	"key": [
	<pre>{     "prmkey": "Hello World",</pre>
	"subkey1": false,
	"subkey2": [ "Item 1", "Item 2" ]
	},
	{
	"prmkey": "Other text", "subkey1": true,
	"subkey2": []

Туре	Value
	}, 1

#### **Resource URI Patterns**

Resource URIs are case-sensitive.

The Traffic Manager provides access to its resources through a common base URI that identifies the root of the resource model:

https://<host>:<port>/api/tm/<version>

#### In this URI path:

- <host>: The hostname of the Traffic Manager whose REST API you are accessing.
- <port>: The port that the REST API is published on (typically "9070").
- <version>: The version number of the REST API you are accessing. Details of supported versions are contained in the release notes supplied with your product variant.

All client applications and scripts that access the Traffic Manager REST API must use the same supported major version of the API at any one time. The Traffic Manager does not support interactions using multiple versions concurrently.



In the previous example, a scheme of HTTPS is used to signify an encrypted connection from a remote client. HTTP is supported only where the connection is to a server on the same host. For further details, see Authentication.

The Traffic Manager presents different resource types at specific child nodes under this root URI.

# **Configuration Resources**

Configuration resources map to objects in the Traffic Manager's configuration system. To access configuration resources, use the following URI pattern:

https://<host>:<port>/api/tm/<version>/config/active

Instances of a particular configuration resource, such as a virtual server, are persistently stored and alter the host Traffic Manager's behavior if changed. Additionally, changes you make here are synchronized automatically to all other Traffic Managers in the cluster.

To view or modify a stored configuration resource record, append the full path to the end of the base URI. For example, to issue a request for a virtual server resource named "Web", use the following URI:

https://myhost:9070/api/tm/8.3/config/active/virtual servers/Web

#### **Counter and Information Resources**

Counter resources map to SNMP counter objects generated by the Traffic Manager. To access counter resources, use the following URI pattern:

https://<host>:<port>/api/tm/<version>/status/<tm>/statistics

Information resources provide basic information data about your cluster members. To access information resources, use the following URI pattern:

https://<host>:<port>/api/tm/<version>/status/<tm>/

Unlike configuration resources, instances of counter and information resources are specific to each Traffic Manager in the cluster. You can access the data for all of your cluster members from the base URI of any one of them by specifying the desired member hostname in the /<tm>/ child node.

For example, to request the SNMP counter data from cluster member "myhost2" for a pool named "P1", use the following URI:

https://myhost:9070/api/tm/8.3/status/myhost2/statistics/pools/P1



The child node <tm> also accepts the special node name "local\_tm", to refer to the REST API of the Traffic Manager you are accessing. For further information, see Traversing the Tree.

# **Traversing the Tree**

Resource URIs can be either:

- Resources.
- A directory structure containing child elements denoting sub-directories or resource nodes.

You can test the overall availability of the REST API by querying the following URI in a compatible Web browser or JSON/REST query application:

```
https://<host>:<port>
```

(As mentioned above, <host> is the hostname of the Traffic Manager and <port> is the port that the REST API is published on).

Some versions of Internet Explorer are unable to directly render the "application/json" MIME type data returned from a Traffic Manager REST API query. Ivanti recommends using an alternative browser. However, to resolve the issue for affected browsers, amend the Windows registry as shown here:

1. Open Notepad and enter the following text:

```
Windows Registry Editor Version 5.00;

Tell IE 7,8,9,10,11 to open JSON documents in the browser on Windows XP and later.

25336920-03F9-11cf-8FD0-00AA00686F13 is the CLSID for the "Browse in place".

[HKEY_CLASSES_ROOT\MIME\Database\Content Type\application/json]

"CLSID"="{25336920-03F9-11cf-8FD0-00AA00686F13}"

"Encoding"=hex:08,00,00,00
```

- 2. Save the document as "IE-Json.reg" and then run it.
- 3. Restart Internet Explorer and re-enter a REST URI to confirm the JSON results appear within the browser.



For further information, see <a href="http://www.codeproject.com/Tips/216175/View-JSON-in-Internet-Explorer">http://www.codeproject.com/Tips/216175/View-JSON-in-Internet-Explorer</a>.

A GET request for this URI should yield the following result:

```
{
    "children": [{
         "name": "api",
         "href": "/api/"
    }]
},
```

This shows that the REST service at <host>:<port> contains a single child element "/api". As discussed in Resource URI Patterns, the full root URI of the configuration resource model then becomes:

```
https://myhost:9070/api/tm/8.3/config/active
```

Therefore, requesting this URI results in a list of child elements similar to the following example:

```
"children": [{
  "name": "action programs",
   "href": "/api/tm/8.3/config/active/action_programs/"
   "name": "actions",
   "href": "/api/tm/8.3/config/active/actions/"
}, {
   "name": "aptimizer",
   "href": "/api/tm/8.3/config/active/aptimizer/"
}, {
   "name": "bandwidth",
   "href": "/api/tm/8.3/config/active/bandwidth/"
}, {
   "name": "cloud api credentials",
   "href": "/api/tm/8.3/config/active/cloud api credentials/"
}, {
(truncated)
}, {
   "name": "virtual servers",
   "href": "/api/tm/8.3/config/active/virtual servers/"
} ]
```

This output identifies all configuration resource types available through the Traffic Manager being queried. Each is identified by a name and href attribute combination.

A query for a specific resource type shows all instances of that resource defined within the Traffic Manager configuration. For example, the following URI lists all virtual servers:

```
https://myhost:9070/api/tm/8.3/config/active/virtual_servers
```

The output shows each stored virtual server, as per the following example:

```
{
   "children": [{
        "name": "vs1",
        "href": "/api/tm/8.3/config/active/virtual_servers/vs1"
}, {
```

SNMP counter and system information resources are unique to each Traffic Manager in the cluster. You can access the data for each cluster member from the API of whichever Traffic Manager you are connected to.

To list the available Traffic Managers in your cluster, perform a request for the following URI:

```
https://myhost1:9070/api/tm/8.3/status
```

The response is a list of child elements similar to the following:

```
"children": [{
    "name": "myhost1.example.com",
    "href": "/api/tm/8.3/status/myhost1.example.com/"
}, {
    "name": "myhost2.example.com",
    "href": "/api/tm/8.3/status/myhost2.example.com/"
}, {
    "name": "myhost3.example.com",
    "href": "/api/tm/8.3/status/myhost3.example.com/"
}, {
    "name": "local_tm",
    "href": "/api/tm/8.3/status/local_tm/"
}]
```

The list also includes the "local\_tm" child node that corresponds to the REST API of the Traffic Manager you are currently accessing. This provides a consistent programmatic interface to access resources for the local Traffic Manager only, no matter which host's API you are connected to. For example, the following URI can be used on the API of any Traffic Manager in the cluster, and the response contains results for that Traffic Manager only:

```
/api/tm/8.3/status/local tm/information
```

To view (or modify, in the case of configuration resources) a stored record for a particular resource type, append the full path to the end of this base URI. For example, a request for a virtual server configuration resource named "Web" looks like this:

https://myhost:9070/api/tm/8.3/config/active/virtual servers/Web

Equally, a request for the SNMP counter output for a pool named "P1" looks like this:

https://myhost:9070/api/tm/8.3/status/local tm/statistics/pools/P1

# The Traffic Manager REST Service

The Traffic Manager REST API is an HTTP service running on the Traffic Manager server. By default, it is available on TCP port 9070, although this can be reconfigured. The REST service supports HTTP versions: 0.9, 1.0, and 1.1; Version 1.1 is recommended.

When connecting to the local machine using a loop-back interface (for example, 127.0.0.1 or "localhost"), plain HTTP must be used. When connecting from a remote machine, connections must be encrypted using SSL (HTTPS).

The service uses the same SSL certificate as the Traffic Manager's admin server, which by default is an automatically generated self-signed certificate. Any HTTP client used to connect to the REST API should have the server's self-signed certificate added to its trusted certificate catalogue. Alternatively the admin server/REST certificate can be replaced with one signed by a trusted certificate authority.

# The Pulse Secure Virtual Web Application Firewall REST Interface

The Pulse Secure Virtual Web Application Firewall (vWAF) component maintains a separate REST interface to facilitate control of vWAF-specific resources. You can reach this interface through the standard Traffic Manager REST service, using the following path:

https://<host>:<port>/api/af/<version>

<version> can be any specific currently published API version, or you can use the string "latest" to access the most current version. Full details of the available resources and actions that can be performed through the vWAF REST API can be found in the vWAF user documentation.

To access the vWAF REST interface, you must first install and activate the vWAF component on your Traffic Manager. You must also enable the Traffic Manager REST service through the Admin UI (for details, see Enabling and Disabling the API).

The Traffic Manager operates as a proxy to the vWAF REST service, and communicates with it through a designated port. To view and modify this port, click **System > Application Firewall > Local Application Firewall Ports** in the Admin UI. Any problems accessing the vWAF REST interface can often be resolved by setting this value to a known free port. Contact your support provider if you require any further information.

# **Authentication**

A REST-based management application communicates with a configuration service running on the Admin Server (the Traffic Manager-based service used to provide the Admin UI), so the same security considerations apply:

- REST requests are authenticated using HTTP Basic Auth.
- REST traffic over HTTPS is automatically encrypted using SSL. Traffic over HTTP is not encrypted, so should only be used inside a secure environment or to/from localhost.
- The Traffic Manager Admin Server authenticates itself with its SSL certificate, which is generally self-signed. You might need to ensure that your REST application accepts self-signed certificates, or install a trusted SSL certificate in your Traffic Manager.
- REST requests are authenticated using the same user credentials as defined in the
  Administration Server. Individual object access is synonymous with page access in the Admin
  UI. For example, if a user wishes to view and manipulate pool objects, they must have been
  granted access to pools on the access permissions page.

# **Supported HTTP Methods**

The REST service supports three primary HTTP methods for accessing and modifying data in the Traffic Manager configuration system:

- GET
- PUT
- DELETE

GET is used when making read-only requests for a resource, whereas PUT is used when updating existing data or adding new configuration objects. DELETE is used when you wish to completely remove configuration objects from the Traffic Manager.

Each of these methods is discussed in more detail in the sections that follow.



The REST service additionally supports the POST method for uploading files to the Traffic Manager, specifically with respect to configuration backup TAR archive files. For more information, see Configuration Backups.

# **Requesting a Resource**

A client interacts with the Traffic Manager REST API by performing operations on its resources. An operation is distinguished by the HTTP method it uses and the path and query components of the associated URI. Some operations, however, are not applicable to every resource.

The GET method is used to retrieve the current representation of the resource it is used on. It does not alter the resource in any way or have any other side effects.

This is achieved by sending a HTTP GET request to the server with no body. The request must accept a response in JSON format only (by specifying an "Accept" header type of application/json), and authorization is provided using HTTP Basic Auth (for more details, see Authentication). Such a request resembles the following:

```
GET /api/tm/8.3/config/active/bandwidth/BWClass1 HTTP/1.1
Authorization: Basic YWRtaW46c2VjcmV0MTIz
Accept: application/json
```

If successful, the server returns a "200 OK" response code with the full resource in the response body. The above Bandwidth class example might produce the following output:

```
"properties": {
    "basic": {
        "maximum": 10000,
        "note": "This is my bandwidth class",
        "sharing": "cluster"
     }
}
```

This is a JSON structure representing the configuration keys present in the requested bandwidth class object. In this case, it consists of a single "basic" section containing three key:value pairs. Other resource types might contain different or additional sections and corresponding keys.

# **Setting Configuration for a Resource**



This section does not apply to read-only resources such as SNMP counters or system information.

Changing data items in the Traffic Manager configuration system is achieved through a PUT request to a configuration type resource. This applies to either creating new resource items or updating the properties of an existing resource item.

When creating a new resource item, the request URI must contain the full path to the intended item, with the name being the final element of the path. For example, creating a new bandwidth class called "mynewclass" requires using the following URI:

/api/tm/8.3/config/active/bandwidth/mynewclass

For both creation and update operations, the request body must contain a representation of the resource properties in JSON format (with the appropriate body "Content-Type" header set). Partial updates to configuration resources can be performed by only including the properties that need to be altered. Other properties are left unchanged.



For PUT requests, ensure that the request body is encoded as UTF-8.

The REST service returns a "200 OK" response for a correctly updated configuration set, or "201 Created" for establishing a new configuration object of a particular resource type. In these cases, the full resource is returned as the response body. The only exception to this rule is when updating a raw file, which instead returns a "204 No Content" empty-body response.

You might want to exercise some care when creating or updating resources. The changes are permanent and no warning is given for existing configuration that is overridden. If you attempt to create a new resource where one of the same name already exists, you overwrite the properties of the existing record. It is recommended that you build such validation into your REST client application.

# **Removing Resources**



This section does not apply to read-only resources such as SNMP counters or system information.

A HTTP DELETE request for the full URI of a configuration item can be sent to the REST server to permanently remove it. On success, a "204 No Content" empty-body response is returned.

# **Further Aspects of the Resource Model**

# **Enumerated Types**

Some configuration keys can accept one or more of a pre-defined set of values. This is known as an enumerated key type, and the list of possible values (with long description) is provided in the reference guide later in this document.

# **Uploading Files**

Resources that represent real files (such as TrafficScript rules) can also be presented in a raw format, where the data returned is the contents of the file. The MIME type of the request payload should be set to application/octet-stream.

# **Custom Configuration Sets**

You can store and retrieve arbitrary name:value configuration pairs in the Traffic Manager configuration system using the REST API. This configuration is replicated across your cluster, and is only accessible through the REST API, SOAP API, and ZCLI.

To store a custom configuration, create an instance of the "custom" resource and set your name:value data to the "string\_lists" property. For example, to create a resource called "customdata", use the following URI:

```
https://myhost:9070/api/tm/8.3/config/active/custom/customdata
```

Set the request body to a JSON structure resembling the following:

}

Using this system, you can organize your custom configuration into logical groups, initially by an instance of the "custom" resource, and within this, by a name:value pair. Each value can itself be a single item or a list of items.

#### **Errors**

If the REST server is unable to handle a HTTP request, it returns a HTTP response with an appropriate HTTP error code. The response body is in JSON and contains a data structure describing the error with a unique identifier (separate to the numeric error code) and a description.

The unique identifier is made up of 2 parts:

```
{section}.{error type}
```

Some errors might provide additional formatted information, specified with an optional "error\_info" parameter. For example, the REST API uses this parameter to return per-property errors when a value fails validation. The following structure demonstrates the general form of an error:

```
"error": {
    "error_id": "{error identifier}",
    "error_text": "{error description}",
    "error_info": {error specific data structure, optional}
}
```

A validation error occurs when one or more of the properties within a configuration resource fail a validation check. The error\_info section then contains a sub-error for each property that failed validation. These sub-errors are like normal errors in that they contain an identifier (error\_id) and a human readable text description (error\_text):

```
}
}
```

# **Configuration Backups**

The REST service supports the ability to create new backup sets of your Traffic Manager configuration.

When a user creates a new backup in the Admin UI, the Traffic Manager copies the current configuration folder (\$ZEUSHOME/zxtm/conf) into a new backup directory under \$ZEUSHOME/zxtm/confarchive. The name of the backup directory reflects the name chosen in the Admin UI.

Each backup set is saved with a series of metadata files:

Filename	Purpose
DESCRIPTION	Description of the backup
NAME	Optional file containing the name of the backup
VERSION_ <version></version>	File to indicate the software version of the Traffic Manager used to create the backup. This file has no contents.
TIMESTAMP	File indicating when the backup was created.
PARTIAL	Indicates that the backup is a partial backup.

To learn more about configuration backups, see the Pulse Secure Virtual Traffic Manager: User's Guide.



The REST service exposes only the name and description metadata for your backups, although each listed file is still present in a backup archive on the Traffic Manager.

Backups are represented through the REST API as child resources of the System Information resource:

```
/api/tm/8.3/status/<tm>/backups/full
```

As with all System Information resources, you must specify the cluster member you want to interrogate (denoted by <tm> in the URI shown). Each child resource of this URI is named in accordance with the corresponding backup name.

#### **Listing Existing Backups**

To see the configuration backups currently stored in a Traffic Manager, perform a GET request for the backups parent resource:

```
/api/tm/8.3/status/<tm>/backups/full
```

If successful, the server returns a "200 OK" response code with the backup list in the response body:

```
"children": [{
    "name": "Backup 1",
    "href": "/api/tm/3.9/status/mytm/backups/full/Backup%201/"
}, {
    "name": "vTMBackup-May16",
    "href": "/api/tm/3.9/status/mytm/backups/full/vTMBackup-May16/"
}, {
    "name": "another backup",
    "href": "/api/tm/3.9/status/mytm/backups/full/another%20backup/"
}]
```

To observe the metadata for a specific backup, perform a GET request for a child name. For example, a request for /api/tm/8.3/status/<tm>/backups/full/vTMBackup-May16 might return the following JSON strucure in the response body:

```
{
    "properties": {
        "backup": {
            "description": "Backup for May 2016",
            "time_stamp": 1462445371,
            "version": "21.4"
        }
    }
}
```

#### **Creating a Backup**

To create a new backup, use an HTTP PUT request to the backups URI:

```
/api/tm/8.3/status/<tm>/backups/full/<backup name>
```

Set <backup\_name> as the name of the backup you want to create.

The request body must contain a JSON resource representing the backup, with an optional description:

```
{
    "properties": {
        "backup": {
            "description": "My vTM backup for today",
        }
    }
}
```

Set the Content-Type header to "application/json".

If your backup request is successful, the Traffic Manager returns a "201 Created" response with the full backup metadata in the response body. If the Traffic Manager cannot create the backup, the response contains an HTTP error and the body contains an explanation of why the backup was unsuccessful.

Make sure your backup name does not already exist. The Traffic Manager does not override existing backups and instead returns an error in the response.

#### **Restoring a Backup**

Restoring a backup means your current configuration is overwritten permanently and all unsaved changes are lost. Ivanti strongly recommends only performing the following procedure if you are sure of the results.

To restore a backup to be your current Traffic Manager configuration, send a PUT request with the name of the selected backup in the URI, with a "restore" argument:

```
/api/tm/8.3/status/<tm>/backups/full/MyBackup?restore
```

Set the request body to an empty properties structure, such as the following:

```
{
    "properties":{
    }
}
```

If your restore request is successful, the Traffic Manager returns a "200 OK" response with the backup metadata in the response body. If the Traffic Manager is unable to restore the backup, the response contains an HTTP error and the body contains an explanation of why the operation was unsuccessful.

#### **Downloading Backups**

To download a backup as a TAR archive file, perform a GET request with the name of the required backup appended to the base backups URI. For example:

```
/api/tm/8.3/status/<tm>/backups/full/MyBackup
```

Set the "Accept" header to "application/x-tar".

When the request is made, a TAR file will be generated, which will be streamed to the client.

Some backup clients are able to make the request, but cannot properly handle an application/x-tar response. In this case, Ivanti recommends a command line tool such as CURL. The following command is an example of how to download a backup with CURL:

```
curl -H "accept:application/x-tar"
    -u <username>:<password>
    http://<host>:<port>/api/tm/8.3/status/<tm>/backups/full/MyBackup > MyBackup.tar
```

#### **Uploading Backups**

To upload a configuration backup file to your Traffic Manager /confarchive directory, use an HTTP POST request to the base backups URI:

```
/api/tm/8.3/status/<tm>/backups/full
```

The name of the backup is not required in the URI; instead, the Traffic Manager uses the contents of the "NAME" file in the backup TAR archive file. Make sure the backup name does not already exist in the Traffic Manager backups list.

Before you send the request, attach your backup archive file and set the Content-Type header to "application/x-tar". The actual process of uploading or attaching the archive file depends on your REST client.

The REST service returns a "201 Created" response for a correctly uploaded configuration backup archive file. If the Traffic Manager is unable to upload the backup file, the response contains an HTTP error and the body contains an explanation of why the operation was unsuccessful.

# **Deleting Backups**

To delete a configuration backup, perform a DELETE request with the full URI of the backup you want to remove. For example, to remove a backup called "MyBackup", use the following URI:

/api/tm/8.3/status/<tm>/backups/full/MyBackup

If the request is successful, a "204 No Content" empty-body response is returned.

# **Traffic Manager UI Features**

# **Enabling and Disabling the API**

To enable or disable the REST service, click **System > Security > REST API** in the Traffic Manager Admin UI. You can additionally use this page to set the TCP port that the service listens on. The default port is 9070, however any unreserved port can be used here provided it does not conflict with other services already running on the Traffic Manager system. Click **Update** to apply any changes.

#### **ATTENTION**

The REST API is currently not available in conjunction with the Traffic Manager's Multi-Site Manager (MSM) feature. Attempts to enable the REST service whilst MSM is operational are denied. Equally, attempting to enable MSM whilst the REST service is running triggers an error. The current state of the Traffic Manager remains unchanged in either of these situations.

To manually restart the REST API service, click **System > Traffic Managers** and then, in the Software Restart section, click **Restart REST API...**. The Traffic Manager asks you to confirm the restart on the next screen. Note that any existing connections are lost while the service restarts.

# **Controlling Timeout Events**

The **System > Security > REST API** page provides a number of settings to control how the Traffic Manager responds to certain timeout events that occur through use of the REST API. These are:

Setting	Description
rest!auth_timeout	The timeout period, in seconds, for the REST Authentication cache. As REST does not include the concept of a "session", each request must include user and password credentials. These credentials are validated each time; however, to save requesting repeated external authentications for the same user (from the same IP address), a cache of recent authentications is maintained. This timeout is the maximum amount of time a given user's credentials can stay in the cache.

Setting	Description
	A setting of 0 (zero) disables the cache, forcing every REST request to be authenticated as it is received. However, this affects the performance of the API.
	(Default: 120 seconds)
rest!replulltime	This is the <i>lull time</i> for configuration replication using REST.
	This is the time, in seconds, of inactivity through the REST API before configuration replication starts. Increasing this value delays configuration replication among a cluster of Traffic Managers.
	(Default: 5 seconds)
rest!repabstime	This is the absolute timeout prior to configuration replication using REST.
	This is the longest time, in seconds, before configuration replication using REST starts, regardless of activity through the API.
	(Default: 20 seconds)
rest!reptimeout	The configuration replication duration timeout using REST.  This is the time, in seconds, allowed for the process of configuration
	replication to complete. On a system with slow cluster communications or a very large configuration, increasing this value improves replication reliability.
	(Default: 10 seconds)

# Configuring the IP Addresses That the REST API Listens On

**System > Security > REST API** contains a setting, rest!bindips, that can be used to control the IP address(es) that the REST API listens on for connections. This can be a space-separated or commaseparated list of IPv4 or IPv6 addresses. Alternatively, it can contain an entry of "\*", in which case the REST API listens on all IP addresses.

If you configure the Traffic Manager to use a management IP address during initial configuration, rest!bindips defaults to this same IP address. You can, however, override this later with a separate IP address or list of IP addresses specific to the REST API.

#### **ATTENTION**

rest!bindips is a machine-specific setting and is not included in the cluster configuration that is replicated out to joining Traffic Manager instances. If you intend to join an unrestricted Traffic Manager into a cluster that has been previously configured to use a management IP address, you must ensure rest!bindips is set on the new instance before you join the cluster to avoid exposing unintended access.

The addresses that are bound to are listed in the error log. Addresses to which the REST API cannot be bound are also logged. If no addresses can be bound, the REST API shuts down.

# **Restricting Access to Trusted Users**

In addition to username/password access, click **System > Security > Restricting Access** to further restrict access to the administrative capabilities of your Traffic Manager system to a set of trusted IP addresses, CIDR subnets, or DNS wildcards. Access to the REST API is also affected by this capability.

# **Log Messages in the Traffic Manager**

#### The Event Log

A number of specific API-related messages might be found in the Traffic Manager event log under certain conditions:

- "REST API started: https://<URI>"
  - Raised when the REST Daemon starts.
- "REST API is shutting down"
  - Raised when the REST Daemon closes down.
- "On IPv6 host but cannot set unspecified ip address to ::"
  - Raised when the REST Daemon can't set itself up to listen on the IPv6 wildcard address.
- "Could not open Traffic Manager PID file for read: <error>"

Raised when REST Daemon can't identify the Traffic Manager PID, and so can't signal it to reload its config after a change has been made via the REST API.

"Could not open Traffic Manager PID file: <error>"

Raised when REST Daemon can't identify the Traffic Manager PID, and so can't signal it to reload its config after a change has been made via the REST API.

"Failed to write to audit log: <error>"

Raised when the REST Daemon can't add lines to the audit log.

#### The Audit Log

The audit log records login attempts, configuration changes, and user logouts. It also records changes made using the Traffic Manager Control API, and through the Traffic Manager Command-Line Interface (CLI). Configuration changes made through the REST API follow the same behavior.

In addition to the typical configuration messages entered into the audit log, the Traffic Manager also provides the ability to track user activity in the REST API. It does this by grouping REST request/response exchanges made in close succession from a given user into a "session".

The Traffic Manager logs the first request in a group of one or more requests from a particular user/ip address combination in the audit log as a "session start". Requests received after the initial request are deemed to be part of the same user session. Then, after a specified timeout interval since the most recent request was received from the same user, a "session end" is logged.

# **Examples and Use-Cases**

This chapter provides examples and use-cases for the REST API.

## **Typical Usage**

#### **ATTENTION**

The following examples are developed to work with version 8.3 of the Traffic Manager REST API. Ivanti makes no warranty as to their suitability for older versions.

The following code samples demonstrate how to interact with the REST API for a variety of purposes. The examples are based on Perl using the "REST::Client" module to handle the connections to the Traffic Manager REST daemon.

For further information on REST::Client, see the CPAN Web site: www.cpan.org.

A typical Perl client connection might resemble the following:

```
#!/usr/bin/perl

use REST::Client;
use strict;

# Set up the connection
my $client = REST::Client->new();
$client->setHost( 'https://myhost:9070' );
$client->addHeader( 'Authorization', 'Basic YWRtaW46am9iYmll' );
$client->addHeader( 'Content-Type', 'application/json' );

# Perform a HTTP GET on this URI
$client->GET( '/api/tm/8.3/config/active' );

# Print out the response body
print $client->responseContent();
```

In the above example, a new connection is established to the REST service on the Traffic Manager "myhost" on port 9070.

The setHost() function allows us to set up a definitive hostname and port to which all requests are made. This is an optional feature, and the full hostname can be supplied when making the actual request if multiple hosts are required.

Two HTTP headers can be added here, one to provide Basic Auth authentication and the other to provide a declaration of the Content Type when making PUT requests. In the majority of cases, the content type is "application/json", apart from transactions involving raw files where it is necessary to use "application/octet-stream".

A GET request is sent to the REST service with a target of the resource URI as the supplied argument. Typically, the above script outputs a JSON structure showing the Traffic Manager resource tree at the top level:

```
"children": [{
        "name": "rules",
        "href": "/api/tm/8.3/config/active/rules/"
}, {
        "name": "actions",
        "href": "/api/tm/8.3/config/active/actions/"
},
        ...
    (truncated)
        ...
{
        "name": "auth",
        "href": "/api/tm/8.3/config/active/auth/"
}]
```



Each of the following examples make use of a further Perl module "JSON" in order to encode and decode between the JSON string used by REST::Client and a native Perl structure. This is done to simplify the parsing algorithm within the script. Further information regarding the JSON Perl module can be found at the CPAN Web site: www.cpan.org.

## **Listing Running Virtual Servers**

In this example, we collect data on stored virtual servers by querying the "vservers" resource and identifying which ones are enabled (running).

The code structure is as follows:

- Instantiate a new REST Client object.
- Specify the hostname and port of the REST service to which all requests are to be directed.

- Add required HTTP headers for authentication and content type.
- Send a GET request for the "vservers" resource in order to return a list of all Virtual Servers on the system.
- Check the response body, and decode from JSON into a Perl structure. This value is a hash ref.
- Identify the "children" hash key, and iterate through the array to which it points.
- Each array item contains a hash of "name" and "href" associative values.
- Using the "name" value, perform a new GET request to return the full configuration for this named virtual server resource.
- Again, using the decoded JSON response body, identify the Boolean value of the "enabled" key
  in the "basic" configuration section. If it is "true", this virtual server is running so print it's name
  to STDOUT.

#### **ATTENTION**

This script does not contain any error checking in order to best demonstrate the basic functionality. It is strongly recommended you incorporate return value checking and other validation mechanisms as appropriate.

```
#!/usr/bin/perl

use REST::Client;
use JSON;
use strict;

# Set up the connection
my $client = REST::Client->new();
$client->setHost( 'https://myhost:9070' );
$client->addHeader( 'Authorization', 'Basic YWRtaW46am9iYmll' );
$client->addHeader( 'Content-Type', 'application/json' );

# Request a list of all virtual servers
client->GET( '/api/tm/8.3/config/active/vservers' );

# Decode response into a perl structure for easy parsing
my $response = decode_json( $client->responseContent() );

# Obtain a reference to the children array
my $vsArrayRef = $response->{children};
```

```
# For each VS, make a request for its configuration and
# check the Boolean value of the 'enabled' key
foreach my $vs ( @$vsArrayRef ) {
   my $vsName = $vs->{name};
   $client->GET( "/api/tm/8.3/config/active/vservers/$vsName" );
   my $vsConfig = decode_json( $client->responseContent() );
   if( $vsConfig->{properties}->{basic}->{enabled} eq "true" ) {
        # Print the name of this matched VS
        print "$vsn\n";
   }
}
```

The expected output of a script such as this would be:

```
$ ./listVS.pl
Main Website
Intranet
Support Site
```

## Adding a Node to a Pool

Provisioning systems can dynamically deploy applications across servers, perhaps in reaction to increased server load. This example demonstrates an application that modifies the nodes that a pool balances traffic to.

The code structure is as follows:

- Instantiate a new REST Client object.
- Specify the hostname and port of the REST service to which all requests are to be directed.
- Add required HTTP headers for authentication and content type.
- Send a GET request for the pool that the new node is added to. Check the response body, and decode from JSON into a Perl structure. This value is a hash ref.
- The new node must be added to the table of existing nodes before writing the data back to the pool resource. Failing to do this results in the existing table being overwritten with a single row containing the new node. Each of the subkeys associated with the node have default values and do not need to be specified.

- Re-encode the Perl structure into JSON and pass as an argument to the PUT request (using the pool name URI as the target).
- In this example, the script performs a check on the response code to ensure any problems are reported back (where the response code is not 200 OK).
- There is an optional portion of code at the end to iterate through the stored node table to ensure that the new node name appears.

```
#!/usr/bin/perl -w
use REST::Client;
use JSON;
use strict;
# Set up the connection
my $client = REST::Client->new();
$client->setHost( 'http://localhost:9070' );
$client->addHeader( 'Authorization', 'Basic YWRtaW46am9iYmll' );
$client->addHeader( 'Content-Type', 'application/json');
# Our pool and new node details
my $poolName = "WebPool";
my $newNode = { "node" => "www3.pulsesecure.net:80" };
# Get the config for the pool in question
$client->GET( "/api/tm/8.3/config/active/pools/$poolName" );
my $poolConfig = decode json( $client->responseContent() );
# Find the existing nodes table (a hashref), and add our new node
my $nodesRef = $poolConfig->{properties}->{basic}->{nodes table};
push @$nodesRef, $newNode;
# Re-encode as a JSON string
my $poolStr = encode json( $poolConfig );
# Now send a PUT request to the REST service
$client->PUT( "/api/tm/8.3/config/active/pools/$poolName",
              $poolStr );
# Print out the response code if we were NOT successful
if( $client->responseCode() ne '200' ) {
```

```
die "FAILED with HTTP code: " . $client->responseCode();
}

# We're done! Verify that the node has been added
$client->GET( "/api/tm/8.3/config/active/pools/$poolName" );
$poolConfig = decode_json( $client->responseContent() );
print "Stored nodes for pool '$poolName':\n";
foreach my $tablerow ( @{$poolConfig->{properties}->{basic}->{nodes_table}} ) {
    print "$tablerow->{node}\n";
}
```

The expected output of a script such as this would be:

```
$ ./addNode.pl
Stored nodes for pool 'WebPool':
www1.pulsesecure.net:80
www2.pulsesecure.net:80
www3.pulsesecure.net:80
```

## **Resource Model Reference**

This chapter provides a complete reference listing for the Traffic Manager REST API resource model.

#### **About the Resource Model Reference**

This chapter lists all the configuration, counter, and information resources available through the REST API model.

Each section relates to a specific resource and lists its name, description, unique URI path, and a table of properties.

For each property, you can find the description and data type. Additional information is provided where applicable, such as default value, permitted values (for enumerated types), and SNMP counter name. For Table-type properties, a list of the Primary and Sub keys is provided.

The path to use in your URIs is listed for each resource. For example, the URI path for a virtual server configuration resource is "virtual\_servers", so to address a stored virtual server named "foo", you would use:

```
/api/tm/8.3/config/active/virtual servers/foo
```

### **Getting Information About the Structure of Resources**

To obtain information about the structure of resources through the REST API itself, use the "metadata" query string argument with any request URI. For example:

```
https://<host>:<port>/api/tm/8.3/config/active/virtual_servers?metadata
https://<host>:<port>/api/tm/8.3/config/active/virtual_servers/foo?metadata
https://<host>:<port>/api/tm/8.3/status/local_tm/statistics/pools/mypool?metadata
https://<host>:<port>/api/tm/8.3/status/myvtm/state?metadata
```

You can append ?metadata to a resource type ("/virtual\_servers") or to an instance of a resource ("/virtual\_servers/foo"). The Traffic Manager returns the relevant details in a "metadata" element in the JSON response. For example:

The response contains resource level metadata, along with a "properties" element. This follows the same structure as a typical "properties" element, with sections and properties. All properties contain values for the "description", "type", and "default" value. The default value matches the type of the property.

## **Configuration Resources**

### **Action Program**

URI Endpoint: /api/tm/8.3/config/active/action\_programs

This is a program or script that can be referenced and used by actions of type 'Program'

Property	Description
There are no properties to display for this resource.	

#### **Admin SSL Trusted Certificate**

URI Endpoint: /api/tm/8.3/config/active/ssl/admin\_cas

The conf/ssl/admin\_cas directory contains SSL certificate authority certificates (CAs) and certificate revocation lists (CRLs) which can be used when validating connections made by the admin server for user authentication. CAs and CRLs can be managed under the Catalogs > SSL > Admin CAs and CRLs section of the Admin Server UI or by using functions under the Catalog.SSL.AdminCertificateAuthorities section of the SOAP API and CLI.

	Property	Description
There are no properties to display for this resource.		

## **Alerting Action**

URI Endpoint: /api/tm/8.3/config/active/actions

A response to an event occurring in your traffic manager. An example of an action might be sending an email or writing a line to a log file.

Property	Description
	A description of the action.
note	Type: FreeformString
note	Required: false
	Default value: <none></none>
	Maximum length in bytes of a message sent to the remote syslog.  Messages longer than this will be truncated before they are sent.
syslog_msg_len_limit	• Type: UInt
	Required: false
	Default value: "2048"
	How long the action can run for before it is stopped automatically (set to 0 to disable timeouts).
timeout	• Type: UInt
	Required: false
	Default value: "60"
	The action type.
	Type: Enum(String)
type	Required: true
type	Default value: <none></none>
	Permitted values:
	"email": E-Mail

Property	Description
	"log": Log to File
	"program": Program
	"soap": SOAP Callback
	"syslog": Log to Syslog
	"trap": SNMP Notify or Trap
	Enable or disable verbose logging for this action.
	Type: Boolean
verbose	Required: false
	Default value: false
Properties for the "email" sect	ion:
	The e-mail address from which messages will appear to originate.
from	Type: String
ITOTTI	Required: false
	Default value: "vTM@%hostname%"
	The SMTP server to which messages should be sent. This must be a valid IPv4 address or resolvable hostname (with optional port).
server	Type: String
	Required: false
	Default value: <none></none>
	A set of e-mail addresses to which messages will be sent.
+-	Type: Set(String)
to	Required: false
	Default value: <none></none>

Property	Description
Properties for the "log" section:	
	The full path of the file to log to. The text %zeushome% will be replaced with the location where the software is installed.
file	Type: String
	Required: false
	Default value: <none></none>
Properties for the "program" s	ection:
	A table containing arguments and argument values to be passed to the event handling program.
	• Type: Table
	Required: false
	Primary key:
arguments	<ul> <li>name (String): The name of the argument to be passed to the event handling program. (Required)</li> </ul>
	Sub keys:
	<ul> <li>value (String): The value of the argument to be passed to the event handling program. (Required)</li> </ul>
	<ul> <li>description (String): A description for the argument provided to the program.</li> </ul>
	The program to run.
program	Type: String
program	Required: false
	Default value: <none></none>
Properties for the "soap" secti	on:
additional_data	Additional information to send with the SOAP call.

Property	Description
	Type: String
	Required: false
	Default value: <none></none>
	The password for HTTP basic authentication.
	Type: Password
password	Required: false
	Default value: <none></none>
	The address of the server implementing the SOAP interface (For example, https://example.com).
proxy	Type: String
	Required: false
	Default value: <none></none>
	Username for HTTP basic authentication. Leave blank if you do not wish to use authentication.
username	Type: String
	Required: false
	Default value: <none></none>
Properties for the "syslog" section:	
sysloghost	The host and optional port to send syslog messages to (if empty, messages will be sent to localhost).
	Type: String
	Required: false
	Default value: <none></none>
Properties for the "trap" section	on:

Property	Description
	The authentication password for sending a Notify over SNMPv3.  Blank to send unauthenticated traps.
auth_password	Type: Password
	Required: false
	Default value: <none></none>
	The community string to use when sending a Trap over SNMPv1 or a Notify over SNMPv2c.
community	Type: String
	Required: false
	Default value: <none></none>
	The hash algorithm for SNMPv3 authentication.
	Type: Enum(String)
	Required: false
hash_algorithm	Default value: "md5"
	Permitted values:
	"md5": MD5
	"sha1": SHA-1
	The encryption password to encrypt a Notify message for SNMPv3.  Requires that authentication also be configured. Blank to send unencrypted traps.
priv_password	Type: Password
	Required: false
	Default value: <none></none>
traphost	The hostname or IPv4 address and optional port number that should receive traps.

Property	Description
	Type: String
	Required: false
	Default value: <none></none>
	The SNMP username to use to send the Notify over SNMPv3.
1120 110 0 100 0	Type: String
username	Required: false
	Default value: <none></none>
	The SNMP version to use to send the Trap/Notify.
	Type: Enum(String)
	Required: false
	Default value: "snmpv1"
version	Permitted values:
	"snmpv1": SNMPv1
	"snmpv2c": SNMPv2c
	"snmpv3": SNMPv3

## **Aptimizer Application Scope**

URI Endpoint: /api/tm/8.3/config/active/aptimizer/scopes

Application scopes define criteria that match URLs to specific logical web applications hosted by a virtual server.

Property	Description
canonical_hostname	If the hostnames for this scope are aliases of each other, the canonical hostname will be used for requests to the server.

Property	Description
	Type: String
	Required: false
	Default value: <none></none>
	The hostnames to limit acceleration to.
hastnames	Type: Set(String)
hostnames	Required: false
	Default value: <none></none>
	The root path of the application defined by this application scope.
root	Type: String
	Required: false
	Default value: "/"

### **BGP Neighbor**

URI Endpoint: /api/tm/8.3/config/active/bgpneighbors

The conf/bgpneighbors directory contains configuration files for BGP neighbors. The name of a file is the name of the neighbor configuration that it defines. BGP neighbors can be managed under the System > Fault Tolerance > BGP Neighbors section of the Admin UI, or by using functions under the BGPNeighbors section of the SOAP API and CLI.

Property	Description
	The IP address of the BGP neighbor
address	Type: String
address	Required: false
	Default value: <none></none>

Property	Description
advertisement_interval	The minimum interval between the sending of BGP routing updates to neighbors. Note that as a result of jitter, as defined for BGP, the interval during which no advertisements are sent will be between 75% and 100% of this value.  • Type: UInt  • Required: false  • Default value: "5"
as_number	The AS number for the BGP neighbor  Type: UInt Required: false
authentication_password	<ul> <li>Default value: "65534"</li> <li>The password to be used for authentication of sessions with neighbors</li> <li>Type: String</li> <li>Required: false</li> <li>Default value: <none></none></li> </ul>
holdtime	The period after which the BGP session with the neighbor is deemed to have become idle - and requires re-establishment - if the neighbor falls silent.  • Type: UInt  • Required: false  • Default value: "90"
keepalive	The interval at which messages are sent to the BGP neighbor to keep the mutual BGP session established.  • Type: UInt

Property	Description
	Required: false
	Default value: "30"
machines	The traffic managers that are to use this neighbor
	Type: Set(String)
	Required: false
	Default value: <none></none>

#### **Bandwidth Class**

URI Endpoint: /api/tm/8.3/config/active/bandwidth

A Bandwidth class, which can be assigned to a virtual server or pool in order to limit the number of bytes per second used by inbound or outbound traffic.

Property	Description
	The maximum bandwidth to allocate to connections that are associated with this bandwidth class (in kbits/second).
maximum	Type: UInt
	Required: false
	Default value: "10000"
note	A description of this bandwidth class.
	Type: FreeformString
	Required: false
	Default value: <none></none>
sharing	The scope of the bandwidth class.
	Type: Enum(String)

Property	Description
	Required: false
	Default value: "cluster"
	Permitted values:
	"cluster": Bandwidth is shared across all traffic managers
	"connection": Each connection can use the maximum rate
	"machine": Bandwidth is shared per traffic manager

### **Cloud Credentials**

URI Endpoint: /api/tm/8.3/config/active/cloud\_api\_credentials

Cloud credentials used in cloud API calls

Property	Description
api_server	The vCenter server hostname or IP address.  • Type: String  • Required: false
cloud_api_timeout	Default value: <none>  The traffic manager creates and destroys nodes via API calls. This setting specifies (in seconds) how long to wait for such calls to</none>
	complete.  • Type: UInt
	<ul><li>Required: false</li><li>Default value: "200"</li></ul>

Property	Description
cred1	The first part of the credentials for the cloud user. Typically this is some variation on the username concept.
	Type: String
	Required: false
	Default value: <none></none>
	The second part of the credentials for the cloud user. Typically this is some variation on the password concept.
cred2	Type: Password
	Required: false
	Default value: <none></none>
	The third part of the credentials for the cloud user. Typically this is some variation on the authentication token concept.
cred3	Type: Password
	Required: false
	Default value: <none></none>
	The script to call for communication with the cloud API.
script	Type: String
script	Required: false
	Default value: <none></none>
update_interval	The traffic manager will periodically check the status of the cloud through an API call. This setting specifies the interval between such updates.
	Type: UInt
	Required: false
	Default value: "30"

## **Custom configuration set**

URI Endpoint: /api/tm/8.3/config/active/custom

Custom configuration sets store arbitrary named values. These values can be read by SOAP or REST clients.

Property	Description
string_lists	This table contains named lists of strings
	Type: Table
	Required: false
	Primary key:
	name (String): Name of list (Required)
	Sub keys:
	<ul> <li>value (List(String)): Named list of user-specified strings.</li> <li>(Required)</li> </ul>

### **DNS Zone**

URI Endpoint: /api/tm/8.3/config/active/dns\_server/zones

The conf/dnsserver/zones/ file contains zone metadata

Property	Description
origin	The domain origin of this Zone.
	Type: String
	Required: true
	Default value: <none></none>
zonefile	The Zone File encapsulated by this Zone.
	Type: String

Property	Description
	Required: true
	Default value: <none></none>

#### **DNS Zone File**

URI Endpoint: /api/tm/8.3/config/active/dns\_server/zone\_files

The conf/dnsserver/zonefiles/ directory contains files that define DNS zones.

Property	Description
There are no properties to display for this resource.	

## **Event Type**

URI Endpoint: /api/tm/8.3/config/active/event\_types

Configuration that ties actions to a set of events that trigger them.

Property	Description
	The actions triggered by events matching this event type, as a list of action references.
actions	Type: List(Reference(config-event-action))
	Required: false
	Default value: <none></none>
built_in	If set to Yes this indicates that this configuration is built-in (provided as part of the software) and must not be deleted or edited.
	Type: Boolean
	Required: false
	Default value: false

Property	Description
note	A description of this event type.
	Type: FreeformString
	Required: false
	Default value: <none></none>
Properties for the "cloudcrede	ntials" section:
	Cloud credentials event tags
	Type: List(String)
event_tags	Required: false
	Default value: <none></none>
	Cloud credentials object names
	Type: List(String)
objects	Required: false
	Default value: <none></none>
Properties for the "config" sec	tion:
	Configuration file event tags
	Type: List(String)
event_tags	Required: false
	Default value: <none></none>
Properties for the "faulttolerance" section:	
	Fault tolerance event tags
event_tags	Type: List(String)
	Required: false
	Default value: <none></none>

Property	Description
Properties for the "general" section:	
	General event tags
avent tags	Type: List(String)
event_tags	Required: false
	Default value: <none></none>
Properties for the "glb" section	n:
	GLB service event tags
event tags	Type: List(String)
event_tags	Required: false
	Default value: <none></none>
	GLB service object names
	Type: List(String)
objects	Required: false
	Default value: <none></none>
Properties for the "java" section:	
	Java event tags
	Type: List(String)
event_tags	Required: false
	Default value: <none></none>
Properties for the "licensekeys" section:	
	License key event tags
event_tags	Type: List(String)
	Required: false

Property	Description
	Default value: <none></none>
	License key object names
	Type: List(String)
objects	Required: false
	Default value: <none></none>
Properties for the "locations" s	section:
	Location event tags
ovent tags	Type: List(String)
event_tags	Required: false
	Default value: <none></none>
	Location object names
ahiasta	Type: List(String)
objects	Required: false
	Default value: <none></none>
Properties for the "monitors" s	section:
	Monitor event tags
ovent tags	Type: List(String)
event_tags	Required: false
	Default value: <none></none>
objects	Monitors object names
	Type: List(String)
	Required: false
	Default value: <none></none>

Property	Description
Properties for the "pools" section:	
	Pool key event tags
	Type: List(String)
event_tags	Required: false
	Default value: <none></none>
	Pool object names
alais an	Type: List(String)
objects	Required: false
	Default value: <none></none>
Properties for the "protection"	section:
	Service protection class event tags
event tags	Type: List(String)
event_tags	Required: false
	Default value: <none></none>
	Service protection class object names
ahiaata	Type: List(String)
objects	Required: false
	Default value: <none></none>
Properties for the "rules" section:	
event_tags	Rule event tags
	Type: List(String)
	Required: false
	Default value: <none></none>

Property	Description
	Rule object names
	Type: List(String)
objects	Required: false
	Default value: <none></none>
Properties for the "slm" section	n:
	SLM class event tags
event togs	Type: List(String)
event_tags	Required: false
	Default value: <none></none>
	SLM class object names
-1-1	Type: List(String)
objects	Required: false
	Default value: <none></none>
Properties for the "ssl" section	
	SSL event tags
avent to a	Type: List(String)
event_tags	Required: false
	Default value: <none></none>
Properties for the "sslhw" section:	
event_tags	SSL hardware event tags
	Type: List(String)
	Required: false
	Default value: <none></none>

Property	Description	
Properties for the "trafficscript	Properties for the "trafficscript" section:	
	TrafficScript event tags	
	Type: List(String)	
event_tags	Required: false	
	Default value: <none></none>	
Properties for the "vservers" se	ection:	
	Virtual server event tags	
avent to as	Type: List(String)	
event_tags	Required: false	
	Default value: <none></none>	
	Virtual server object names	
alais an	Type: List(String)	
objects	Required: false	
	Default value: <none></none>	
Properties for the "zxtms" sect	ion:	
	Traffic manager event tags	
event tags	Type: List(String)	
event_tags	Required: false	
	Default value: <none></none>	
objects	Traffic manager object names	
	Type: List(String)	
	Required: false	
	Default value: <none></none>	

### **Extra File**

URI Endpoint: /api/tm/8.3/config/active/extra\_files

A user-uploaded file. Such files can be used in TrafficScript code using the resource.get function.

Property	Description
There are no properties to display for this resource.	

### **GLB Service**

URI Endpoint: /api/tm/8.3/config/active/glb\_services

A global load balancing service is used by a virtual server to modify DNS requests in order load balance data across different GLB locations.

Property	Description
algorithm	Defines the global load balancing algorithm to be used.  Type: Enum(String)  Required: false  Default value: "hybrid"  Permitted values:  "chained": Sends traffic to one location at a time, until that location fails where the next one in the chain is used.  "geo": Distributes traffic based solely on the geographic location of each client.  "hybrid": Distribute traffic based on both the load and geographic location.  "load": Distributes traffic based on the current load to each location.

Property	Description
	"round_robin": Distributes traffic by assigning each request to a new location in turn. Over a period of time, all locations will receive the same number of requests.  "weighted_random": Distributes traffic in a random way, but according to a weighted policy defined by individual location weights
all_monitors_needed	Do all monitors assigned to a location need to report success in order for it to be considered healthy?  Type: Boolean Required: false Default value: true
autorecovery	The last location to fail will be available as soon as it recovers.  Type: Boolean  Required: false  Default value: true
chained_auto_failback	<ul> <li>Enable/Disable automatic failback mode.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>
chained_location_order	The locations this service operates for and defines the order in which locations fail.  Type: List(String)  Required: false  Default value: <none></none>

Property	Description
disable_on_failure	Locations recovering from a failure will become disabled.  Type: Boolean  Required: false  Default value: false
dnssec_keys	A table mapping domains to the private keys that authenticate them  Type: Table  Required: false  Primary key:  domain (String): A domain authenticated by the associated private keys. (Required)  Sub keys:  ssl_key (Set(String)): Private keys that authenticate the associated domain. (Required)
domains	The domains shown here should be a list of Fully Qualified Domain Names that you would like to balance globally. Responses from the back end DNS servers for queries that do not match this list will be forwarded to the client unmodified. Note: "*" may be used as a wild card.  • Type: Set(String)  • Required: false  • Default value: <none></none>
enabled	<ul> <li>Enable/Disable our response manipulation of DNS.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>

Property	Description
geo_effect	How much should the locality of visitors affect the choice of location used? This value is a percentage, 0% means that no locality information will be used, and 100% means that locality will always control which location is used. Values between the two extremes will act accordingly.  • Type: UInt
	Required: false
	Default value: "50"
	The response to be sent in case there are no locations available.
last_resort_response	Type: Set(String)
lust_resort_response	Required: false
	Default value: <none></none>
	This is the list of locations for which this service is draining. A location that is draining will never serve any of its service IP addresses for this domain. This can be used to take a location off-line.
location_draining	Type: Set(String)
	Required: false
	Default value: <none></none>
	Table containing location specific settings.
location_settings	• Type: Table
	Required: false
	Primary key:
	location (String): Location to which the associated settings apply. (Required)
	Sub keys:

Property	Description
	weight (UInt): Weight for this location, for use by the weighted random algorithm.
	<ul> <li>ips (Set(String)): The IP addresses that are present in a location. If the Global Load Balancer decides to direct a DNS query to this location, then it will filter out all IPs that are not in this list. (Required)</li> </ul>
	monitors (Set(String)): The monitors that are present in a location.
	Return all or none of the IPs under complete failure.
return inc on fail	Type: Boolean
return_ips_on_fail	Required: false
	Default value: true
	Response rules to be applied in the context of the service, in order, comma separated.
rules	Type: List(Reference(config-trafficscript))
	Required: false
	Default value: <none></none>
	The TTL for the DNS resource records handled by the GLB service.
441	Type: Int
ttl	Required: false
	Default value: "-1"
Properties for the "log" section	n:
enabled	Log connections to this GLB service?
	Type: Boolean
	Required: false

Property	Description
	Default value: false
filename	The filename the verbose query information should be logged to. Appliances will ignore this.
	Type: String
	Required: false
	Default value: "%zeushome%/zxtm/log/services/%g.log"
format	The format of the log lines.
	Type: String
	Required: false
	• Default value: "%t, %s, %l, %q, %g, %n, %d, %a"

# **Global Settings**

URI Endpoint: /api/tm/8.3/config/active/global\_settings

General settings that apply to every machine in the cluster.

Property	Description
accepting_delay	How often, in milliseconds, each traffic manager child process (that isn't listening for new connections) checks to see whether it should start listening for new connections.
	• Type: UInt
	Required: false
	Default value: "50"
afm_enabled	Is the application firewall enabled.
	Type: Boolean
	Required: false

Property	Description
	Default value: false
chunk_size	The default chunk size for reading/writing requests.
	Type: UInt
	Required: false
	Default value: "16384"
client_first_opt	Whether or not your traffic manager should make use of TCP optimisations to defer the processing of new client-first connections until the client has sent some data.
	Type: Boolean
	Required: false
	Default value: false
cluster_identifier	Cluster identifier. Generally supplied by Services Director.
	Type: String
	Required: false
	Default value: <none></none>
license_servers	A list of license servers for FLA licensing. A license server should be specified as a <ip host="">:<port> pair.</port></ip>
	Type: Set(String)
	Required: false
	Default value: <none></none>
max_fds	The maximum number of file descriptors that your traffic manager will allocate.
	Type: UInt
	Required: false

Property	Description
	Default value: "1048576"
max_tcp_buff_mem	The maximum amount of memory allowed to be used to buffer network data in user space for all TCP connections. The TCP data buffered are either received from clients but before sending to pool nodes, or recevied from pool nodes but before sending to clients. This is specified as either a percentage of system RAM, 5% for example, or an absolute size such as 1024MB and 2GB. A numeric value without suffix MB, GB or % defaults to MB. A value of 800 means 800MB. A value of 0 means unlimited.
	Type: String
	Required: false
	Default value: <none></none>
monitor_memory_size	The maximum number of each of nodes, pools or locations that can be monitored. The memory used to store information about nodes, pools and locations is allocated at start-up, so the traffic manager must be restarted after changing this setting.
	Type: UInt
	Required: false
	Default value: "4096"
rate_class_limit	The maximum number of Rate classes that can be created.  Approximately 100 bytes will be pre-allocated per Rate class.
	Type: UInt
	Required: false
	Default value: "25000"
shared_pool_size	The size of the shared memory pool used for shared storage across worker processes (e.g. bandwidth shared data). This is specified as either a percentage of system RAM, 5% for example, or an absolute size such as 10MB.

Property	Description
	Type: String
	Required: false
	Default value: "10MB"
slm_class_limit	The maximum number of SLM classes that can be created.  Approximately 100 bytes will be pre-allocated per SLM class.
	• Type: UInt
	Required: false
	Default value: "1024"
so_rbuff_size	The size of the operating system's read buffer. A value of 0 (zero) means to use the OS default; in normal circumstances this is what should be used.
	Type: UInt
	Required: false
	Default value: <none></none>
so_wbuff_size	The size of the operating system's write buffer. A value of 0 (zero) means to use the OS default; in normal circumstances this is what should be used.
	Type: UInt
	Required: false
	Default value: <none></none>
socket_optimizations	Whether or not the traffic manager should use potential network socket optimisations. If set to auto, a decision will be made based on the host platform.
	Type: Enum(String)
	Required: false

Property	Description
	Default value: "auto"
	Permitted values:
	"auto": Decide based on local platform
	"no": Disable socket optimizations
	"yes": Enable socket optimizations
	The maximum number of Traffic IP Groups that can be created.
	Type: UInt
tip_class_limit	Required: false
	Default value: "10000"
Properties for the "admin" sec	tion:
	Whether or not the admin server, the internal control port and the config daemon honor the Fallback SCSV to protect connections against downgrade attacks.
honor_fallback_scsv	Type: Boolean
	Required: false
	Default value: true
ssl3_allow_rehandshake	Whether or not SSL3/TLS re-handshakes should be supported for admin server and internal connections.
	Type: Enum(String)
	Required: false
	Default value: "rfc5746"
	Permitted values:
	"always": Always allow
	"never": Never allow

Property	Description
	"rfc5746": Only if client uses RFC 5746 (Secure Renegotiation Extension)
	"safe": Allow safe re-handshakes
	The SSL ciphers to use for admin server and internal connections.  For information on supported ciphers see the online help.
ssl3_ciphers	Type: String
	Required: false
	Default value: <none></none>
	The length in bits of the Diffie-Hellman key for ciphers that use Diffie-Hellman key agreement for admin server and internal connections.
	Type: Enum(UInt)
	Required: false
	Default value: "dh_2048"
ssl3_diffie_hellman_key_ length	Permitted values:
	"dh_1024": Use 1024 bit keys for Diffie- Hellman ciphers.
	"dh_2048": Use 2048 bit keys for Diffie- Hellman ciphers.
	"dh_3072": Use 3072 bit keys for Diffie- Hellman ciphers.
	"dh_4096": Use 4096 bit keys for Diffie- Hellman ciphers.

Property	Description
ssl3_min_rehandshake_	If SSL3/TLS re-handshakes are supported on the admin server, this defines the minimum time interval (in milliseconds) between handshakes on a single SSL3/TLS connection that is permitted. To disable the minimum interval for handshakes the key should be set to the value 0.
interval	Type: UInt
	Required: false
	Default value: "1000"
	The SSL elliptic curve preference list for admin and internal connections. The named curves P256, P384 and P521 may be configured.
ssl_elliptic_curves	Type: List(String)
	Required: false
	Default value: <none></none>
	Whether or not SSL3 and TLS1 use one-byte fragments as a BEAST countermeasure for admin server and internal connections.
ssl_insert_extra_fragment	Type: Boolean
	Required: false
	Default value: false
ssl_max_handshake_ message_size	The maximum size (in bytes) of SSL handshake messages that the admin server and internal connections will accept. To accept any size of handshake message the key should be set to the value 0.
	Type: UInt
	Required: false
	Default value: "10240"

Property	Description
ssl_signature_algorithms	The SSL signature algorithms preference list for admin and internal connections using TLS version 1.2 or higher. For information on supported algorithms see the online help.
	Type: String
	Required: false
	Default value: <none></none>
	Whether or not SSL3 support is enabled for admin server and internal connections.
support_ssl3	Type: Boolean
	Required: false
	Default value: false
	Whether or not TLS1.0 support is enabled for admin server and internal connections.
support_tls1	Type: Boolean
	Required: false
	Default value: true
support_tls1_1	Whether or not TLS1.1 support is enabled for admin server and internal connections.
	Type: Boolean
	Required: false
	Default value: true
support_tls1_2	Whether or not TLS1.2 support is enabled for admin server and internal connections.
	Type: Boolean
	Required: false

Property	Description
1 - 7	·
	Default value: true
support_tls1_3	Whether or not TLS1.3 support is enabled for admin server and internal connections.
	Type: Boolean
	Required: false
	Default value: true
Properties for the "appliance"	section:
	The password used to protect the bootloader. An empty string means there will be no protection.
bootloader_password	Type: Password
	Required: false
	Default value: <none></none>
return_path_routing_ enabled	Whether or not the traffic manager will attempt to route response packets back to clients via the same route on which the corresponding request arrived. Note that this applies only to the last hop of the route - the behaviour of upstream routers cannot be altered by the traffic manager.
	Type: Boolean
	Required: false
	Default value: false
Properties for the "aptimizer" section:	
max_dependent_fetch_size	The maximum size of a dependent resource that can undergo Web Accelerator optimization. Any content larger than this size will not be optimized. Units of KB and MB can be used, no postfix denotes bytes. A value of 0 disables the limit.
	Type: String

Property	Description
	Required: false
	Default value: "2MB"
max_original_content_ buffer_size	The maximum size of unoptimized content buffered in the traffic manager for a single backend response that is undergoing Web Accelerator optimization. Responses larger than this will not be optimized. Note that if the backend response is compressed then this setting pertains to the compressed size, before Web Accelerator decompresses it. Units of KB and MB can be used, no postfix denotes bytes. Value range is 1 - 128MB.
	Type: String
	Required: false
	Default value: "2MB"
	The period of time (in seconds) after which a previous failure will no longer count towards the watchdog limit.
watchdog_interval	• Type: UInt
	Required: false
	Default value: "300"
watchdog_limit	The maximum number of times the Web Accelerator sub-process will be started or restarted within the interval defined by the aptimizer!watchdog_interval setting. If the process fails this many times, it must be restarted manually from the Diagnose page. Zero means no limit.
	Type: UInt
	Required: false
	Default value: "3"
Properties for the "auditlog" se	ection:
via_eventd	Whether to mirror the audit log to EventD.

Property	Description	
	Type: Boolean	
	Required: false	
	Default value: false	
	Whether to output audit log message to the syslog.	
	Type: Boolean	
via_syslog	Required: false	
	Default value: false	
Properties for the "auth" section	on:	
	Lifetime in seconds of cryptographic keys used to decrypt SAML SP sessions stored externally (client-side).	
saml_key_lifetime	Type: UInt	
	Required: false	
	Default value: "86400"	
	Rotation interval in seconds for cryptographic keys used to encrypt SAML SP sessions stored externally (client-side).	
saml_key_rotation_interval	Type: UInt	
•	Required: false	
	Default value: "14400"	
Properties for the "autoscaler" section:		
verbose	Whether or not detailed messages about the autoscaler's activity are written to the error log.	
	Type: Boolean	
	Required: false	
	Default value: false	

Property	Description	
Properties for the "bgp" section:		
as_number	The number of the BGP AS in which the traffic manager will operate.  Must be entered in decimal.	
	Type: UInt	
	Required: false	
	Default value: "65534"	
	Whether BGP Route Health Injection is enabled	
enabled	Type: Boolean	
enabled	Required: false	
	Default value: false	
Properties for the "cluster_con	nms" section:	
allow_update_default	The default value of allow_update for new cluster members. If you have cluster members joining from less trusted locations (such as cloud instances) this can be set to false in order to make them effectively "read-only" cluster members.	
2.1,	Type: Boolean	
	Required: false	
	Default value: true	
allowed_update_hosts	The hosts that can contact the internal administration port on each traffic manager. This should be a list containing IP addresses, CIDR IP subnets, and localhost; or it can be set to all to allow any host to connect.	
	Type: List(String)	
	Required: false	
	Default value: "all"	

Property	Description
state_sync_interval	How often to propagate the session persistence and bandwidth information to other traffic managers in the same cluster. Set this to 0 (zero) to disable propagation. Note that a cluster using "unicast" heartbeat messages cannot turn off these messages.  • Type: UInt  • Required: false  • Default value: "3"
state_sync_timeout	The maximum amount of time to wait when propagating session persistence and bandwidth information to other traffic managers in the same cluster. Once this timeout is hit the transfer is aborted and a new connection created.  • Type: UInt  • Required: false  • Default value: "6"
Properties for the "connection	" section:
idle_connections_max	The maximum number of unused HTTP keepalive connections with back-end nodes that the traffic manager should maintain for re-use. Setting this to 0 (zero) will cause the traffic manager to auto-size this parameter based on the available number of file-descriptors.  • Type: UInt
	<ul><li>Required: false</li><li>Default value: <none></none></li></ul>
idle_timeout	How long an unused HTTP keepalive connection should be kept before it is discarded.  • Type: UInt
idie_timeout	<ul><li>Type: UInt</li><li>Required: false</li></ul>

Property	Description
	Default value: "10"
listen_queue_size	The listen queue size for managing incoming connections. It may be necessary to increase the system's listen queue size if this value is altered. If the value is set to 0 then the default system setting will be used.  • Type: UInt
	Required: false
	Default value: <none></none>
max_accepting	Number of processes that should accept new connections. Only this many traffic manager child processes will listen for new connections at any one time. Setting this to 0 (zero) will cause your traffic manager to select an appropriate default value based on the architecture and number of CPUs.
	Type: UInt
	Required: false
	Default value: <none></none>
multiple_accept	Whether or not the traffic manager should try to read multiple new connections each time a new client connects. This can improve performance under some very specific conditions. However, in general it is recommended that this be set to 'false'.
	Type: Boolean
	Required: false
	Default value: false
udp_read_multiple	Whether or not the traffic manager should try to read multiple UDP packets from clients each time the kernel reports data received from clients. This can improve performance for the situation with high UDP traffic throughput from clients to the traffic manager.  Therefore, in general it is recommended that this be set to 'Yes'.

Property	Description
	Type: Boolean
	Required: false
	Default value: true
Properties for the "dns" sectio	n:
	Maximum Time To Live (expiry time) for entries in the DNS cache.
	Type: UInt
max_ttl	Required: false
	Default value: "86400"
	Minimum Time To Live (expiry time) for entries in the DNS cache.
	Type: UInt
min_ttl	Required: false
	Default value: "86400"
	Expiry time for failed lookups in the DNS cache.
	Type: UInt
negative_expiry	Required: false
	Default value: "60"
	Maximum number of entries in the DNS cache.
size	Type: UInt
	Required: false
	Default value: "10867"
	Timeout for receiving a response from a DNS server.
timeout	Type: UInt
	Required: false

Property	Description
	Default value: "12"
Properties for the "ec2" section:	
	Deprecated: This key is unused. Amazon authentication credentials are now extracted from IAM Roles assigned to an EC2 instance.
access_key_id	Type: String
	Required: false
	Default value: <none></none>
	The maximum amount of time requests to the AWS Query API can take before timing out.
awstool_timeout	Type: UInt
	Required: false
	Default value: "10"
	URL for the EC2 metadata server, http://169.254.169.254/latest/meta-data for example.
metadata_server	Type: String
	Required: false
	Default value: <none></none>
	URL for the Amazon EC2 endpoint, https://ec2.amazonaws.com/ for example.
query_server	Type: String
47=	Required: false
	Default value: <none></none>
secret_access_key	Deprecated: This key is unused. Amazon authentication credentials are now extracted from IAM Roles assigned to an EC2 instance.
	Type: Password

Property	Description
	Required: false
	Default value: <none></none>
verify_query_server_cert	Whether to verify Amazon EC2 endpoint's certificate using CA(s) present in SSL Certificate Authorities Catalog.
	Type: Boolean
	Required: false
	Default value: false
Properties for the "eventing" s	ection:
	The minimum length of time that must elapse between alert emails being sent. Where multiple alerts occur inside this timeframe, they will be retained and sent within a single email rather than separately.
mail_interval	Type: UInt
	Required: false
	Default value: "30"
max_attempts	The number of times to attempt to send an alert email before giving up.
	Type: UInt
	Required: false
	Default value: "10"
Properties for the "fault_tolerance" section:	
arp_count	The number of ARP packets a traffic manager should send when an IP address is raised.
	Type: UInt
	Required: false
	Default value: "10"

Property	Description
auto_failback	Whether or not traffic IPs automatically move back to machines that have recovered from a failure and have dropped their traffic IPs.
	Type: Boolean
	Required: false
	Default value: true
	Configure the delay of automatic failback after a previous failover event. This setting has no effect if autofailback is disabled.
autofailback_delay	Type: UInt
	Required: false
	Default value: "10"
	How long the traffic manager should wait for status updates from any of the traffic manager's child processes before assuming one of them is no longer servicing traffic.
child_timeout	Type: UInt
	Required: false
	Default value: "5"
	The IP addresses used to check front-end connectivity. The text %gateway% will be replaced with the default gateway on each system. Set this to an empty string if the traffic manager is on an Intranet with no external connectivity.
frontend_check_ips	Type: Set(String)
	Required: false
	Default value: "%gateway%"
heartbeat_method	The method traffic managers should use to exchange cluster
	heartbeat messages.  • Type: Enum(String)

Property	Description
	Required: false
	Default value: "unicast"
	Permitted values:
	"multicast": multicast
	"unicast": unicast
	The interval between unsolicited periodic IGMP Membership Report messages for Multi-Hosted Traffic IP Groups.
igmp_interval	Type: UInt
	Required: false
	Default value: "30"
	The frequency, in milliseconds, that each traffic manager machine should check and announce its connectivity.
monitor_interval	Type: UInt
	Required: false
	Default value: "500"
monitor_timeout	How long, in seconds, each traffic manager should wait for a response from its connectivity tests or from other traffic manager machines before registering a failure.
	Type: UInt
	Required: false
	Default value: "5"
	The multicast address and port to use to exchange cluster heartbeat messages.
multicast_address	Type: String
	Required: false

Property	Description
	Default value: "239.100.1.1:9090"
	The unicast UDP port to use to exchange cluster heartbeat messages.
unicast_port	Type: UInt
	Required: false
	Default value: "9090"
	Whether or not cluster heartbeat messages should only be sent and received over the management network.
use_bind_ip	Type: Boolean
	Required: false
	Default value: false
	Whether or not a traffic manager should log all connectivity tests.  This is very verbose, and should only be used for diagnostic purposes.
verbose	Type: Boolean
	Required: false
	Default value: false
Properties for the "fips" section:	
enabled	Enable FIPS Mode (requires software restart).
	Type: Boolean
	Required: false
	Default value: false
Properties for the "ftp" section	):

Property	Description	
data_bind_low	Whether or not the traffic manager should permit use of FTP data connection source ports lower than 1024. If No the traffic manager can completely drop root privileges, if Yes some or all privileges may be retained in order to bind to low ports.  Type: Boolean Required: false Default value: false	
Properties for the "glb" section	n:	
	Write a message to the logs for every DNS query that is load balanced, showing the source IP address and the chosen datacenter.	
verbose	Type: Boolean	
	Required: false	
	Default value: false	
Properties for the "historical_activity" section:		
	Number of days to store historical traffic information, if set to 0 the data will be kept indefinitely.	
keep_days	• Type: UInt	
	Required: false	
	Default value: "90"	
Properties for the "ip" section:		
appliance_returnpath	A table of MAC address/network interface to IP address mappings for each router where return path routing is required.	
	Type: Table	
	Required: false	
	Primary key:	

Property	Description
	mac (String): The MAC address/network interface of a router the software is connected to. (Required)  Sub-keys:
	<ul> <li>Sub keys:</li> <li>ipv4 (String): The MAC address/network interface to IPv4 address mapping of a router the software is connected to. The value is the IPv4 address, the * (asterisk) in the key name is the MAC address and an optional network interface name, for example, 00:50:56:a6:24:3d or 00:50:56:a6:24:3d#eth0.</li> </ul>
	<ul> <li>ipv6 (String): The MAC address/network interface to IPv6 address mapping of a router the software is connected to. The value is the IPv6 address, the * (asterisk) in the key name is the MAC address and an optional network interface name, for example, 00:50:56:a6:24:3d or 00:50:56:a6:24:3d#eth0.</li> </ul>
Properties for the "java" sectio	n:
classpath	<ul> <li>CLASSPATH to use when starting the Java runner.</li> <li>Type: String</li> <li>Required: false</li> <li>Default value: <none></none></li> </ul>
command	Java command to use when starting the Java runner, including any additional options.  Type: String  Required: false  Default value: "java -server"

Property	Description
enabled	Whether or not Java support should be enabled. If this is set to No, then your traffic manager will not start any Java processes. Java support is only required if you are using the TrafficScript java.run() function.  • Type: Boolean
	Required: false
	Default value: false
	Java library directory for additional jar files. The Java runner will load classes from any .jar files stored in this directory, as well as the * jar files and classes stored in traffic manager's catalog.
lib	Type: String
	Required: false
	Default value: <none></none>
max_connections	Maximum number of simultaneous Java requests. If there are more than this many requests, then further requests will be queued until the earlier requests are completed. This setting is per-CPU, so if your traffic manager is running on a machine with 4 CPU cores, then each core can make this many requests at one time.
	Type: UInt
	Required: false
	Default value: "256"
	Default time to keep a Java session.
session_age	Type: UInt
	Required: false
	Default value: "86400"
Properties for the "kerberos"	section:

Property	Description
verbose	Whether or not a traffic manager should log all Kerberos related activity. This is very verbose, and should only be used for diagnostic purposes.
	Type: Boolean
	Required: false
	Default value: false
Properties for the "log" section	n:
	The minimum severity of events/alerts that should be logged to disk. INFO will log all events; a higher severity setting will log fewer events. More fine-grained control can be achieved using events and actions.
	Type: Enum(UInt)
	Required: false
error_level	Default value: "info"
_	Permitted values:
	"fatal": Only fatal errors are logged
	"info": All events are logged to disk
	"serious": Only serious errors or worse
	"warn": Only warnings and errors are logged
flush_time	How long to wait before flushing the request log files for each virtual server.
	Type: UInt
	Required: false
	Default value: "5"

Property	Description
log_file	The file to log event messages to.
	Type: String
	Required: false
	Default value: "%zeushome%/zxtm/log/errors"
	The maximum number of connection errors logged per second when connection error reporting is enabled.
rate	Type: UInt
	Required: false
	Default value: "50"
	How long to wait before re-opening request log files, this ensures that log files will be recreated in the case of log rotation.
reopen	• Type: UInt
	Required: false
	Default value: "30"
	The minimum time between log messages for log intensive features such as SLM.
time	Type: UInt
	Required: false
	Default value: "60"
Properties for the "log_export" section:	
auth_hec_token	The HTTP Event Collector token to use for HTTP authentication with a Splunk server.
	Type: String
	Required: false

Property	Description
	Default value: <none></none>
	The HTTP authentication method to use when exporting log entries.
	Type: Enum(String)
	Required: false
	Default value: "none"
auth_http	Permitted values:
	"basic": Basic (Username and Password)
	"none": None
	"splunk": Splunk (HEC token)
	The password to use for HTTP basic authentication.
auth password	Type: Password
auth_password	Required: false
	Default value: <none></none>
	The username to use for HTTP basic authentication.
auth usarnama	Type: String
auth_username	Required: false
	Default value: <none></none>
enabled	Monitor log files and export entries to the configured endpoint.
	Type: Boolean
	Required: false
	Default value: false
endpoint	The URL to which log entries should be sent. Entries are sent using HTTP(S) POST requests.

Property	Description
	Type: String
	Required: false
	Default value: <none></none>
	The number of seconds after which HTTP requests sent to the configured endpoint will be considered to have failed if no response is received. A value of 0 means that HTTP requests will not time out.
request_timeout	Type: UInt
	Required: false
	Default value: "30"
	Whether the server certificate should be verified when connecting to the endpoint. If enabled, server certificates that do not match the server name, are self-signed, have expired, have been revoked, or that are signed by an unknown CA will be rejected.
tls_verify	Type: Boolean
	Required: false
	Default value: true
Properties for the "ospfv2" section:	
	The OSPF area in which the traffic manager will operate. May be entered in decimal or IPv4 address format.
area	Type: String
	Required: false
	Default value: "0.0.0.1"
area_type	The type of OSPF area in which the traffic manager will operate. This must be the same for all routers in the area, as required by OSPF.
	Type: Enum(String)

Property	Description
	Required: false
	Default value: "normal"
	Permitted values:
	"normal": Normal area
	"nssa": Not So Stubby Area (RFC3101)
	"stub": Stub area
	OSPFv2 authentication key ID. If set to 0, which is the default value, the key is disabled.
authentication_key_id_a	Type: UInt
	Required: false
	Default value: <none></none>
	OSPFv2 authentication key ID. If set to 0, which is the default value, the key is disabled.
authentication_key_id_b	Type: UInt
	Required: false
	Default value: <none></none>
authentication_shared_	OSPFv2 authentication shared secret (MD5). If set to blank, which is the default value, the key is disabled.
	Type: String
secret_a	Required: false
	Default value: <none></none>
authentication_shared_	OSPFv2 authentication shared secret (MD5). If set to blank, which is the default value, the key is disabled.
secret_b	Type: String

Property	Description
	Required: false
	Default value: <none></none>
	The number of seconds before declaring a silent router down.
deed internal	Type: UInt
dead_interval	Required: false
	Default value: "40"
	Whether OSPFv2 Route Health Injection is enabled
an alala d	Type: Boolean
enabled	Required: false
	Default value: false
	The interval at which OSPF "hello" packets are sent to the network.
halla interval	Type: UInt
hello_interval	Required: false
	Default value: "10"
Properties for the "protection"	section:
conncount_size	The amount of shared memory reserved for an inter-process table of combined connection counts, used by all Service Protection classes that have per_process_connection_count set to No. The amount is specified as an absolute size, eg 20MB.
	Type: String
	Required: false
	Default value: "20MB"
Properties for the "recent_connections" section:	

Property	Description
max_per_process	How many recently closed connections each traffic manager process should save. These saved connections will be shown alongside currently active connections when viewing the Connections page. You should set this value to 0 in a benchmarking or performance-critical environment.
-1 -1	• Type: UInt
	Required: false
	Default value: "500"
retain_time	The amount of time for which snapshots will be retained on the Connections page.
	• Type: UInt
	Required: false
	Default value: "60"
snapshot_size	The maximum number of connections each traffic manager process should show when viewing a snapshot on the Connections page.  This value includes both currently active connections and saved connections. If set to 0 all active and saved connection will be displayed on the Connections page.
	• Type: UInt
	Required: false
	Default value: "500"
Properties for the "remote_licensing" section:	
comm_channel_enabled	Whether to create a Communications Channel agent to send and receive messages from the Services Director Registration Server.  This will be disabled when performing self-registration with a Services Director which does not support this feature.
	Type: Boolean

Property	Description
	Required: false
	Default value: true
	The port number the Services Director instance is using for access to the traffic manager Communications Channel.
comm_channel_port	Type: UInt
	Required: false
	Default value: "8102"
	The Owner of a Services Director instance, used for self-registration.
2000	Type: String
owner	Required: false
	Default value: <none></none>
	The secret associated with the Owner.
	Type: String
owner_secret	Required: false
	Default value: <none></none>
	The auto-accept Policy ID that this instance should attempt to use.
	Type: String
policy_id	Required: false
	Default value: <none></none>
registration_server	A Services Director address for self-registration. A registration server should be specified as a <ip host="">:<port> pair.</port></ip>
	Type: String
	Required: false

Property	Description
	Default value: <none></none>
server_certificate	The certificate of a Services Director instance, used for self-registration.
	Type: String
	Required: false
	Default value: <none></none>
Properties for the "rest_api" se	ection:
	The length of time after a successful request that the authentication of a given username and password will be cached for an IP address. A setting of 0 disables the cache forcing every REST request to be authenticated which will adversely affect performance.
auth_timeout	Type: UInt
	Required: false
	Default value: "120"
	Whether or not the REST service is enabled.
	Type: Boolean
enabled	Required: false
	Default value: true
	The maximum allowed length in bytes of a HTTP request's headers.
	Type: UInt
http_max_header_length	Required: false
	Default value: "4096"
maxfds	Maximum number of file descriptors that the REST API will allocate.  The REST API must be restarted for a change to this setting to take effect.

Property	Description
	Type: UInt
	Required: false
	Default value: "1048576"
	Configuration changes will be replicated across the cluster after this period of time, regardless of whether additional API requests are being made.
replicate_absolute	• Type: UInt
	Required: false
	Default value: "20"
	Configuration changes made via the REST API will be propagated across the cluster when no further API requests have been made for this period of time.
replicate_lull	• Type: UInt
	Required: false
	Default value: "5"
	The period of time after which configuration replication across the cluster will be cancelled if it has not completed.
replicate_timeout	• Type: UInt
	Required: false
	Default value: "10"
Properties for the "security" section:	
login_banner	Banner text displayed on the Admin Server login page and before logging in to appliance SSH servers.
	Type: FreeformString
	Required: false

Property	Description
	Default value: <none></none>
login_banner_accept	Whether or not users must explicitly agree to the displayed login_banner text before logging in to the Admin Server.
	Type: Boolean
	Required: false
	Default value: false
	The number of seconds before another login attempt can be made after a failed attempt.
login_delay	Type: UInt
	Required: false
	Default value: "4"
	The number of sequential failed login attempts that will cause a user account to be suspended. Setting this to 0 disables this feature. To apply this to users who have never successfully logged in, track_unknown_users must also be enabled.
max_login_attempts	Type: UInt
	Required: false
	Default value: <none></none>
max_login_external	Whether or not usernames blocked due to the max_login_attempts limit should also be blocked from authentication against external services (such as LDAP and RADIUS).
	Type: Boolean
	Required: false
	Default value: false
max_login_suspension_time	The number of minutes to suspend users who have exceeded the max_login_attempts limit.

Property	Description
	Type: UInt
	Required: false
	Default value: "15"
	Whether or not to allow the same character to appear consecutively in passwords.
password_allow_	Type: Boolean
consecutive_chars	Required: false
	Default value: true
	The maximum number of times a password can be changed in a 24-hour period. Set to 0 to disable this restriction.
password_changes_per_day	Type: UInt
	Required: false
	Default value: <none></none>
	Minimum number of alphabetic characters a password must contain. Set to 0 to disable this restriction.
password_min_alpha_chars	Type: UInt
	Required: false
	Default value: <none></none>
password_min_length	Minimum number of characters a password must contain. Set to 0 to disable this restriction.
	Type: UInt
	Required: false
	Default value: <none></none>
password_min_numeric_ chars	Minimum number of numeric characters a password must contain.  Set to 0 to disable this restriction.

Property	Description
	Type: UInt
	Required: false
	Default value: <none></none>
	Minimum number of special (non-alphanumeric) characters a password must contain. Set to 0 to disable this restriction.
password_min_special_chars	Type: UInt
	Required: false
	Default value: <none></none>
	Minimum number of uppercase characters a password must contain. Set to 0 to disable this restriction.
password_min_uppercase_ chars	• Type: UInt
	Required: false
	Default value: <none></none>
	The number of times a password must have been changed before it can be reused. Set to 0 to disable this restriction.
password_reuse_after	• Type: UInt
	Required: false
	Default value: <none></none>
post_login_banner	Banner text to be displayed on the appliance console after login.
	Type: String
	Required: false
	Default value: <none></none>

Property	Description
track_unknown_users	Whether to remember past login attempts from usernames that are not known to exist (should be set to false for an Admin Server accessible from the public Internet). This does not affect the audit log.  Type: Boolean Required: false Default value: false
	Banner text to be displayed on all Admin Server pages.
ui_page_banner	<ul><li>Type: String</li><li>Required: false</li></ul>
	Default value: <none></none>
Properties for the "session" se	ction:
asp_cache_size	The maximum number of entries in the ASP session persistence cache. This is used for storing session mappings for ASP session persistence. Approximately 100 bytes will be pre-allocated per entry.
	<ul><li>Type: UInt</li><li>Required: false</li></ul>
	Default value: "32768"
ip_cache_expiry	IP session persistence cache expiry time in seconds. A session will not be reused if the time since it was last used exceeds this value. 0 indicates no expiry timeout.
	Type: UInt
	Required: false
	Default value: <none></none>

Property	Description
	The maximum number of entries in the IP session persistence cache. This is used to provide session persistence based on the source IP address. Approximately 100 bytes will be pre-allocated per entry.
ip_cache_size	• Type: UInt
	Required: false
	Default value: "32768"
	J2EE session persistence cache expiry time in seconds. A session will not be reused if the time since it was last used exceeds this value. 0 indicates no expiry timeout.
j2ee_cache_expiry	Type: UInt
	Required: false
	Default value: <none></none>
j2ee_cache_size	The maximum number of entries in the J2EE session persistence cache. This is used for storing session mappings for J2EE session persistence. Approximately 100 bytes will be pre-allocated per entry.
	Type: UInt
	Required: false
	Default value: "32768"
ssl_cache_size	The maximum number of entries in the SSL session persistence cache. This is used to provide session persistence based on the SSL session ID. Approximately 200 bytes will be pre-allocated per entry.
	Type: UInt
	Required: false
	Default value: "32768"

Property	Description
universal_cache_expiry	Universal session persistence cache expiry time in seconds. A session will not be reused if the time since it was last used exceeds this value. 0 indicates no expiry timeout.  • Type: UInt
	<ul><li>Required: false</li><li>Default value: <none></none></li></ul>
	The maximum number of entries in the global universal session persistence cache. This is used for storing session mappings for universal session persistence. Approximately 100 bytes will be preallocated per entry.
universal_cache_size	• Type: UInt
	Required: false
	Default value: "32768"
Properties for the "snmp" sect	ion:
user_counters	The number of user defined SNMP counters. Approximately 100 bytes will be pre-allocated at start-up per user defined SNMP counter.
	• Type: UInt
	Required: false
	Default value: "10"
Properties for the "soap" section:	
idle_minutes	The number of minutes that the SOAP server should remain idle before exiting. The SOAP server has a short startup delay the first time a SOAP request is made, subsequent SOAP requests don't have this delay.
	• Type: UInt
	Required: false

Property	Description
	Default value: "10"
Properties for the "ssl" section	
	Whether or not SSL/TLS re-handshakes should be supported. Enabling support for re-handshakes can expose services to Man-in-the-Middle attacks. It is recommended that only "safe" handshakes be permitted, or none at all.
	Type: Enum(String)
	Required: false
allow rehandshake	Default value: "safe"
allow_rehandshake	Permitted values:
	"always": Always allow
	"never": Never allow
	"rfc5746": Only if client uses RFC 5746 (Secure Renegotiation Extension) "safe": Allow safe re-handshakes
	Whether or not the SSL server session cache is enabled, unless overridden by virtual server settings.
cache_enabled	Type: Boolean
cache_enabled	Required: false
	Default value: true
cache_expiry	How long the SSL session IDs for SSL decryption should be stored for.
	Type: UInt
	Required: false
	Default value: "1800"

Property	Description
cache_per_virtualserver	Whether an SSL session created by a given virtual server can only be resumed by a connection to the same virtual server.
	Type: Boolean
	Required: false
	Default value: true
	How many entries the SSL session ID cache should hold. This cache is used to cache SSL sessions to help speed up SSL handshakes when performing SSL decryption. Each entry will allocate approximately 1.75kB of metadata.
cache_size	Type: UInt
	Required: false
	Default value: "6151"
	The SSL/TLS cipher suites preference list for SSL/TLS connections, unless overridden by virtual server or pool settings. For information on supported cipher suites see the online help.
cipher_suites	Type: String
	Required: false
	Default value: <none></none>
client_cache_enabled	Whether or the SSL client cache will be used, unless overridden by pool settings.
	Type: Boolean
	Required: false
	Default value: true
client_cache_expiry	How long in seconds SSL sessions should be stored in the client cache for, by default. Servers returning session tickets may also provide a lifetime hint, which will be used if it is less than this value.

Property	Description
	Type: UInt
	Required: false
	Default value: "14400"
client_cache_size	How many entries the SSL client session cache should hold, per child. This cache is used to cache SSL sessions to help speed up SSL handshakes when performing SSL encryption. Each entry will require approx 100 bytes of memory plus space for either an SSL session id or an SSL session ticket, which may be as small as 16 bytes or may be as large as a few kilobytes, depending upon the server behavior.
	Type: UInt
	Required: false
	Default value: "1024"
	Whether or not session tickets, including TLS >= 1.3 PSKs, may be requested and stored in the SSL client cache.
client_cache_tickets_enabled	Type: Boolean
	Required: false
	Default value: true
crl_mem_size	How much shared memory to allocate for loading Certificate Revocation Lists. This should be at least 3 times the total size of all CRLs on disk. This is specified as either a percentage of system RAM, 1% for example, or an absolute size such as 10MB.
	Type: String
	Required: false
	Default value: "5MB"
diffie_hellman_modulus_size	The size in bits of the modulus for the domain parameters used for cipher suites that use finite field Diffie-Hellman key agreement.

Property	Description
	Type: Enum(UInt)
	Required: false
	Default value: "dh_2048"
	Permitted values:
	"dh_1024": 1024 bit modulus
	"dh_2048": 2048 bit modulus
	"dh_3072": 3072 bit modulus
	"dh_4096": 4096 bit modulus
elliptic_curves	The SSL/TLS elliptic curve preference list for SSL/TLS connections using TLS version 1.0 or higher, unless overridden by virtual server or pool settings. For information on supported curves see the online help.
	Type: List(String)
	Required: false
	Default value: <none></none>
honor_fallback_scsv	Whether or not ssl-decrypting Virtual Servers honor the Fallback SCSV to protect connections against downgrade attacks.
	Type: Boolean
	Required: false
	Default value: true
	Whether or not SSL3 and TLS1 use one-byte fragments as a BEAST countermeasure.
insert_extra_fragment	Type: Boolean
	Required: false

Property	Description
	Default value: false
	Whether SSL connection key logging should be available via the ssl.sslkeylogline() TrafficScript function. If this setting is disabled then ssl.sslkeylogline() will always return the empty string.
log_keys	Type: Boolean
	Required: false
	Default value: false
	The maximum size (in bytes) of SSL handshake messages that SSL connections will accept. To accept any size of handshake message the key should be set to the value 0.
max_handshake_message_ size	Type: UInt
	Required: false
	Default value: "10240"
	Whether or not TLS 1.3 middlebox compatibility mode as described in RFC 8446 appendix D.4 will be used in connections to pool nodes, unless overridden by pool settings.
middlebox_compatibility	Type: Boolean
	Required: false
	Default value: true
min_rehandshake_interval	If SSL3/TLS re-handshakes are supported, this defines the minimum time interval (in milliseconds) between handshakes on a single SSL3/TLS connection that is permitted. To disable the minimum interval for handshakes the key should be set to the value 0.
	Type: UInt
	Required: false
	Default value: "1000"

Property	Description
ocsp_cache_size	The maximum number of cached client certificate OCSP results stored. This cache is used to speed up OCSP checks against client certificates by caching results. Approximately 1040 bytes are preallocated per entry.
	Type: UInt
	Required: false
	Default value: "2048"
	How long to wait before refreshing requests on behalf of the store of certificate status responses used by OCSP stapling, if we don't have an up-to-date OCSP response.
ocsp_stapling_default_ refresh_interval	Type: UInt
	Required: false
	Default value: "60"
	Maximum time to wait before refreshing requests on behalf of the store of certificate status responses used by OCSP stapling. (0 means no maximum.)
ocsp_stapling_maximum_ refresh_interval	Type: UInt
	Required: false
	Default value: "864000"
ocsp_stapling_mem_size	How much shared memory to allocate for the store of certificate status responses for OCSP stapling. This should be at least 2kB times the number of certificates configured to use OCSP stapling. This is specified as either a percentage of system RAM, 1% for example, or an absolute size such as 10MB.
	Type: String
	Required: false
	Default value: "1MB"

Property	Description
ocsp_stapling_time_ tolerance	How many seconds to allow the current time to be outside the validity time of an OCSP response before considering it invalid.  • Type: UInt  • Required: false  • Default value: "30"
ocsp_stapling_verify_ response	Whether the OCSP response signature should be verified before the OCSP response is cached.  Type: Boolean Required: false Default value: false
signature_algorithms	The SSL/TLS signature algorithms preference list for SSL/TLS connections using TLS version 1.2 or higher, unless overridden by virtual server or pool settings. For information on supported algorithms see the online help.  Type: String Required: false Default value: <none></none>
support_ssl3	Whether or not SSL3 support is enabled.  Type: Boolean Required: false Default value: false
support_tls1	<ul> <li>Whether or not TLS1.0 support is enabled.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: true</li> </ul>

Property	Description
support_tls1_1	Whether or not TLS1.1 support is enabled.
	Type: Boolean
	Required: false
	Default value: true
	Whether or not TLS1.2 support is enabled.
support_tls1_2	Type: Boolean
support_tis1_2	Required: false
	Default value: true
	Whether or not TLS1.3 support is enabled.
support_tls1_3	Type: Boolean
support_tis1_5	Required: false
	Default value: true
	Whether or not session tickets will be issued to and accepted from clients that support them, unless overridden by virtual server settings.
tickets_enabled	Type: Boolean
	Required: false
	Default value: true
tickets_reissue_policy	When an SSL session ticket will be reissued (ie when a new ticket will be generated for the same SSL session).
	Type: Enum(String)
	Required: false
	Default value: "never"
	Permitted values:

Property	Description
	"always": always
	"never": never
	The length of time for which an SSL session ticket will be accepted by a virtual server after the ticket is created. If a ticket is reissued (if ssl!tickets!reissue_policy is set to 'always') this time starts at the time when the ticket was reissued.
tickets_ticket_expiry	Type: UInt
	Required: false
	Default value: "14400"
tickets_ticket_key_expiry	The length of time for which an auto-generated SSL ticket key will be used to decrypt old session ticket, before being deleted from memory. This setting is ignored if there are any entries in the (REST-only) SSL ticket keys catalog.  • Type: UInt
	Required: false
	Default value: "86400"
tickets_ticket_key_rotation	The length of time for which an auto-generated SSL ticket key will be used to encrypt new session tickets, before a new SSL ticket key is generated. The ticket encryption key will be held in memory for ssl!tickets!ticket_key_expiry, so that tickets encrypted using the key can still be decrypted and used. This setting is ignored if there are any entries in the (REST-only) SSL ticket keys catalog.
	Type: UInt
	Required: false
	Default value: "14400"
tickets_time_tolerance	How many seconds to allow the current time to be outside the validity time of an SSL ticket before considering it invalid.

Property	Description	
	Type: UInt	
	Required: false	
	Default value: "30"	
	Whether the traffic manager should validate that SSL server certificates form a matching key pair before the certificate gets used on an SSL decrypting virtual server.	
validate_server_certificates_ catalog	Type: Boolean	
	Required: false	
	Default value: true	
Properties for the "ssl_hardware" section:		
accel	Whether or not the SSL hardware is an "accelerator" (faster than software). By default the traffic manager will only use the SSL hardware if a key requires it (i.e. the key is stored on secure hardware and the traffic manager only has a placeholder/identifier key). With this option enabled, your traffic manager will instead try to use hardware for all SSL decrypts.	
	Type: Boolean	
	Required: false	
	Default value: false	
azure_client_id	The client identifier used when accessing the Microsoft Azure Key Vault.	
	Type: String	
	Required: false	
	Default value: <none></none>	
azure_client_secret	The client secret used when accessing the Microsoft Azure Key Vault.	

Property	Description
	Type: Password
	Required: false
	Default value: <none></none>
	The URL for the REST API of the Microsoft Azure Key Vault.
arura vasilt sud	Type: String
azure_vault_url	Required: false
	Default value: <none></none>
	Whether or not the Azure Key Vault REST API certificate should be verified.
azure_verify_rest_api_cert	Type: Boolean
	Required: false
	Default value: true
	Print verbose information about the PKCS11 hardware security module to the event log.
driver_pkcs11_debug	Type: Boolean
	Required: false
	Default value: false
	The location of the PKCS#11 library for your SSL hardware if it is not in a standard location. The traffic manager will search the standard locations by default.
driver_pkcs11_lib	Type: String
	Required: false
	Default value: <none></none>
driver_pkcs11_slot_desc	The label of the SSL Hardware slot to use. Only required if you have multiple HW accelerator slots.

Property	Description
	Type: String
	Required: false
	Default value: <none></none>
	The type of SSL hardware slot to use.
	Type: Enum(String)
	Required: false
	Default value: "operator"
driver_pkcs11_slot_type	Permitted values:
	"module": Module Protected
	"operator": Operator Card Set
	"softcard": Soft Card
	The User PIN for the PKCS token (PKCS#11 devices only).
duivan alvas 11 vasan ais	Type: Password
driver_pkcs11_user_pin	Required: false
	Default value: <none></none>
failure_count	The number of consecutive failures from the SSL hardware that will be tolerated before the traffic manager assumes its session with the device is invalid and tries to log in again. This is necessary when the device reboots following a power failure.
	Type: UInt
	Required: false
	Default value: "5"
library	The type of SSL hardware to use. The drivers for the SSL hardware should be installed and accessible to the traffic manager software.

Property	Description
	Type: Enum(String)
	Required: false
	Default value: "none"
	Permitted values:
	"azure": Microsoft Azure Key Vault
	"none": None
	"pkcs11": PKCS#11
Properties for the "telemetry"	section:
	Allow the reporting of anonymized usage data for product improvement and customer support purposes.
enabled	Type: Boolean
	Required: false
	Default value: true
Properties for the "trafficscript	" section:
	The maximum amount of memory available to store TrafficScript data.local.set() information. This can be specified as a percentage of system RAM, 5% for example; or an absolute size such as 200MB.
data_local_size	Type: String
	Required: false
	Default value: "5%"
data_size	The maximum amount of memory available to store TrafficScript data.set() information. This can be specified as a percentage of system RAM, 5% for example; or an absolute size such as 200MB.
	Type: String
	Required: false

Property	Description
	Default value: "5%"
	Raise an event if a TrafficScript rule runs for more than this number of milliseconds in a single invocation. If you get such events repeatedly, you may want to consider re-working some of your TrafficScript rules. A value of 0 means no warnings will be issued.
execution_time_warning	Type: UInt
	Required: false
	Default value: "500"
max_instr	The maximum number of instructions a TrafficScript rule will run. A rule will be aborted if it runs more than this number of instructions without yielding, preventing infinite loops.
	Type: UInt
	Required: false
	Default value: "100000"
memory_warning	Raise an event if a TrafficScript rule requires more than this amount of buffered network data. If you get such events repeatedly, you may want to consider re-working some of your TrafficScript rules to use less memory or to stream the data that they process rather than storing it all in memory. This setting also limits the amount of data that can be returned by request.GetLine().
	Type: UInt
	Required: false
	Default value: "1048576"
regex_cache_size	The maximum number of regular expressions to cache in TrafficScript. Regular expressions will be compiled in order to speed up their use in the future.
	Type: UInt

Property	Description
	Required: false
	Default value: "57"
	The maximum number of ways TrafficScript will attempt to match a regular expression at each position in the subject string, before it aborts the rule and reports a TrafficScript error.
regex_match_limit	Type: UInt
	Required: false
	Default value: "10000000"
	The percentage of regex_match_limit at which TrafficScript reports a performance warning.
regex_match_warn_	Type: UInt
percentage	Required: false
	Default value: "5"
variable_pool_use	Allow the pool.use and pool.select TrafficScript functions to accept variables instead of requiring literal strings. Enabling this feature has the following effects1. Your traffic manager may no longer be able to know whether a pool is in use.2. Errors for pools that aren't in use will not be hidden.3. Some settings displayed for a Pool may not be appropriate for the type of traffic being managed.4. Pool usage information on the pool edit pages and config summary may not be accurate.5. Monitors will run for all pools (with this option disabled monitors will only run for Pools that are used).
	Type: Boolean
	Required: false
	Default value: false
Properties for the "transaction	_export" section:

Property	Description
enabled	Export metadata about transactions processed by the traffic manager to an external location.
	Type: Boolean
	Required: false
	Default value: false
	The endpoint to which transaction metadata should be exported.  The endpoint is specified as a hostname or IP address with a port.
endpoint	Type: String
	Required: false
	Default value: <none></none>
tls	Whether the connection to the specified endpoint should be encrypted.
	Type: Boolean
	Required: false
	Default value: true
tls_verify	Whether the server certificate presented by the endpoint should be verified, preventing a connection from being established if the certificate does not match the server name, is self-signed, is expired, is revoked, or has an unknown CA.
	Type: Boolean
	Required: false
	Default value: true
Properties for the "watchdog" section:	
timeout	The maximum time in seconds a process can fail to update its heartbeat, before the watchdog considers it to have stalled.

Property	Description
	Type: UInt
	Required: false
	Default value: "5"
Properties for the "web_cache"	" section:
avg_path_length	The estimated average length of the path (including query string) for resources being cached. An amount of memory equal to this figure multiplied by max_file_num will be allocated for storing the paths for cache entries. This setting can be increased if your web site makes extensive use of long URLs.
	Type: UInt
	Required: false
	Default value: "512"
disk	Whether or not to use a disk-backed (typically SSD) cache. If set to Yes cached web pages will be stored in a file on disk. This enables the traffic manager to use a cache that is larger than available RAM. The size setting should also be adjusted to select a suitable maximum size based on your disk space. Note that the disk caching is optimized for use with SSD storage.
	Type: Boolean
	Required: false
	Default value: false
disk_dir	If disk caching is enabled, this sets the directory where the disk cache file will be stored. The traffic manager will create a file called webcache.data in this location. Note that the disk caching is optimized for use with SSD storage.
	Type: String
	Required: false

Property	Description
	Default value: "%zeushome%/zxtm/internal"
	Maximum number of entries in the cache. Approximately 0.9 KB will be pre-allocated per entry for metadata, this is in addition to the memory reserved for the content cache and for storing the paths of the cached resources.
max_file_num	Type: UInt
	Required: false
	Default value: "10000"
max_file_size	Largest size of a cacheable object in the cache. This is specified as either a percentage of the total cache size, 2% for example, or an absolute size such as 20MB.
	Type: String
	Required: false
	Default value: "2%"
max_path_length	The maximum length of the path (including query string) for the resource being cached. If the path exceeds this length then it will not be added to the cache.
	Type: UInt
	Required: false
	Default value: "2048"
normalize_query	Enable normalization (lexical ordering of the parameterassignments) of the query string.
	Type: Boolean
	Required: false
	Default value: true

Property	Description
size	The maximum size of the HTTP web page cache. This is specified as either a percentage of system RAM, 20% for example, or an absolute size such as 200MB.
	Type: String
	Required: false
	Default value: "20%"
verbose	Add an X-Cache-Info header to every HTTP response, showing whether the request and/or the response was cacheable.
	Type: Boolean
	Required: false
	Default value: false

## **Kerberos Configuration File**

URI Endpoint: /api/tm/8.3/config/active/kerberos/krb5confs

A Kerberos krb5.conf file that provides the raw configuration for a Kerberos principal.

Property	Description
There are no properties to display for this resource.	

## **Kerberos Keytab**

URI Endpoint: /api/tm/8.3/config/active/kerberos/keytabs

A Kerberos keytab file contains credentials to authenticate as (a number of) Kerberos principals.

Property	Description
There are no properties to display for this resource.	

# **Kerberos Principal**

URI Endpoint: /api/tm/8.3/config/active/kerberos/principals

A Kerberos principal can be used by the traffic manager to participate in a Kerberos realm.

Property	Description
kdcs	A list of <hostname ip="">:<port> pairs for Kerberos key distribution center (KDC) services to be explicitly used for the realm of the principal. If no KDCs are explicitly configured, DNS will be used to discover the KDC(s) to use.  • Type: List(String)</port></hostname>
	Required: false
	Default value: <none></none>
	The name of the Kerberos keytab file containing suitable credentials to authenticate as the specified Kerberos principal.
keytab	Type: String
	Required: true
	Default value: <none></none>
	The name of an optional Kerberos configuration file (krb5.conf).
krb5conf	Type: String
	Required: false
	Default value: <none></none>
realm	The Kerberos realm where the principal belongs.
	Type: String
	Required: false
	Default value: <none></none>
service	The service name part of the Kerberos principal name the traffic manager should use to authenticate itself.

Property	Description
	Type: String
	Required: true
	Default value: <none></none>

#### License

URI Endpoint: /api/tm/8.3/config/active/license\_keys

A license key is an encoded text file that controls what functionality is available from each traffic manager in the cluster. Every production traffic manager must have a valid licence key in order to function; a traffic manager without a license will operate as Community Edition, which provides most of the functionality, but places restrictions on bandwidth and cluster size.

Property	Description
There are no properties to display for this resource.	

#### Location

URI Endpoint: /api/tm/8.3/config/active/locations

These are geographic locations as used by Global Load Balancing services. Such a location may not necessarily contain a traffic manager; instead it could refer to the location of a remote datacenter.

Property	Description
id	The identifier of this location.
	• Type: UInt
	Required: true
	Default value: <none></none>
latitude	The latitude of this location.
	Type: Float

Property	Description
	Required: false
	Default value: "0.0"
	The longitude of this location.
	Type: Float
longitude	Required: false
	Default value: "0.0"
	A note, used to describe this location.
	Type: FreeformString
note	Required: false
	Default value: <none></none>
	Does this location contain traffic managers and configuration or is it a recipient of GLB requests?
	Type: Enum(String)
	Required: false
type	Default value: "config"
	Permitted values:
	"config": Configuration
	"glb": GLB

# **Log Export**

URI Endpoint: /api/tm/8.3/config/active/log\_export

Definitions of log files which should be exported to the analytics engine

Property	Description
appliance_only	Whether entries from the specified log files should be exported only from appliances.
	Type: Boolean
	Required: false
	Default value: false
	Export entries from the log files included in this category.
enabled	Type: Boolean
enabled	Required: false
	Default value: false
	The set of files to export as part of this category, specified as a list of glob patterns.
files	Type: Set(String)
	Required: false
	Default value: <none></none>
	How much historic log activity should be exported.
	Type: Enum(String)
	Required: false
	Default value: "none"
history	Permitted values:
	"all": Export all historic entries
	"none": Do not export any historic entries
	"recent": Export recent historic entries, according to the 'history_period' setting
history_period	The number of days of historic log entries that should be exported.

Property	Description
	<ul><li>Type: UInt</li><li>Required: false</li></ul>
	Default value: "10"
	This is table 'metadata'
	Type: Table
	Required: false
	Primary key:
metadata	<ul> <li>name (String): The name of a metadata item which should be sent to the analytics engine along with entries from these log files. (Required)</li> </ul>
	Sub keys:
	<ul> <li>value (String): Additional metadata to include with the log entries when exporting them to the configured endpoint. Metadata can be used by the system that is receiving the exported data to categorise and parse the log entries. (Required)</li> </ul>
	A description of this category of log files.
note	Type: String
	Required: false
	Default value: <none></none>

### **Monitor**

URI Endpoint: /api/tm/8.3/config/active/monitors

Monitors check important remote services are running, by periodically sending them traffic and checking the response is correct. They are used by virtual servers to detect the failure of backend nodes.

Property	Description
back_off	Should the monitor slowly increase the delay after it has failed?  Type: Boolean  Required: false  Default value: true
delay	The minimum time between calls to a monitor.  • Type: UInt  • Required: false  • Default value: "3"
failures	The number of times in a row that a node must fail execution of the monitor before it is classed as unavailable.  Type: UInt Required: false Default value: "3"
health_only	Should this monitor only report health (ignore load)?  Type: Boolean  Required: false  Default value: false
machine	The machine to monitor, where relevant this should be in the form <hostname>:<port>, for "ping" monitors the :<port> part must not be specified.  • Type: String  • Required: false  • Default value: <none></none></port></port></hostname>
note	A description of the monitor.

Property	Description
	Type: FreeformString
	Required: false
	Default value: <none></none>
	A monitor can either monitor each node in the pool separately and disable an individual node if it fails, or it can monitor a specific machine and disable the entire pool if that machine fails. GLB location monitors must monitor a specific machine.
	Type: Enum(String)
	Required: false
scope	Default value: "pernode"
	Permitted values:
	"pernode": Node: Monitor each node in the pool separately
	"poolwide": Pool/GLB: Monitor a specified machine
	The maximum runtime for an individual instance of the monitor.
timeout	Type: UInt
	Required: false
	Default value: "3"
	The internal monitor implementation of this monitor.
	Type: Enum(String)
type	Required: false
	Default value: "ping"
	Permitted values:

Property	Description	
	"connect": TCP Connect monitor	
	"http": HTTP monitor	
	"ping": Ping monitor	
	"program": External program monitor	
	"rtsp": RTSP monitor	
	"sip": SIP monitor	
	"tcp_transaction": TCP transaction monitor	
	Whether or not the monitor should connect using SSL.	
use sel	Type: Boolean	
use_ssl	Required: false	
	Default value: false	
	Whether or not the monitor should emit verbose logging. This is useful for diagnosing problems.	
verbose	Type: Boolean	
	Required: false	
	Default value: false	
Properties for the "http" section	rties for the "http" section:	
	The HTTP basic-auth <user>:<password> to use for the test HTTP request.</password></user>	
authentication	Type: String	
	Required: false	
	Default value: <none></none>	

Property	Description
	A regular expression that the HTTP response body must match. If the response body content doesn't matter then set this to .* (match anything).
body_regex	Type: String
	Required: false
	Default value: <none></none>
	The host header to use in the test HTTP request.
host_header	Type: String
nost_neader	Required: false
	Default value: <none></none>
	The path to use in the test HTTP request. This must be a string beginning with a / (forward slash).
path	Type: String
	Required: false
	Default value: "/"
	A regular expression that the HTTP status code must match. If the status code doesn't matter then set this to .* (match anything).
status_regex	Type: String
	Required: false
	• Default value: "^[234][0-9][0-9]\$"
Properties for the "rtsp" section	n:
	The regular expression that the RTSP response body must match.
body_regex	Type: String
	Required: false

Property	Description
	Default value: <none></none>
	The path to use in the RTSP request (some servers will return 500 Internal Server Error unless this is a valid media file).
path	Type: String
	Required: false
	Default value: "/"
	The regular expression that the RTSP response status code must match.
status_regex	Type: String
	Required: false
	• Default value: "^[234][0-9][0-9]\$"
Properties for the "script" sect	ion:
	A table containing arguments and argument values to be passed to the monitor program.
	• Type: Table
arguments	Required: false
	Primary key:
	name (String): The name of the argument to be passed to the monitor program. (Required)
	Sub keys:
	value (String): The value of the argument to be passed to the monitor program. (Required)
	description (String): A description for the argument provided to the program.

Property	Description
program	The program to run. This must be an executable file, either within the monitor scripts directory or specified as an absolute path to some other location on the filesystem.
	Type: String
	Required: false
	Default value: <none></none>
Properties for the "sip" section	1:
	The regular expression that the SIP response body must match.
hada aana	Type: String
body_regex	Required: false
	Default value: <none></none>
	The regular expression that the SIP response status code must match.
status_regex	Type: String
	Required: false
	• Default value: "^[234][0-9][0-9]\$"
	Which transport protocol the SIP monitor will use to query the server.
	Type: Enum(String)
	Required: false
transport	Default value: "udp"
	Permitted values:
	"tcp": TCP
	"udp": UDP

Property	Description
Properties for the "tcp" section	n:
close_string	An optional string to write to the server before closing the connection.
	Type: String
	Required: false
	Default value: <none></none>
	The maximum amount of data to read back from a server, use 0 for unlimited. Applies to TCP and HTTP monitors.
max_response_len	Type: UInt
	Required: false
	Default value: "2048"
	A regular expression to match against the response from the server.  Applies to TCP monitors only.
response_regex	Type: String
	Required: false
	Default value: ".+"
	The string to write down the TCP connection.
is assis a	Type: String
write_string	Required: false
	Default value: <none></none>
Properties for the "udp" section	n:
accept_all	If this monitor uses UDP, should it accept responses from any IP and port?
	Type: Boolean

Property	Description
	Required: false
	Default value: false

## **Monitor Program**

URI Endpoint: /api/tm/8.3/config/active/monitor\_scripts

An executable program that can be used to by external program monitors to report the health of backend services.

	Property	Description
There are no properties to display for this resource.		play for this resource.

## **NAT Configuration**

URI Endpoint: /api/tm/8.3/config/active/appliance/nat

The NAT configuration file stores rules controlling NAT on an appliance.

Property	Description
many_to_one_all_ports	This is table 'many_to_one_all_ports'  Type: Table  Required: false  Primary key:  rule_number (String): A unique rule identifier (Required)  Sub keys:
	<ul> <li>pool (String): Pool of a "many to one overload" type</li> <li>NAT rule. (Required)</li> </ul>

Property	Description
	tip (String): TIP Group of a "many to one overload" type NAT rule. (Required)
	This is table 'many_to_one_port_locked'
	Type: Table
	Required: false
	Primary key:
many_to_one_port_locked	rule_number (String): A unique rule identifier (Required)
	Sub keys:
	pool (String): Pool of a "many to one port locked" type     NAT rule. (Required)
	port (UInt): Port number of a "many to one port locked"     type NAT rule. (Required)
	protocol (Enum(String)): Protocol of a "many to one port locked" type NAT rule. (Required)
	Permitted values:
	"icmp": ICMP
	"sctp": SCTP
	"tcp": TCP
	"udp": UDP
	"udplite": UDPLITE
	tip (String): TIP Group of a "many to one port locked" type NAT rule. (Required)
one_to_one	This is table 'one_to_one'
	Type: Table

Property	Description
	Required: false
	Primary key:
	rule_number (String): A unique rule identifier (Required)
	Sub keys:
	enable_inbound (Boolean): Enabling the inbound part of a "one to one" type NAT rule. (Required)
	ip (String): IP Address of a "one to one" type NAT rule.  (Required)
	tip (String): TIP group of a "one to one" type NAT rule. (Required)
	This is table 'port_mapping'
port_mapping	• Type: Table
	Required: false
	Primary key:
	rule_number (String): A unique rule identifier (Required)
	Sub keys:
	dport_first (UInt): First port of the dest. port range of a     "port mapping" rule. (Required)
	dport_last (UInt): Last port of the dest. port range of a     "port mapping" rule. (Required)
	virtual_server (String): Target Virtual Server of a "port mapping" rule. (Required)

## Pool

URI Endpoint: /api/tm/8.3/config/active/pools

The conf/pools directory contains configuration files for backend node pools. The name of a file is the name of the pool it defines. Pools can be configured under the Services > Pools section of the Admin Server UI or by using functions under the Pool section of the SOAP API and CLI.

Property	Description
bandwidth_class	The Bandwidth Management Class this pool uses, if any.
	Type: Reference(config-bandwidth)
	Required: false
	Default value: <none></none>
failure_pool	If all of the nodes in this pool have failed, then requests can be diverted to another pool.
	Type: Reference(config-pool)
	Required: false
	Default value: <none></none>
max_connection_attempts	The maximum number of nodes to which the traffic manager will attempt to send a request before returning an error to the client.  Requests that are non-retryable will be attempted against only one node. Zero signifies no limit.
	Type: UInt
	Required: false
	Default value: <none></none>
max_idle_connections_ pernode	The maximum number of unused HTTP keepalive connections that should be maintained to an individual node. Zero signifies no limit.
	Type: UInt
	Required: false
	Default value: "50"

Property	Description
max_timed_out_ connection_attempts	The maximum number of connection attempts the traffic manager will make where the server fails to respond within the time limit defined by the max_reply_time setting. Zero signifies no limit.  Type: UInt  Required: false  Default value: "2"
monitors	The monitors assigned to this pool, used to detect failures in the back end nodes.  • Type: Set(Reference(config-monitor))
	<ul><li>Required: false</li><li>Default value: <none></none></li></ul>
node_close_with_rst	Whether or not connections to the back-end nodes should be closed with a RST packet, rather than a FIN packet. This avoids the TIME_WAIT state, which on rare occasions allows wandering duplicate packets to be safely ignored.  Type: Boolean Required: false Default value: false
node_connection_attempts	The number of times the software will attempt to connect to the same back-end node before marking it as failed. This is only used when passive_monitoring is enabled.
	<ul><li>Type: UInt</li><li>Required: false</li></ul>
node_delete_behavior	Default value: "3"  Specify the deletion behavior for nodes in this pool.
	Type: Enum(String)

Property	Description
	<ul> <li>Required: false</li> <li>Default value: "immediate"</li> <li>Permitted values:  "drain": Allow existing connections to the node to finish before deletion.  "immediate": All connections to the node are closed immediately.</li> </ul>
node_drain_to_delete_ timeout	The maximum time that a node will be allowed to remain in a draining state after it has been deleted. A value of 0 means no maximum time.  Type: UInt Required: false Default value: <none></none>
nodes_table	<ul> <li>A table of all nodes in this pool. A node should be specified as a <ip>:<port> pair, and has a state, weight and priority.</port></ip></li> <li>Type: Table</li> <li>Required: false</li> <li>Primary key: <ul> <li>node (String): A node is a combination of an ip address and port (Required)</li> </ul> </li> <li>Sub keys: <ul> <li>priority (UInt): The priority of the node, higher values signify higher priority. If a priority is not specified for a node it is assumed to be 1.</li> <li>state (Enum(String)): The state of the pool, which can either be Active, Draining or Disabled</li> </ul> </li> </ul>

Property	Description
	Permitted values:
	"active": The node is is active.
	"disabled": The node is disabled.
	"draining": The node is draining.
	<ul> <li>weight (Int): Weight for the node. The actual value in isolation does not matter: As long as it is a valid integer 1-100, the per-node weightings are calculated on the relative values between the nodes.</li> </ul>
	<ul> <li>source_ip (String): The source address the Traffic</li> <li>Manager uses to connect to this node.</li> </ul>
	A description of the pool.
note	Type: String
note	Required: false
	Default value: <none></none>
passive_monitoring	Whether or not the software should check that 'real' requests (i.e. not those from monitors) to this pool appear to be working. This should normally be enabled, so that when a node is refusing connections, responding too slowly, or sending back invalid data, it can mark that node as failed, and stop sending requests to it. If this is disabled, you should ensure that suitable health monitors are configured to check your servers instead, otherwise failed requests will not be detected and subsequently retried.
	Type: Boolean
	Required: false
	Default value: true
persistence_class	The default Session Persistence class this pool uses, if any.
persistence_ciass	Type: Reference(config-persistence)

Property	Description
	Required: false
	Default value: <none></none>
	Whether or not connections to the back-ends appear to originate from the source client IP address.
transparent	Type: Boolean
	Required: false
	Default value: false
Properties for the "auto_scaling	ng" section:
	The time in seconds from the creation of the node which the traffic manager should wait before adding the node to the autoscaled pool. Set this to allow applications on the newly created node time to intialize before being sent traffic.
addnode_delaytime	Type: UInt
	Required: false
	Default value: <none></none>
	The Cloud Credentials object containing authentication credentials to use in cloud API calls.
cloud_credentials	Type: Reference(cloud-api)
	Required: false
	Default value: <none></none>
cluster	The ESX host or ESX cluster name to put the new virtual machine instances on.
	Type: String
	Required: false
	Default value: <none></none>

Property	Description
	The name of the logical datacenter on the vCenter server. Virtual machines will be scaled up and down under the datacenter root folder.
data_center	Type: String
	Required: false
	Default value: <none></none>
	The name of the datastore to be used by the newly created virtual machine.
data_store	Type: String
	Required: false
	Default value: <none></none>
	Are the nodes of this pool subject to autoscaling? If yes, nodes will be automatically added and removed from the pool by the chosen autoscaling mechanism.
enabled	Type: Boolean
	Required: false
	Default value: false
external	Whether or not autoscaling is being handled by an external system.  Set this value to Yes if all aspects of autoscaling are handled by an external system, such as RightScale. If set to No, the traffic manager will determine when to scale the pool and will communicate with the cloud provider to create and destroy nodes as necessary.
	Type: Boolean
	Required: false
	Default value: true

Property	Description
extraargs	Any extra arguments to the autoscaling API. Each argument can be separated by comma. E.g in case of EC2, it can take extra parameters to the Amazon's RunInstance API say DisableApiTermination=false,Placement.Tenancy=default.  • Type: String  • Required: false  • Default value: <none></none>
hysteresis	The time period in seconds for which a change condition must persist before the change is actually instigated.  Type: UInt Required: false Default value: "20"
imageid	The identifier for the image of the instances to create.  Type: String Required: false Default value: <none></none>
ips_to_use	Which type of IP addresses on the node to use. Choose private IPs if the traffic manager is in the same cloud as the nodes, otherwise choose public IPs.  • Type: Enum(String)  • Required: false  • Default value: "publicips"  • Permitted values:  "private_ips": Private IP addresses  "publicips": Public IP addresses

Property	Description
	The time in seconds for which the last node in an autoscaled pool must have been idle before it is destroyed. This is only relevant if min_nodes is 0.
last_node_idle_time	Type: UInt
	Required: false
	Default value: "3600"
	The maximum number of nodes in this autoscaled pool.
max_nodes	• Type: UInt
max_nodes	Required: false
	Default value: "4"
	The minimum number of nodes in this autoscaled pool.
min nados	Type: UInt
min_nodes	Required: false
	Default value: "1"
	The beginning of the name of nodes in the cloud that are part of this autoscaled pool.
name	Type: String
	Required: false
	Default value: <none></none>
port	The port number to use for each node in this autoscaled pool.
	Type: UInt
	Required: false
	Default value: "80"

Property	Description
refractory	The time period in seconds after the instigation of a re-size during which no further changes will be made to the pool size.
	Type: UInt
	Required: false
	Default value: "180"
response_time	The expected response time of the nodes in ms. This time is used as a reference when deciding whether a node's response time is conforming. All responses from all the nodes will be compared to this reference and the percentage of conforming responses is the base for decisions about scaling the pool up or down.
·	Type: UInt
	Required: false
	Default value: "1000"
	The fraction, in percent, of conforming requests above which the pool size is decreased. If the percentage of conforming requests exceeds this value, the pool is scaled down.
scale_down_level	Type: UInt
	Required: false
	Default value: "95"
scale_up_level	The fraction, in percent, of conforming requests below which the pool size is increased. If the percentage of conforming requests drops below this value, the pool is scaled up.
	Type: UInt
	Required: false
	Default value: "40"
securitygroupids	List of security group IDs to associate to the new EC2 instance.

Property	Description
	Type: Set(String)
	Required: false
	Default value: <none></none>
	The identifier for the size of the instances to create.
size id	Type: String
size_id	Required: false
	Default value: <none></none>
	List of subnet IDs where the new EC2-VPC instance(s) will be launched. Instances will be evenly distributed among the subnets. If the list is empty, instances will be launched inside EC2-Classic.
subnetids	Type: Set(String)
	Required: false
	Default value: <none></none>
Properties for the "connection	n" section:
	How long the pool should wait for a connection to a node to be established before giving up and trying another node.
max_connect_time	Type: UInt
	Required: false
	Default value: "4"
max_connections_per_node	The maximum number of concurrent connections allowed to each back-end node in this pool per machine. A value of 0 means unlimited connections.
	Type: UInt
	Required: false
	Default value: <none></none>

Property	Description
	The maximum number of connections that can be queued due to connections limits. A value of 0 means unlimited queue size.
max_queue_size	Type: UInt
	Required: false
	Default value: <none></none>
	How long the pool should wait for a response from the node before either discarding the request or trying another node (retryable requests only).
max_reply_time	Type: UInt
	Required: false
	Default value: "30"
max_transactions_per_node	The maximum number of concurrent transactions allowed to each back-end node in this pool per machine. A value of 0 means unlimited transactions. Idle connections kept alive for reuse do not count against this limit. A transaction begins by allocating a connection for sending the request, and ends (for the purposes of queuing) after a complete response has been received from the node.  • Type: UInt
	Required: false
	Default value: <none>  The province time to be a second of the province time.</none>
queue_timeout	The maximum time to keep a connection queued in seconds.  Type: UInt Required: false Default value: "10"
Properties for the "dns_autoscale" section:	

Property	Description	
enabled	When enabled, the Traffic Manager will periodically resolve the hostnames in the "hostnames" list using a DNS query, and use the results to automatically add, remove or update the IP addresses of the nodes in the pool.  Type: Boolean Required: false	
	A list of hostnames which will be used for DNS-derived autoscaling	
	Type: Set(String)	
hostnames	Required: false	
	Default value: <none></none>	
	The port number to use for each node when using DNS-derived autoscaling	
port	Type: UInt	
	Required: false	
	Default value: "80"	
Properties for the "ftp" section:		
support_rfc_2428	Whether or not the backend IPv4 nodes understand the EPRT and EPSV command from RFC 2428. It is always assumed that IPv6 nodes support these commands.	
	Type: Boolean	
	Required: false	
	Default value: false	
Properties for the "http" secti	on:	

Property	Description
keepalive	Whether or not the pool should maintain HTTP keepalive connections to the nodes.
	Type: Boolean
	Required: false
	Default value: true
	Whether or not the pool should maintain HTTP keepalive connections to the nodes for non-idempotent requests.
keepalive_non_idempotent	Type: Boolean
	Required: false
	Default value: false
Properties for the "kerberos_p	protocol_transition" section:
	The Kerberos principal the traffic manager should use when performing Kerberos Protocol Transition.
principal	Type: String
	Required: false
	Default value: <none></none>
	The Kerberos principal name of the service this pool targets.
toward	Type: String
target	Required: false
	Default value: <none></none>
Properties for the "load_balancing" section:	
algorithm	The load balancing algorithm that this pool uses to distribute load across its nodes.
	Type: Enum(String)

Property	Description
	Required: false
	Default value: "round_robin"
	Permitted values:
	"fastest_response_time": The Response Time algorithm monitors the response times for recent requests to each node. It sends each new request to the node that has recently been responding the most quickly.
	"least_connections": This algorithm sends each new request to the node with the fewest currently active connections.
	"perceptive": The Perceptive algorithm uses a combination of response time data and connection counts to predict which node is likely to have the fastest response time for each request.
	"random": This algorithm chooses a random node for each request.
	"round_robin": This algorithm distributes traffic by assigning each request to a new node in turn.
	"weighted_least_connections": This algorithm works in a similar way to the Least Connections algorithm, but assigns more requests to nodes with a greater 'weight'.
	"weighted_round_robin": Weighted Round Robin works in a similar way to Round Robin, but assigns more requests to nodes with a greater 'weight'.
priority_enabled	Enable priority lists.

Property	Description	
	Type: Boolean	
	Required: false	
	Default value: false	
	Minimum number of highest-priority active nodes.	
	Type: UInt	
priority_nodes	Required: false	
	Default value: "1"	
Properties for the "node" sect	tion:	
	Close all connections to a node once we detect that it has failed.	
alana ara danda	Type: Boolean	
close_on_death	Required: false	
	Default value: false	
	The amount of time, in seconds, that a traffic manager will wait before re-trying a node that has been marked as failed by passive monitoring.	
retry_fail_time	Type: UInt	
	Required: false	
	Default value: "60"	
Properties for the "service_discovery" section:		
enabled	Are the nodes of this pool determined by a Service Discovery plugin? If yes, nodes will be automatically added and removed from the pool by the traffic manager.	
	Type: Boolean	
	Required: false	

Property	Description
	Default value: false
	The minimum time before rerunning the Service Discovery plugin
	Type: UInt
interval	Required: false
	Default value: "10"
	The plugin script a Service Discovery autoscaled pool should use to retrieve the list of nodes.
plugin	Type: String
	Required: false
	Default value: <none></none>
plugin_args	The arguments for the script specified in "service_discovery!plugin", e.g. a common instance tag, or name of a managed group of cloud instances.
	Type: String
	Required: false
	Default value: <none></none>
timeout	The maximum time a plugin should be allowed to run before timing out. Set to 0 for no timeout.
	Type: UInt
	Required: false
	Default value: <none></none>
Properties for the "smtp" section:	
send_starttls	If we are encrypting traffic for an SMTP connection, should we upgrade to SSL using STARTTLS.
	Type: Boolean

Property	Description
	Required: false
	Default value: true
Properties for the "ssl" section	ո:
cipher_suites	The SSL/TLS cipher suites to allow for connections to a back-end node. Leaving this empty will make the pool use the globally configured cipher suites, see configuration key ssl!cipher_suites in the Global Settings section of the System tab. See there for how to specify SSL/TLS cipher suites.
	Type: String
	Required: false
	Default value: <none></none>
	Whether or not a suitable certificate and private key from the SSL Client Certificates catalog be used if the back-end server requests client authentication.
client_auth	Type: Boolean
	Required: false
	Default value: false
common_name_match	A list of names against which the 'common name' of the certificate is matched; these names are used in addition to the node's hostname or IP address as specified in the config file or added by the autoscaler process.
	Type: Set(String)
	Required: false
	Default value: <none></none>

Property	Description
elliptic_curves	The SSL elliptic curve preference list for SSL connections from this pool using TLS version 1.0 or higher. Leaving this empty will make the pool use the globally configured preference list. The named curves P256, P384 and P521 may be configured.  • Type: List(String)
	<ul><li>Required: false</li><li>Default value: <none></none></li></ul>
	Whether or not the pool should encrypt data before sending it to a back-end node.
enable	Type: Boolean
	Required: false
	Default value: false
enhance	SSL protocol enhancements allow your traffic manager to prefix each new SSL connection with information about the client. This enables Pulse Secure Virtual Traffic Manager virtual servers referenced by this pool to discover the original client's IP address. Only enable this if you are using nodes for this pool which are Pulse Secure vTMs, whose virtual servers have the ssl_trust_magic setting enabled.
	Type: Boolean
	Required: false
	Default value: false
middlebox_compatibility	Whether or not TLS 1.3 middlebox compatibility mode as described in RFC 8446 appendix D.4 will be used in connections to pool nodes. Choosing the global setting means the value of configuration key ssl!middlebox_compatibility from the Global Settings section of the System tab will be enforced.
	Type: Enum(String)

Property	Description
	Required: false
	Default value: "use_default"
	Permitted values:
	"disabled": Disable use of middlebox compatibility
	"enabled": Enable use of middlebox compatibility
	"use_default": Use the global setting for use of middlebox compatibility
send_close_alerts	Whether or not to send an SSL/TLS "close alert" when initiating a socket disconnection.
	Type: Boolean
	Required: false
	Default value: true
	Whether or not the software should use the TLS 1.0 server_name extension, which may help the back-end node provide the correct certificate. Enabling this setting will force the use of at least TLS 1.0.
server_name	Type: Boolean
	Required: false
	Default value: false
session_cache_enabled	Whether or not the SSL client cache will be used for this pool. Choosing the global setting means the value of the configuration key ssl!client_cache!enabled from the Global Settings section of the System tab will be enforced.
	Type: Enum(String)
	Required: false

Property	Description
	Default value: "use_default"
	Permitted values:
	"disabled": Disable use of the session cache
	"enabled": Enable use of the session cache
	"use_default": Use the global setting for use of the session cache
	Whether or not SSL session tickets, including TLS >= 1.3 PSKs, will be used for this pool if the session cache is also enabled. Choosing the global setting means the value of the configuration key ssl!client_ cache!tickets_enabled from the Global Settings section of the System tab will be enforced.
	Type: Enum(String)
and the second second	Required: false
session_tickets_enabled	Default value: "use_default"
	Permitted values:
	"disabled": Disable use of session tickets
	"enabled": Enable use of session tickets
	"use_default": Use the global setting for use of session tickets
signature_algorithms	The SSL signature algorithms preference list for SSL connections from this pool using TLS version 1.2 or higher. Leaving this empty will make the pool use the globally configured preference list, signature_algorithms in the ssl section of the global_settings resource. See there and in the online help for how to specify SSL signature algorithms.
	Type: String
	Required: false

Property	Description
	Default value: <none></none>
	An entry in the SSL client certificates catalog, containing a certificate and private key to be used whenever client authentication is requested. If set, this overrides server request parameters.
ssl_fixed_client_certificate	Type: String
	Required: false
	Default value: <none></none>
	Whether or not strict certificate verification should be performed.  This will turn on checks to disallow server certificates that don't match the server name or a name in the ssl_common_name_match list, are self-signed, expired, revoked, or have an unknown CA.
strict_verify	Type: Boolean
	Required: false
	Default value: false
	Whether or not SSLv3 is enabled for this pool. Choosing the global setting means the value of the configuration key ssl!support_ssl3 from the Global Settings section of the System tab will be enforced.
	Type: Enum(String)
support_ssl3	Required: false
	Default value: "use_default"
	Permitted values:
	"disabled": Disable SSLv3
	"enabled": Enable SSLv3
	"use_default": Use the global setting for SSLv3

Property	Description
	Whether or not TLSv1.0 is enabled for this pool. Choosing the global setting means the value of the configuration key ssl!support_tls1 from the Global Settings section of the System tab will be enforced.
	Type: Enum(String)
	Required: false
support_tls1	Default value: "use_default"
	Permitted values:
	"disabled": Disable TLSv1.0
	"enabled": Enable TLSv1.0
	"use_default": Use the global setting for TLSv1.0
	Whether or not TLSv1.1 is enabled for this pool. Choosing the global setting means the value of the configuration key ssl!support_tls1_1 from the Global Settings section of the System tab will be enforced.
	Type: Enum(String)
	Required: false
support_tls1_1	Default value: "use_default"
	Permitted values:
	"disabled": Disable TLSv1.1
	"enabled": Enable TLSv1.1
	"use_default": Use the global setting for TLSv1.1
support_tls1_2	Whether or not TLSv1.2 is enabled for this pool. Choosing the global setting means the value of the configuration key ssl!support_tls1_2 from the Global Settings section of the System tab will be enforced.

Property	Description
	<ul> <li>Type: Enum(String)</li> <li>Required: false</li> <li>Default value: "use_default"</li> <li>Permitted values:  "disabled": Disable TLSv1.2  "enabled": Enable TLSv1.2</li> </ul>
	"use_default": Use the global setting for TLSv1.2
support_tls1_3	Whether or not TLSv1.3 is enabled for this pool. Choosing the global setting means the value of the configuration key ssl!support_tls1_3 from the Global Settings section of the System tab will be enforced.  • Type: Enum(String)  • Required: false  • Default value: "use_default"  • Permitted values:  "disabled": Disable TLSv1.3  "enabled": Enable TLSv1.3  "use_default": Use the global setting for TLSv1.3
Properties for the "tcp" section:	
nagle	Whether or not Nagle's algorithm should be used for TCP connections to the back-end nodes.  Type: Boolean Required: false

Property	Description
	Default value: true
Properties for the "udp" secti	on:
	The IP addresses and ports from which responses to UDP requests should be accepted. If set to accept responses from a specific set of IP addresses, you will need to enter a CIDR Mask (such as 10.100.0.0/16).
	Type: Enum(String)
	Required: false
	Default value: "dest_only"
accept_from	Permitted values:
	"all": Any IP address and any port.
	"dest_ip_only": Only the IP address to which the request was sent, but from any port.
	"dest_only": Only the IP address and port to which the request was sent.
	"ip_mask": Only a specific set of IP addresses, but from any port.
	The CIDR mask that matches IPs we want to receive responses from.
account from mack	Type: String
accept_from_mask	Required: false
	Default value: <none></none>
response_timeout	The maximum length of time that a node is permitted to take after receiving a UDP request packet before sending a reply packet. Zero indicates that there is no maximum, preventing a node that does not send replies from being presumed to have failed.
	Type: UInt

Property	Description
	Required: false
	Default value: <none></none>

## **Protection Class**

URI Endpoint: /api/tm/8.3/config/active/protection

A protection class specifies the level of protection against network attacks for a virtual server.

Property	Description
debug	<ul><li>Whether or not to output verbose logging.</li><li>Type: Boolean</li><li>Required: false</li></ul>
	Default value: false
	Enable or disable this service protection class.
enabled	Type: Boolean
	Required: false
	Default value: true
	Log service protection messages at these intervals. If set to 0 no messages will be logged and no alerts will be sent.
log_time	Type: UInt
	Required: false
	Default value: "60"
note	A description of the service protection class.
	Type: String
	Required: false

Property	Description
	Default value: <none></none>
	A TrafficScript rule that will be run on the connection after the service protection criteria have been evaluated. This rule will be executed prior to normal rules configured for the virtual server.
rule	Type: Reference(config-trafficscript)
	Required: false
	Default value: <none></none>
	Place the service protection class into testing mode. (Log when this class would have dropped a connection, but allow all connections through).
testing	Type: Boolean
	Required: false
	Default value: false
Properties for the "access_rest	riction" section:
	Always allow access to these IP addresses. This overrides the connection limits for these machines, but does not stop other restrictions such as HTTP validity checks.
allowed	Type: Set(String)
	Required: false
	Default value: <none></none>
banned	Disallow access to these IP addresses.
	Type: Set(String)
	Required: false
	Default value: <none></none>
Properties for the "concurrent	_connections" section:

Property	Description
max_10_connections	Additional limit on maximum concurrent connections from the top 10 busiest connecting IP addresses combined. The value should be between 1 and 10 times the max_1_connections limit. (This limit is disabled if per_process_connection_count is No, or max_1_ connections is 0, or min_connections is 0.)
	Type: UInt
	Required: false
	Default value: "200"
	Maximum concurrent connections each connecting IP address is allowed. Set to 0 to disable this limit.
max_1_connections	Type: UInt
	Required: false
	Default value: "30"
min_connections	Entry threshold for the max_10_connections limit: the max_10_connections limit is not applied to connecting IP addresses with this many or fewer concurrent connections. Setting to 0 disables both the max_1_connections and max_10_connections limits, if per_process_connection_count is Yes. (If per_process_connection_count is No, this setting is ignored.)
	• Type: UInt
	Required: false
	Default value: "4"
per_process_connection_ count	Whether concurrent connection counting and limits are perprocess. (Each Traffic Manager typically has several processes: one process per available CPU core.) If Yes, a connecting IP address may make that many connections to each process within a Traffic Manager. If No, a connecting IP address may make that many connections to each Traffic Manager as a whole.

Property	Description
	Type: Boolean
	Required: false
	Default value: true
Properties for the "connection	_rate" section:
max_connection_rate	Maximum number of new connections each connecting IP address is allowed to make in the rate_timer interval. Set to 0 to disable this limit. If applied to an HTTP Virtual Server each request sent on a connection that is kept alive counts as a new connection. The rate limit is per process: each process within a Traffic Manager accepts new connections from the connecting IP address at this rate. (Each Traffic Manager typically has several processes: one process per available CPU core).  • Type: UInt  • Required: false
	Default value: <none></none>
rate_timer	How frequently the max_connection_rate is assessed. For example, a value of 1 (second) will impose a limit of max_connection_rate connections per second; a value of 60 will impose a limit of max_connection_rate connections per minute. The valid range is 1-99999 seconds.  • Type: UInt
	Required: false
	Default value: "60"
Properties for the "http" section:	
check_rfc2396	Whether or not requests with poorly-formed URLs be should be rejected. This tests URL compliance as defined in RFC2396. Note that enabling this may block some older, non-conforming web browsers.

Property	Description
	Type: Boolean
	Required: false
	Default value: false
	Maximum permitted length of HTTP request body data, set to 0 to disable the limit.
max_body_length	Type: UInt
	Required: false
	Default value: <none></none>
	Maximum permitted length of a single HTTP request header (key and value), set to 0 to disable the limit.
max_header_length	Type: UInt
	Required: false
	Default value: <none></none>
max_request_length	Maximum permitted size of all the HTTP request headers, set to 0 to disable the limit.
	Type: UInt
	Required: false
	Default value: <none></none>
	Maximum permitted URL length, set to 0 to disable the limit.
max_url_length	• Type: UInt
	Required: false
	Default value: <none></none>
reject_binary	Whether or not URLs and HTTP request headers that contain binary data (after decoding) should be rejected.

Property	Description
	Type: Boolean
	Required: false
	Default value: false
send_error_page	This setting tells the traffic manager to send an HTTP error message if a connection fails the service protection tests, instead of just dropping it. Details of which HTTP response will be sent when particular tests fail can be found in the Help section for this page.  • Type: Boolean  • Required: false  • Default value: true

### **Pulse Secure Virtual Web Application Firewall**

URI Endpoint: /api/tm/8.3/config/active/application\_firewall

The conf/zeusafm.conf file contains configuration files for the application firewall. Some keys present in the zeusafm.conf are not documented here. Refer to the Pulse Secure Web Application Firewall documentation for further details. The configuration can be edited under the System > Application Firewall section of the Administration Server or by using functions under the AFM section of the SOAP API and CLI.

Property	Description
There are no properties to display for this resource.	

## **Rate Shaping Class**

URI Endpoint: /api/tm/8.3/config/active/rate

A rate shaping class restricts the number of connections being processed by a virtual server at once.

Property	Description
max_rate_per_minute	Requests that are associated with this rate class will be rate-shaped to this many requests per minute, set to 0 to disable the limit.  Type: UInt Required: false Default value: <none></none>
max_rate_per_second	Although requests will be rate-shaped to the max_rate_per_minute, the traffic manager will also rate limit per-second. This smooths traffic so that a full minute's traffic will not be serviced in the first second of the minute, set this to 0 to disable the per-second limit.  • Type: UInt  • Required: false  • Default value: <none></none>
note	A description of the rate class.  Type: FreeformString  Required: false  Default value: <none></none>

#### Rule

URI Endpoint: /api/tm/8.3/config/active/rules

TrafficScript rules allow traffic inspection and modification.

Property	Description
There are no properties to display for this resource.	

## **SLM Class**

URI Endpoint: /api/tm/8.3/config/active/service\_level\_monitors

Service level monitoring is used to produce alerts when an application's performance is degraded. This is done by monitoring the response time of connections to a virtual server.

Property	Description
note	A description for the SLM class.
	<ul><li>Type: FreeformString</li><li>Required: false</li></ul>
	Default value: <none></none>
	Responses that start being sent to the client within this time limit, expressed in milliseconds, are treated as conforming.
response_time	• Type: UInt
	Required: false
	Default value: "1000"
	When the percentage of conforming responses drops below this level, a serious error level message will be emitted.
serious_threshold	• Type: UInt
	Required: false
	Default value: <none></none>
warning_threshold	When the percentage of conforming responses drops below this level, a warning message will be emitted.
	• Type: UInt
	Required: false
	Default value: "50"

# **SSL Client Key Pair**

URI Endpoint: /api/tm/8.3/config/active/ssl/client\_keys

SSL Client Certificates are used when connecting to backend nodes that require client certificate authentication.

Property	Description
	Notes for this certificate
	Type: FreeformString
note	Required: true
	Default value: <none></none>
	Private key for certificate
avi tata	Type: FreeformString
private	Required: true
	Default value: <none></none>
	Public certificate
public	Type: FreeformString
public	Required: true
	Default value: <none></none>
	Certificate Signing Request for certificate
request	Type: FreeformString
	Required: true
	Default value: <none></none>

## **SSL Key Pair**

URI Endpoint: /api/tm/8.3/config/active/ssl/server\_keys

SSL Server Certificates are presented to clients by virtual servers when SSL decryption is enabled.

Property	Description
	Notes for this certificate
n et e	Type: FreeformString
note	Required: true
	Default value: <none></none>
	Private key for certificate
private	Type: FreeformString
private	Required: true
	Default value: <none></none>
	Public certificate
public	Type: FreeformString
public	Required: true
	Default value: <none></none>
request	Certificate Signing Request for certificate
	Type: FreeformString
	Required: true
	Default value: <none></none>

# **SSL Ticket Key**

URI Endpoint: /api/tm/8.3/config/active/ssl/ticket\_keys

Configuration for SSL ticket encryption keys when managed externally via the ssl/ticket\_keys REST API endpoints.

Property	Description
	The algorithm used to encrypt session tickets. The algorithm determines the length of the key that must be provided.
	Type: Enum(String)
	Required: false
algorithm	Default value: "aes_256_cbc_hmac_sha256"
	Permitted values:
	"aes_256_cbc_hmac_sha256": AES-256 CBC with HMAC-SHA256. Requires a total of 64 bytes of key material.
id	A 16-byte key identifier, with each byte encoded as two hexadecimal digits. Key identifiers are transmitted in plaintext at the beginning of a TLS session ticket, and are used to identify the ticket encryption key that was used to encrypt a ticket. (They correspond to the 'key_ name' field in RFC 5077.) They are required to be unique across the set of SSL ticket encryption keys.
	Type: String
	Required: true
	Default value: <none></none>
key	The session ticket encryption key, with each byte encoded as two hexadecimal digits. The required key length is determined by the chosen key algorithm. See the documentation for the 'algorithm' field for more details.
	Type: Password
	Required: true
	Default value: <none></none>

Property	Description
validity_end	The latest time at which this key may be used to encrypt new session tickets. Given as number of seconds since the epoch (1970-01-01T00:00:00Z).
	Type: UInt
	Required: true
	Default value: <none></none>
validity_start	The earliest time at which this key may be used to encrypt new session tickets. Given as number of seconds since the epoch (1970-01-01T00:00:00Z).
	Type: UInt
	Required: true
	Default value: <none></none>

#### **SSL Trusted Certificate**

URI Endpoint: /api/tm/8.3/config/active/ssl/cas

SSL certificate authority certificates (CAs) and certificate revocation lists (CRLs) can be used when validating server and client certificates.

Property	Description
There are no properties to display for this resource.	

## **Security Settings**

URI Endpoint: /api/tm/8.3/config/active/security

Security settings that restrict remote administration for the cluster. Additional security options can be found in Global Settings.

Property	Description		
access	Access to the admin server and REST API is restricted by usernames and passwords. You can further restrict access to just trusted IP addresses, CIDR IP subnets or DNS wildcards. These access restrictions are also used when another traffic manager initially joins the cluster, after joining the cluster these restrictions are no longer used. Care must be taken when changing this setting, as it can cause the administration server to become inaccessible. Access to the admin UI will not be affected until it is restarted.		
	Type: Set(String)		
	Required: false		
	Default value: <none></none>		
Properties for the "ssh_intrusic	Properties for the "ssh_intrusion" section:		
bantime	The amount of time in seconds to ban an offending host for.  Type: UInt Required: false Default value: "600"		
blacklist	The list of hosts to permanently ban, identified by IP address or DNS hostname in a space-separated list.  • Type: Set(String)		
	<ul><li>Required: false</li><li>Default value: <none></none></li></ul>		
	Whether or not the SSH Intrusion Prevention tool is enabled.		
	• Type: Boolean		
enabled	Required: false		
	Default value: true		

Property	Description
findtime	The window of time in seconds the maximum number of connection attempts applies to. More than (maxretry) failed attempts in this time span will trigger a ban.
	• Type: UInt
	Required: false
	Default value: "600"
maxretry	The number of failed connection attempts a host can make before being banned.
	• Type: UInt
	Required: false
	Default value: "6"
whitelist	The list of hosts to never ban, identified by IP address, DNS hostname or subnet mask, in a space-separated list.
	Type: Set(String)
	Required: false
	Default value: <none></none>

## **Service Discovery Plugins**

URI Endpoint: /api/tm/8.3/config/active/servicediscovery

The conf/servicediscovery directory contains plugins for use with Service Discovery for pool nodes.

	Property	Description
There are no properties to display for this resource.		play for this resource.

#### **Session Persistence Class**

URI Endpoint: /api/tm/8.3/config/active/persistence

A session persistence class is used to identify the session a new connection belongs too and deliver it to the same backend node.

Property	Description
cookie	The cookie name to use for tracking session persistence.
	Type: String
	Required: false
	Default value: <none></none>
delete	Whether or not the session should be deleted when a session failure occurs. (Note, setting a failure mode of 'choose a new node' implicitly deletes the session.)
	Type: Boolean
	Required: false
	Default value: true
failure_mode	The action the pool should take if the session data is invalid or it cannot contact the node specified by the session.
	Type: Enum(String)
	Required: false
	Default value: "new_node"
	Permitted values:
	"close": Close the connection (using error_ file on Virtual Servers > Edit > Protocol Settings)
	"new_node": Choose a new node to use
	"url": Redirect the user to a given URL
note	A description of the session persistence class.
TIOLE	Type: FreeformString

Property	Description
	Required: false
	Default value: <none></none>
	When using IP-based session persistence, ensure all requests from this IPv4 subnet, specified as a prefix length, are sent to the same node. If set to 0, requests from different IPv4 addresses will be load-balanced individually.
subnet_prefix_length_v4	Type: Int
	Required: false
	Default value: <none></none>
	When using IP-based session persistence, ensure all requests from this IPv6 subnet, specified as a prefix length, are sent to the same node. If set to 0, requests from different IPv6 addresses will be load-balanced individually.
subnet_prefix_length_v6	Type: Int
	Required: false
	Default value: <none></none>
transparent_always_set_	Whether or not the cookie should be inserted in every response sent to the client when using transparent session affinity. If set to No then the cookie is inserted only if the corresponding request did not already contain a matching cookie.
cookie	Type: Boolean
	Required: false
	Default value: false
transparent_directives	The cookie directives to include in the cookie sent when using transparent session affinity. If more than one directive is included, the semi-colon separator between them must be included in this string. The semi-colon separator between the cookie value and the first directive should not be included in this string.

Property	Description
	Type: String
	Required: false
	Default value: <none></none>
	The type of session persistence to use.
	Type: Enum(String)
	Required: false
	Default value: "ip"
	Permitted values:
	"asp": ASP and ASP.NET session persistence
	"cookie": Monitor application cookies
type	"ip": IP-based persistence
	"j2ee": J2EE session persistence
	"named": Named Node session persistence
	"ssl": SSL Session ID persistence
	"transparent": Transparent session affinity
	"universal": Universal session persistence
	"x_zeus": X-Zeus-Backend cookies
url	The redirect URL to send clients to if the session persistence is configured to redirect users when a node dies.
	Type: String
	Required: false
	Default value: <none></none>

## **Traffic IP Group**

URI Endpoint: /api/tm/8.3/config/active/traffic\_ip\_groups

Traffic IP groups are sets of IP addresses that are distributed across a cluster for fault tolerance.

Property	Description
enabled	If set to No, the traffic IP group will be disabled and none of the traffic IP addresses will be raised.
	Type: Boolean
	Required: false
	Default value: true
	Whether or not the source port should be taken into account when deciding which traffic manager should handle a request.
hash_source_port	Type: Boolean
	Required: false
	Default value: false
	Configure how traffic IPs are assigned to traffic managers in Single-Hosted mode
ip_assignment_mode	Type: Enum(String)
	Required: false
	Default value: "balanced"
	Permitted values:
	"alphabetic": Alphabetical order of traffic manager hostnames
	"balanced": Approximately balanced between traffic managers

Property	Description
	A table assigning traffic IP addresses to machines that should host them. Traffic IP addresses not specified in this table will automatically be assigned to a machine.
	• Type: Table
	Required: false
ip_mapping	Primary key:
	<ul> <li>ip (String): A traffic IP address (from the ipaddresses property). (Required)</li> </ul>
	Sub keys:
	traffic_manager (String): The name of the traffic manager that should host the IP address. (Required)
	The IP addresses that belong to the Traffic IP group.
ipaddresses	Type: Set(String)
ipadaresses	Required: false
	Default value: <none></none>
keeptogether	If set to Yes then all the traffic IPs will be raised on a single traffic manager. By default they're distributed across all active traffic managers in the traffic IP group.
	Type: Boolean
	Required: false
	Default value: false
location	The location in which the Traffic IP group is based.
	Type: Int
	Required: false
	Default value: <none></none>

Property	Description
machines	The traffic managers that can host the traffic IP group's IP addresses.  Type: Set(Reference(config-tm))  Required: false  Default value: <none></none>
mode	The method used to distribute traffic IPs across machines in the cluster. If "multihosted" is used then multicast must be set to an appropriate multicast IP address.  • Type: Enum(String)  • Required: false  • Default value: "singlehosted"  • Permitted values:  "ec2elastic": Use an EC2-Classic Elastic IP address.  "ec2vpcelastic": Use an EC2-VPC Elastic IP address.  "ec2vpcprivate": Use an EC2-VPC Private IP address.  "gceexternal": Use GCE External IP addresses.  "multihosted": Raise each address on every machine in the group (Multi-Hosted mode)  - IPv4 only  "rhi": Use route health injection to route traffic to the active machine - IPv4 only  "singlehosted": Raise each address on a single machine (Single-Hosted mode)

Property	Description
	The multicast IP address used to duplicate traffic to all traffic managers in the group.
multicast	Type: String
	Required: false
	Default value: <none></none>
	A note, used to describe this Traffic IP Group
note	Type: String
note	Required: false
	Default value: <none></none>
	The base BGP routing metric for this Traffic IP group. This is the advertised routing cost for the active traffic manager in the cluster. It can be used to set up inter-cluster failover.
rhi_bgp_metric_base	Type: UInt
	Required: false
	Default value: "10"
	The BGP routing metric offset for this Traffic IP group. This is the difference between the advertised routing cost for the active and passive traffic manager in the cluster.
rhi_bgp_passive_metric_ offset	• Type: UInt
	Required: false
	Default value: "10"
rhi_ospfv2_metric_base	The base OSPFv2 routing metric for this Traffic IP group. This is the advertised routing cost for the active traffic manager in the cluster. It can be used to set up inter-cluster failover.
	Type: UInt

Property	Description
	<ul><li>Required: false</li><li>Default value: "10"</li></ul>
rhi_ospfv2_passive_metric_ offset	The OSPFv2 routing metric offset for this Traffic IP group. This is the difference between the advertised routing cost for the active and passive traffic manager in the cluster.  • Type: UInt  • Required: false
	Default value: "10"  A list of protocols to be used for RHI. Currently must be 'ospf' or 'bgp' or both. The default, if empty, is 'ospf', which means that it is
rhi_protocols	<ul> <li>not possible to specify no protocol.</li> <li>Type: String</li> <li>Required: false</li> <li>Default value: "ospf"</li> </ul>
slaves	A list of traffic managers that are in 'passive' mode. This means that in a fully working environment, they will not have any traffic IP addresses assigned to them.  • Type: Set(Reference(config-tm))  • Required: false  • Default value: <none></none>

## **Traffic Manager**

URI Endpoint: /api/tm/8.3/config/active/traffic\_managers

The conf/zxtms directory contains a configuration file for each traffic manager in your cluster. The name of each file is the hostname of the traffic manager it represents. These files contain host-specific configuration data and on each installation of the software, the conf/../global.cfg file is sym-linked to the host's own configuration in the conf/zxtms directory. The files may contain a variety of configuration options that are configured in various locations under the System section of the Admin Server UI and the System section of the SOAP API and CLI.

Property	Description
adminMasterXMLIP	The Application Firewall master XML IP.
	Type: String
	Required: false
	Default value: "0.0.0.0"
	The Application Firewall slave XML IP.
adminSlaveXMLIP	Type: String
aummadvexivitir	Required: false
	Default value: "0.0.0.0"
	The table of network cards of a hardware appliance
	• Type: Table
	Required: false
appliance_card	Primary key:
	name (String): Network card PCI ID (Required)
	Sub keys:
	interfaces (List(String)): The order of the interfaces of a network card (Required)
	label (String): The labels of the installed network cards
appliance_sysctl	Custom kernel parameters applied by the user with sysctl interface
	• Type: Table

Property	Description
	Required: false
	Primary key:
	<ul> <li>sysctl (String): The name of the kernel parameter, e.g. net.ipv4.forward (Required)</li> </ul>
	Sub keys:
	description (String): Associated optional description for the sysctl
	value (String): The value of the kernel parameter (Required)
	The Application Firewall Authentication Server IP.
	Type: String
authenticationServerIP	Required: false
	Default value: "0.0.0.0"
	Cloud platform where the traffic manager is running.
alassed relatification	Type: String
cloud_platform	Required: false
	Default value: <none></none>
	This is the location of the local traffic manager is in.
	Type: String
location	Required: false
	Default value: <none></none>
	Replace Traffic Manager name with an IP address.
nameip	Type: String
	Required: false

Property	Description
	Default value: <none></none>
	How many worker threads the Web Accelerator process should create to optimise content. By default, one thread will be created for each CPU on the system.
num_aptimizer_threads	Type: UInt
	Required: false
	Default value: <none></none>
	The number of worker processes the software will run. By default, one child process will be created for each CPU on the system. You may wish to reduce this to effectively "reserve" CPU(s) for other processes running on the host system.
num_children	Type: UInt
	Required: false
	Default value: <none></none>
	The number of Application Firewall decider process to run.
numberOfCPUs	Type: UInt
Humberoteros	Required: false
	Default value: <none></none>
restServerPort	The Application Firewall REST Internal API port, this port should not be accessed directly
	Type: UInt
	Required: false
	Default value: <none></none>
trafficip	A table mapping interfaces to networks, used by the traffic manager to select which interface to raise a Traffic IP on.

Property	Description
	<ul> <li>Type: Table</li> <li>Required: false</li> <li>Primary key: <ul> <li>name (String): A network interface. (Required)</li> </ul> </li> <li>Sub keys:</li> </ul>
	<ul> <li>networks (Set(String)): A set of IP/masks to which the network interface maps. (Required)</li> </ul>
updaterIP	The Application Firewall Updater IP.  Type: String  Required: false  Default value: "0.0.0.0"
Properties for the "admin" sect	ion:
hsts_enable	Whether or not HSTS (RFC 6797) is enabled for admin server connections.  Type: Boolean Required: false Default value: false
hsts_max_age	The number of seconds that the HSTS header field max-age will be set to  Type: UInt Required: false Default value: "31536000"
Properties for the "appliance" s	section:

Property	Description
disable_kpti	Whether the traffic manager appliance should run without kernel page table isolation (KPTI). KPTI provides protection to prevent unprivileged software from being potentially able to read arbitrary memory from the kernel (i.e. the Meltdown attack, CVE-2017-5754); however this protection incurs a general system performance penalty. If you are running trusted software on the appliance, and the trade-off between performance at the cost of 'defense in depth' favors the former in your deployment, you may wish to enable this configuration key. If you are unsure, it is recommended that you leave this key disabled, which is also the default.  • Type: Boolean  • Required: false  • Default value: false
dnscache	The DNS cache setting the appliance should use and place in /etc/systemd/resolved.conf.  Type: Boolean Required: false Default value: true
dnssec	The DNSSEC setting the appliance should use and place in /etc/systemd/resolved.conf.  Type: Enum(String)  Required: false  Default value: "no"  Permitted values:  "allow_downgrade": Use DNSSEC when available  "no": DNSSEC disabled

Property	Description
	"yes": DNSSEC enabled
	The default gateway.
	Type: String
gateway_ipv4	Required: false
	Default value: <none></none>
	The default IPv6 gateway.
	Type: String
gateway_ipv6	Required: false
	Default value: <none></none>
	Name (hostname.domainname) of the appliance.
h a storage	Type: String
hostname	Required: false
	Default value: <none></none>
	A table of hostname to static ip address mappings, to be placed in the /etc/hosts file.
	Type: Table
hosts	Required: false
	Primary key:
	name (String): The name of a host. (Required)
	Sub keys:
	ip_address (String): The static IP address of the host.  (Required)
if	A table of network interface specific settings.

Property	Description
	Type: Table
	Required: false
	Primary key:
	name (String): A network interface name. (Required)
	Sub keys:
	autoneg (Boolean): Whether auto-negotiation should be enabled for the interface.
	bmode (Enum(String)): The trunking mode used for the interface (only 802.3ad is currently supported).
	Permitted values:
	"802_3ad": IEEE 802.3ad
	"balance_alb": Adaptive Load Balancing
	bond (String): The trunk of which the interface should be a member.
	duplex (Boolean): Whether full-duplex should be enabled for the interface.
	mode (Enum(String)): Set the configuriation mode of an interface, the interface name is used in place of the * (asterisk).
	Permitted values:
	"dhcp": DHCP
	"static": Static
	mtu (UInt): The maximum transmission unit (MTU) of the interface.
	speed (Enum(String)): The speed of the interface.

Property	Description
	Permitted values:
	"10": 10Mbs
	"100": 100Mbs
	"1000": 1Gbs
	"10000": 10Gbs
	"100000": 100Gbs
	"40000": 40Gbs
	A table of network interfaces and their network settings.
	• Type: Table
	Required: false
	Primary key:
	name (String): A network interface name. (Required)
ip	Sub keys:
	addr (String): The IP address for the interface.  (Required)
	isexternal (Boolean): Whether the interface is externally facing.
	mask (String): The IP mask (netmask) for the interface.  (Required)
ipmi_lan_access	Whether IPMI LAN access should be enabled or not.
	• Type: Boolean
	Required: false
	Default value: false
ipmi_lan_addr	The IP address of the appliance IPMI LAN channel.

Property	Description
	Type: String
	Required: false
	Default value: <none></none>
	The default gateway of the IPMI LAN channel.
inmi lan gataway	Type: String
ipmi_lan_gateway	Required: false
	Default value: "0.0.0.0"
	The addressing mode the IPMI LAN channel operates.
	Type: Enum(String)
	Required: false
ipmi_lan_ipsrc	Default value: "static"
	Permitted values:
	"dhcp": Address obtained by DHCP
	"static": Static IP Address
	Set the IP netmask for the IPMI LAN channel.
,	Type: String
ipmi_lan_mask	Required: false
	Default value: <none></none>
ipv4_forwarding	Whether or not IPv4 forwarding is enabled.
	Type: Boolean
	Required: false
	Default value: false
ipv6_forwarding	Whether or not IPv6 forwarding is enabled.

Property	Description
	Type: Boolean
	Required: false
	Default value: false
	Whether or not the license agreement has been accepted. This determines whether or not the Initial Configuration wizard is displayed.
licence_agreed	Type: Boolean
	Required: false
	Default value: false
	Whether or not the software manages the Azure policy routing.
managaazurarautas	Type: Boolean
manageazureroutes	Required: false
	Default value: true
	Whether or not the software manages the EC2 config.
managaaslaant	Type: Boolean
manageec2conf	Required: false
	Default value: true
	Whether or not the software manages the GCE routing.
	Type: Boolean
managegceroutes	Required: false
	Default value: true
manageiptrans	Whether or not the software manages the IP transparency
	Type: Boolean

Property	Description
	Required: false
	Default value: true
	Whether or not the software manages the system configuration for reserved ports
managereservedports	Type: Boolean
	Required: false
	Default value: true
	Whether or not the software manages return path routing. If disabled, the appliance won't modify iptables / rules / routes for this feature.
managereturnpath	Type: Boolean
	Required: false
	Default value: true
	Whether or not the software manages the system services
	Type: Boolean
manageservices	Required: false
	Default value: true
	Whether or not the software manages the EC2-VPC secondary IPs.
	Type: Boolean
managevpcconf	Required: false
	Default value: true
name_servers	The IP addresses of the nameservers the appliance should use and place in /etc/systemd/resolved.conf.
	Type: Set(String)

Property	Description
	Required: false
	Default value: <none></none>
	The NTP servers the appliance should use to synchronize its clock.
	Type: List(String)
ntpservers	Required: false
	Default value: "0.zeus.pool.ntp.org 1.zeus.pool.ntp.org     2.zeus.pool.ntp.org 3.zeus.pool.ntp.org"
	A table of destination IP addresses and routing details to reach them.
	Type: Table
	Required: false
	Primary key:
	name (String): A destination IP address. (Required)
routes	Sub keys:
	gw (String): The gateway IP to configure for the route.  (Required)
	if (String): The network interface to configure for the route. (Required)
	mask (String): The netmask to apply to the IP address.  (Required)
search_domains	The search domains the appliance should use and place in /etc/systemd/resolved.conf.
	Type: Set(String)
	Required: false
	Default value: <none></none>

Property	Description
ssh_enabled	Whether or not the SSH server is enabled on the appliance.  Type: Boolean  Required: false  Default value: true
ssh_password_allowed	Whether or not the SSH server allows password based login.  Type: Boolean  Required: false  Default value: true
ssh_port	The port that the SSH server should listen on.  Type: UInt  Required: false  Default value: "22"
timezone	The timezone the appliance should use. This must be a path to a timezone file that exists under /usr/share/zoneinfo/.  • Type: String  • Required: false  • Default value: "US/Pacific"
vlans	The VLANs the software should raise. A VLAN should be configured using the format <dev>.<vlanid>, where <dev> is the name of a network device that exists in the host system, eth0.100 for example.  • Type: Set(String)  • Required: false  • Default value: <none></none></dev></vlanid></dev>
Properties for the "cluster_com	ms" section:

Property	Description
allow_update	Whether or not this instance of the software can send configuration updates to other members of the cluster. When not clustered this key is ignored. When clustered the value can only be changed by another machine in the cluster that has allow_update set to true. If set to false then it will not be possible to log into the admin server for this instance.
	Type: Boolean
	Required: false
	Default value: true
bind_ip	The IP address that the software should bind to for internal administration communications. See also port. If the software is not part of a cluster the default is to use 127.0.0.1 and there should be no reason to touch this setting. If the software is part of a cluster then the default is to listen on all raised IPs, in this case an alternative configuration is to listen on a single IP address. This may be useful if you have a separate management network and wish to restrict control messages to it. It is important to ensure that the allowed_update_hosts (in the Global Settings resource) is compatible with the IP configured here.  • Type: String  • Required: false
	Default value: "*"
external_ip	This is the optional external ip of the traffic manager, which is used to circumvent natting when traffic managers in a cluster span different networks.
	Type: String
	Required: false
	Default value: <none></none>

Property	Description
port	The port that the software should listen on for internal administration communications. See also bind_ip.  • Type: UInt
	<ul><li>Required: false</li><li>Default value: "9080"</li></ul>
Properties for the "ec2" section	
,	List of MAC addresses of interfaces which the traffic manager can use to associate the EC2 elastic IPs (Traffic IPs) to the instance.
trafficips_public_enis	Type: Set(String)
	Required: false
	Default value: <none></none>
Properties for the "fault_tolera	nce" section:
	The BGP router id If set to empty, then the IPv4 address used to communicate with the default IPv4 gateway is used instead.  Specifying 0.0.0.0 will stop the traffic manager routing software from running the BGP protocol.
bgp_router_id	Type: String
	Required: false
	Default value: <none></none>
ospfv2_ip	The traffic manager's permanent IPv4 address which the routing software will use for peering and transit traffic, and as its OSPF router ID. If set to empty, then the address used to communicate with the default IPv4 gateway is used instead. Specifying 0.0.0.0 will stop the traffic manager routing software from running the OSPF protocol.
	Type: String
	Required: false

Property	Description	
	Default value: <none></none>	
ospfv2_neighbor_addrs	The IP addresses of routers which are expected to be found as OSPFv2 neighbors of the traffic manager. A warning will be reported if some of the expected routers are not peered, and an error will be reported if none of the expected routers are peered. An empty list disables monitoring. The special value %gateway% is a placeholder for the default gateway.	
	Type: Set(String)	
	Required: false	
	Default value: "%gateway%"	
Properties for the "iptables" section:		
config_enabled	Whether the Traffic Manager should configure the iptables built-in chains to call Traffic Manager defined rules (e.g. the IP transparency chain). This should only be disabled in case of conflict with other software that manages iptables, e.g. firewalls. When disabled, you will need to add rules manually to use these features - see the user manual for details.	
	Type: Boolean	
	Required: false	
	Default value: true	
Properties for the "iptrans" sec	tion:	
	The netfilter forwarding mark to use for IP transparency rules	
fwmark	Type: UInt	
	Required: false	
	Default value: "320"	
iptables_enabled	Whether IP transparency may be used via netfilter/iptables. This requires the iptables socket extension.	

Property	Description
	Type: Boolean
	Required: false
	Default value: true
	The special routing table ID to use for IP transparency rules
	Type: UInt
routing_table	Required: false
	Default value: "320"
Properties for the "java" section	า:
	The port the Java Extension handler process should listen on. This port will be bound for localhost communications only.
port	Type: UInt
	Required: false
	Default value: "9060"
Properties for the "remote_lice	nsing" section:
	The e-mail address sent as part of a remote licensing request.
anail adduses	Type: String
email_address	Required: false
	Default value: <none></none>
	A free-text field sent as part of a remote licensing request.
	Type: String
message	Required: false
	Default value: <none></none>
Properties for the "rest_api" section:	

Property	Description
bind_ips	A list of IP Addresses which the REST API will listen on for connections. The list should contain IP addresses (IPv4 or IPv6) or a single entry containing an asterisk (*). This indicates that the REST API should listen on all IP Addresses.
	Type: Set(String)
	Required: false
	Default value: "*"
	The port on which the REST API should listen for requests.
nort	Type: UInt
port	Required: false
	Default value: "9070"
Properties for the "snmp" section:	
	Restrict which IP addresses can access the SNMP command responder service. The value can be all, localhost, or a list of IP CIDR subnet masks. For example 10.100.0.0/16 would allow connections from any IP address beginning with 10.100.
allow	Type: Set(String)
	Required: false
	Default value: "all"
auth_password	The authentication password. Required (minimum length 8 characters) if security_level includes authentication.
	Type: Password
	Required: false
	Default value: <none></none>
bind_ip	The IP address the SNMP service should bind its listen port to. The value * (asterisk) means SNMP will listen on all IP addresses.

Property	Description
	Type: String
	Required: false
	Default value: "*"
	The community string required for SNMPv1 and SNMPv2c commands. (If empty, all SNMPv1 and SNMPv2c commands will be rejected).
community	Type: String
	Required: false
	Default value: "public"
	Whether or not the SNMP command responder service should be enabled on this traffic manager.
enabled	Type: Boolean
	Required: false
	Default value: false
	The hash algorithm for authenticated SNMPv3 communications.
hash_algorithm	Type: Enum(String)
	Required: false
	Default value: "md5"
	Permitted values:
	"md5": MD5
	"sha1": SHA-1
port	The port the SNMP command responder service should listen on. The value default denotes port 161 if the software is running with root privileges, and 1161 otherwise.
	Type: String

Property	Description
	Required: false
	Default value: "default"
	The privacy password. Required (minimum length 8 characters) if security_level includes privacy (message encryption).
priv_password	Type: Password
	Required: false
	Default value: <none></none>
	The security level for SNMPv3 communications.
	Type: Enum(String)
	Required: false
security_level	Default value: "noauthnopriv"
	Permitted values:
	"authnopriv": Authentication only
	"authpriv": Authentication and Privacy
	"noauthnopriv": No Authentication, No Privacy
username	The username required for SNMPv3 commands. (If empty, all SNMPv3 commands will be rejected).
	Type: String
	Required: false
	Default value: <none></none>

# **TrafficScript Authenticator**

URI Endpoint: /api/tm/8.3/config/active/rule\_authenticators

TrafficScript authenticators define remote authentication services that can be queried via a TrafficScript rule.

Property	Description
host	The hostname or IP address of the remote authenticator.
	Type: String
	Required: false
	Default value: <none></none>
	A description of the authenticator.
note	Type: FreeformString
note	Required: false
	Default value: <none></none>
	The port on which the remote authenticator should be contacted.
nort	Type: UInt
port	Required: false
	Default value: "389"
Properties for the "Idap" section	on:
attributes	A list of attributes to return from the search. If blank, no attributes will be returned. If set to '*' then all user attributes will be returned.
	Type: Set(String)
	Required: false
	Default value: <none></none>
bind_dn	The distinguished name (DN) of the 'bind' user. The traffic manager will connect to the LDAP server as this user when searching for user records.
	Type: String
	Required: false

Property	Description
	Default value: <none></none>
bind_password	The password for the bind user.
	Type: Password
	Required: false
	Default value: <none></none>
	The filter used to locate the LDAP record for the user being authenticated. Any occurrences of '%u' in the filter will be replaced by the name of the user being authenticated.
filter	Type: String
	Required: false
	Default value: <none></none>
	The base distinguished name (DN) under which user records are located on the server.
filter_base_dn	Type: String
	Required: false
	Default value: <none></none>
ssl_cert	The SSL certificate that the traffic manager should use to validate the remote server. If no certificate is specified then no signature validation will be performed.
	Type: Reference(config-ssl-cacrl)
	Required: false
	Default value: <none></none>
ssl_enabled	Whether or not to enable SSL encryption to the LDAP server.
	Type: Boolean
	Required: false

Property	Description
	Default value: false
ssl_type	The type of LDAP SSL encryption to use.
	Type: Enum(String)
	Required: false
	Default value: "Idaps"
	Permitted values:
	"Idaps": LDAPS
	"starttls": Start TLS

## **Trusted SAML Identity Provider**

URI Endpoint: /api/tm/8.3/config/active/saml/trustedidps

Configuration for SAML IDP trust relationships.

Property	Description
add_zlib_header	Whether or not to add the zlib header when compressing the AuthnRequest
	Type: Boolean
	Required: false
	Default value: false
certificate	The certificate used to verify Assertions signed by the identity provider
	Type: String
	Required: true
	Default value: <none></none>

Property	Description
entity_id	The entity id of the IDP
	Type: String
entity_id	Required: true
	Default value: <none></none>
strict_verify	Whether or not SAML responses will be verified strictly
	Type: Boolean
	Required: false
	Default value: true
url	The IDP URL to which Authentication Requests should be sent
	Type: String
	Required: true
	Default value: <none></none>

#### **User Authenticator**

URI Endpoint: /api/tm/8.3/config/active/user\_authenticators

A user authenticator is used to allow access to the UI and REST API by querying a remote authentication service.

Property	Description
description	A description of the authenticator.
	Type: String
	Required: false
	Default value: <none></none>

Whether or not this authenticator is enabled.  Type: Boolean Required: false Default value: false The type and protocol used by this authentication service. Type: Enum(String) Required: true Default value: <none> Permitted values:</none>
<ul> <li>Required: false</li> <li>Default value: false</li> </ul> The type and protocol used by this authentication service. <ul> <li>Type: Enum(String)</li> <li>Required: true</li> <li>Default value: <none></none></li> </ul>
<ul> <li>Default value: false</li> <li>The type and protocol used by this authentication service.</li> <li>Type: Enum(String)</li> <li>Required: true</li> <li>Default value: <none></none></li> </ul>
<ul> <li>The type and protocol used by this authentication service.</li> <li>Type: Enum(String)</li> <li>Required: true</li> <li>Default value: <none></none></li> </ul>
<ul><li>Type: Enum(String)</li><li>Required: true</li><li>Default value: <none></none></li></ul>
<ul><li>Required: true</li><li>Default value: <none></none></li></ul>
Default value: <none></none>
Permitted values:
i citilitica valaes.
"ldap": LDAP
"radius": RADIUS
"tacacs_plus": TACACS+
The base DN (Distinguished Name) under which directory searches will be applied. The entries for your users should all appear under his DN. An example of a typical base DN is: OU=users, DC=mycompany, DC=local
Type: String
Required: false
Default value: <none></none>
Template to construct the bind DN (Distinguished Name) from the username. The string %u will be replaced by the username. Examples: %u@mycompany.local for Active Directory or cn=%u, dc=mycompany, dc=local for both LDAP and Active Directory.  • Type: String
h h is

Property	Description
	Required: false
	Default value: <none></none>
	The bind DN (Distinguished Name) for a user can either be searched for in the directory using the base distinguished name and filter values, or it can be constructed from the username.
	Type: Enum(String)
	Required: false
dn_method	Default value: "none"
	Permitted values:
	"construct": Construct
	"none": No setting configured
	"search": Search
	If the group attribute is not defined, or returns no results for the user logging in, the group named here will be used. If not specified, users will be denied access to the traffic manager if no groups matching a Permission Group can be found for them in the directory.
fallback_group	Type: String
	Required: false
	Default value: <none></none>
filter	A filter that can be used to extract a unique user record located under the base DN (Distinguished Name). The string %u will be replaced by the username. This filter is used to find a user's bind DN when dn_method is set to "Search", and to extract group information if the group filter is not specified. Examples: sAMAccountName=%u for Active Directory, or uid=%u for some Unix LDAP schemas.
	Type: String

Property	Description
	Required: false
	Default value: <none></none>
	The LDAP attribute that gives a user's group. If there are multiple entries for the attribute all will be extracted and they'll be lexicographically sorted, then the first one to match a Permission Group name will be used.
group_attribute	Type: String
	Required: false
	Default value: <none></none>
group_field	The sub-field of the group attribute that gives a user's group. For example, if group_attribute is memberOf and this retrieves values of the form CN=mygroup, OU=groups, OU=users, DC=mycompany, DC=local you would set group_field to CN. If there are multiple matching fields only the first matching field will be used.  • Type: String  • Required: false
	Default value: <none></none>
group_filter	If the user record returned by filter does not contain the required group information you may specify an alternative group search filter here. This will usually be required if you have Unix/POSIX-style user records. If multiple records are returned the list of group names will be extracted from all of them. The string %u will be replaced by the username. Example: (&(memberUid=%u)(objectClass=posixGroup))
	Type: String
	Required: false
	Default value: <none></none>
port	The port to connect to the LDAP server on.

Property	Description
	Type: UInt
	Required: false
	Default value: "389"
search_dn	The bind DN (Distinguished Name) to use when searching the directory for a user's bind DN. You can leave this blank if it is possible to perform the bind DN search using an anonymous bind.
	Type: String
	Required: false
	Default value: <none></none>
search_password	If binding to the LDAP server using search_dn requires a password, enter it here.
	Type: Password
	Required: false
	Default value: <none></none>
server	The IP or hostname of the LDAP server.
	Type: String
	Required: false
	Default value: <none></none>
ssl	The type of TLS encryption, if any, to use. Usually STARTTLS will be used with port 389, and LDAPS with port 636. A Certificate Authority that the LDAP server's certificate chains back to must be present in the "Admin Certificate Authorities and Certificate Revocation Lists Catalog" under "SSL catalogs", otherwise the connection will fail.
	Type: Enum(String)
	Required: false

Property	Description
Порену	·
	Default value: "none"
	Permitted values:
	"ldaps": LDAPS
	"none": None
	"starttls": STARTTLS
timeout	Connection timeout in seconds.
	Type: UInt
	Required: false
	Default value: "30"
Properties for the "radius" section:	
fallback_group	If no group is found using the vendor and group identifiers, or the group found is not valid, the group specified here will be used.
	Type: String
	Required: false
	Default value: <none></none>
group_attribute	The RADIUS identifier for the attribute that specifies an account's group. May be left blank if fallback group is specified.
	Type: UInt
	Required: false
	Default value: "1"
group_vendor	The RADIUS identifier for the vendor of the RADIUS attribute that specifies an account's group. Leave blank if using a standard attribute (i.e. for Filter-Id set group_attribute to 11).
	Type: UInt

Property	Description
	Required: false
	Default value: "7146"
	This value is sent to the RADIUS server.
nos identifies	Type: String
nas_identifier	Required: false
	Default value: <none></none>
	This value is sent to the RADIUS server, if left blank the address of the interfaced used to connect to the server will be used.
nas_ip_address	Type: String
	Required: false
	Default value: <none></none>
	The port to connect to the RADIUS server on.
nort	• Type: UInt
port	Required: false
	Default value: "1812"
	Secret key shared with the RADIUS server.
secret	Type: Password
seciet	Required: false
	Default value: <none></none>
	The IP or hostname of the RADIUS server.
convor	Type: String
server	Required: false
	Default value: <none></none>

Property	Description
	Connection timeout in seconds.
4:	• Type: UInt
timeout	Required: false
	Default value: "30"
Properties for the "tacacs_plus	" section:
	Authentication type to use.
	Type: Enum(String)
	Required: false
auth_type	Default value: "pap"
	Permitted values:
	"ascii": ASCII
	"рар": РАР
	If group_service is not used, or no group value is provided for the user by the TACACS+ server, the group specified here will be used. If this is not specified, users with no TACACS+ defined group will be denied access.
fallback_group	Type: String
	Required: false
	Default value: <none></none>
	The TACACS+ "service" field that provides each user's group.
	Type: String
group_field	Required: false
	Default value: "permission-group"
group_service	The TACACS+ "service" that provides each user's group field.

Property	Description
	Type: String
	Required: false
	Default value: "zeus"
	The port to connect to the TACACS+ server on.
	Type: UInt
port	Required: false
	Default value: "49"
	Secret key shared with the TACACS+ server.
	Type: Password
secret	Required: false
	Default value: <none></none>
	The IP or hostname of the TACACS+ server.
	Type: String
server	Required: false
	Default value: <none></none>
	Connection timeout in seconds.
timoqut	• Type: UInt
timeout	Required: false
	Default value: "30"

## **User Group**

URI Endpoint: /api/tm/8.3/config/active/user\_groups

Permission groups specify permissions for groups of users. These groups can be given read-write or read-only access to different parts of the configuration hierarchy. Each group will contain a table of permissions. Each table entry has a name that corresponds to a part of the configuration hierarchy, and a corresponding access level. The access level may have values of either none, ro (read only, this is the default), or full. Some permissions have sub-permissions, these are denoted by following the parent permission name with a colon (:) followed by the sub-permission name. The built-in admin group has a special permission key of all with the value full, this must not be altered for the admin group but can be used in other group configuration files to change the default permission level for the group.

Property	Description
description	A description for the group.  Type: String Required: false Default value: <none></none>
password_expire_time	Members of this group must renew their passwords after this number of days. To disable password expiry for the group set this to 0 (zero). Note that this setting applies only to local users.  • Type: UInt  • Required: false  • Default value: <none></none>
permissions	A table defining which level of permission this group has for specific configuration elements.  Type: Table Required: false Primary key:  name (String): Configuration element to which this group has a level of permission. (Required)  Sub keys:

Property	Description
	access_level (String): Permission level for the configuration element (none, ro or full) (Required)
	Inactive UI sessions will timeout after this number of seconds. To disable inactivity timeouts for the group set this to 0 (zero).
timeout	Type: UInt
	Required: false
	Default value: "30"

## **Virtual Server**

URI Endpoint: /api/tm/8.3/config/active/virtual\_servers

The conf/vservers directory contains configuration files that define virtual servers. The name of a file is the name of the virtual server it defines. Virtual servers can be configured under the Services > Virtual Servers section of the Admin Server UI or by using functions under the VirtualServer section of the SOAP API and CLI.

Prope rty	Description	
	The bandwidth management class that this server should use, if any.	
band width_ class	Type: Reference(config-bandwidth)	
	Required: false	
	Default value: <none></none>	
compl etion_ rules	Rules that are run at the end of a transaction, in order, comma separated.	
	Type: List(String)	
	Required: false	
	Default value: <none></none>	

Prope rty	Description
conne ct_ timeo ut	The time, in seconds, for which an established connection can remain idle waiting for some initial data to be received from the client. The initial data is defined as a complete set of request headers for HTTP, SIP and RTSP services, or the first byte of data for all other services. A value of 0 will disable the timeout.  • Type: UInt  • Required: false  • Default value: "10"
enabl ed	Whether the virtual server is enabled.  Type: Boolean  Required: false  Default value: false
glb_ servic es	The associated GLB services for this DNS virtual server.  • Type: Set(String)  • Required: false  • Default value: <none></none>
listen_ on_ any	Whether to listen on all IP addresses  Type: Boolean  Required: false  Default value: true
listen_ on_ hosts	Hostnames and IP addresses to listen on  Type: Set(String)  Required: false  Default value: <none></none>

Prope rty	Description
listen_ on_ traffic_ ips	Traffic IP Groups to listen on  Type: Set(String)  Required: false  Default value: <none></none>
max_ concu rrent_ conne ctions	The maximum number of concurrent TCP connections that will be handled by this virtual server. If set to a non-zero value, the traffic manager will limit the number of concurrent TCP connections that this virtual server will accept to the value specified. When the limit is reached, new connections to this virtual server will not be accepted. If set to 0 the number of concurrent TCP connections will not be limited.  • Type: UInt  • Required: false  • Default value: <none></none>
note	A description for the virtual server.  Type: FreeformString  Required: false  Default value: <none></none>
pool	The default pool to use for traffic.  Type: Reference(config-pool) Required: true Default value: <none></none>
port	The port on which to listen for incoming connections.  Type: UInt Required: true Default value: <none></none>

Prope rty	Description
protec tion_ class	The service protection class that should be used to protect this server, if any.  Type: String  Required: false  Default value: <none></none>
protoc	The protocol that the virtual server is using.  Type: Enum(String)  Required: false  Default value: "http"  Permitted values:  "client_first": Generic client first  "dns": DNS (UDP)  "dns_tcp": DNS (TCP)  "ftp": FTP  "https": SSL (HTTPS)  "imaps": SSL (IMAPS)  "imapv2": IMAPv2  "imapv4": IMAPv4  "ldap": LDAP  "ldaps": SSL (LDAPS)  "pop3": POP3

Prope rty	Description
	"pop3s": SSL (POP3S)
	"rtsp": RTSP
	"server_first": Generic server first
	"siptcp": SIP (TCP)
	"sipudp": SIP (UDP)
	"smtp": SMTP
	"ssl": SSL
	"stream": Generic streaming
	"telnet": Telnet
	"udp": UDP
	"udpstreaming": UDP - Streaming
proxy_	Expect connections to the traffic manager to be prefixed with a PROXY protocol header. If enabled, the information contained in the PROXY header will be available in TrafficScript. Connections that are not prefixed with a valid PROXY protocol header will be discarded.
protoc	Type: Boolean
ol	Required: false
	Default value: false
	Rules to be applied to incoming requests, in order, comma separated.
reque st_	Type: List(String)
rules	Required: false
	Default value: <none></none>

Prope rty	Description	
respo nse_ rules	Rules to be applied to responses, in order, comma separated.  • Type: List(Reference(config-trafficscript))  • Required: false  • Default value: <none></none>	
slm_ class	The service level monitoring class that this server should use, if any.  Type: Reference(config-slm)  Required: false  Default value: <none></none>	
ssl_ decry pt	<ul> <li>Whether or not the virtual server should decrypt incoming SSL traffic.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>	
transp arent	Whether or not bound sockets should be configured for transparent proxying.  Type: Boolean Required: false Default value: false	
Properti	Properties for the "aptimizer" section:	
enabl ed	<ul> <li>Whether the virtual server should optimize web content.</li> <li>Type: Boolean</li> <li>Required: false</li> <li>Default value: false</li> </ul>	
profile	A table of Aptimizer profiles and the application scopes that apply to them.	

Prope rty	Description		
	Type: Table		
	Required: false		
	Primary key:		
	name (String): The name of an Aptimizer acceleration profile. (Required)		
	Sub keys:		
	<ul> <li>urls (Set(String)): The application scopes which apply to the acceleration profile. (Required)</li> </ul>		
Properti	operties for the "auth" section:		
	Name of the Trusted Identity Provider configuration to use. To create Identity Providers, please visit section Trusted Identity Providers		
saml_	Type: String		
idp	Required: false		
	Default value: <none></none>		
	The NameID format to request and expect from the identity provider.		
	Type: Enum(String)		
	Required: false		
saml_ namei	Default value: "none"		
d_ format	Permitted values:		
	"emailaddress": emailAddress		
	"none": none		
	"unspecified": unspecified		

Prope rty	Description
saml_ sp_ acs_ url	The 'Assertion Consumer Service' endpoint for the SAML service provider on this virtual server, ie the endpoint to which the identity provider will cause the user agent to send SAML assertions. This should be an HTTPS URL, must be in the same cookie domain as all hostnames used by the end user to access the virtual server (see cookie configuration) and the port must be the port on which this virtual server is listening. It must match the URI placed by the identity provider in the 'Recipient' attribute in the SAML assertion, if present.  • Type: String  • Required: false  • Default value: <none></none>
saml_ sp_ entity_ id	The entity ID to be used by the SAML service provider function on this virtual server. This should usually be a URL, or a URN, however it may be any string. It must match the entity ID placed by the identity provider in the 'Audience' field in the SAML assertion.  • Type: String  • Required: false  • Default value: <none></none>
saml_ time_ tolera nce	Time tolerance on authentication checks. When checking time-stamps and expiry dates against the current time on the system, allow a tolerance of this many seconds. For example, if a SAML response contains a 'NotOnOrAfter' that is 4 seconds in the past according to the local time, and the tolerance is set to 5 seconds, it will still be accepted. This is to prevent a lack of clock synchronization from resulting in rejection of SAML responses.  • Type: UInt  • Required: false  • Default value: "5"

Prope rty	Description
sessio	Attributes of cookie used for authentication session.
n_ cooki	Type: String
e_ attrib	Required: false
utes	Default value: "HttpOnly; SameSite=Strict"
sessio	Name of cookie used for authentication session.
n_	Type: String
cooki e_	Required: false
name	Default value: "VS_SamISP_Auth"
sessio	Whether or not to include state of authentication sessions stored encrypted on the client as plaintext in the logs.
n_log_ extern	Type: Boolean
al_	Required: false
state	Default value: false
	Timeout on authentication session.
sessio n_	Type: UInt
timeo	Required: false
	Default value: "7200"
	Type of authentication to apply to requests to the virtual server.
	Type: Enum(String)
type	Required: false
	Default value: "none"
	Permitted values:

Prope rty	Description
	"none": None
	"saml_sp": SAML Service Provider
	Whether or not detailed messages about virtual server authentication should be written to the error log.
verbo	Type: Boolean
se	Required: false
	Default value: false
Properti	es for the "connection" section:
	Whether or not the virtual server should use keepalive connections with the remote clients.
keepal	Type: Boolean
ive	Required: false
	Default value: true
keepal	The length of time that the virtual server should keep an idle keepalive connection before discarding it. A value of 0 (zero) will mean that the keepalives are never closed by the traffic manager.
ive_ timeo	Type: UInt
ut	Required: false
	Default value: "10"
max_ client_ buffer	The amount of memory, in bytes, that the virtual server should use to store data sent by the client through one TCP connection or HTTP/2 stream. Larger values will use more memory, but will minimise the number of read() and write() system calls that the traffic manager must perform.
	Type: UInt
	Required: false

Prope rty	Description
	Default value: "65536"
max_ serve	The amount of memory, in bytes, that the virtual server should use to store data returned by the server through one TCP connection. Larger values will use more memory, but will minimise the number of read() and write() system calls that the traffic manager must perform.
r_ buffer	Type: UInt
Sanci	Required: false
	Default value: "65536"
max_ transa ction_	The total amount of time a transaction can take, counted from the first byte being received until the transaction is complete. For HTTP, this can mean all data has been written in both directions, or the connection has been closed; in most other cases it is the same as the connection being closed. The default value of 0 means there is no maximum duration, i.e., transactions can take arbitrarily long if none of the other timeouts occur.
durati on	Type: UInt
	Required: false
	Default value: <none></none>
serve r_first_ banne	If specified, the traffic manager will use the value as the banner to send for server-first protocols such as FTP, POP, SMTP and IMAP. This allows rules to use the first part of the client data (such as the username) to select a pool. The banner should be in the correct format for the protocol, e.g. for FTP it should start with "220"  • Type: String
r	Required: false
	Default value: <none></none>
timeo ut	A connection should be closed if no additional data has been received for this period of time. A value of 0 (zero) will disable this timeout.
	Type: UInt

Prope rty	Description
	Required: false
	Default value: "300"
Properti	es for the "connection_errors" section:
	The error message to be sent to the client when the traffic manager detects an internal or backend error for the virtual server.
error_	Type: Reference(config-extra-file)
file	Required: false
	Default value: "Default"
Properti	es for the "cookie" section:
	The way in which the traffic manager should rewrite the domain portion of any cookies set by a back-end web server.
	Type: Enum(UInt)
	Required: false
domai	Default value: "no_rewrite"
n	Permitted values:
	"no_rewrite": Do not rewrite the domain
	"set_to_named": Rewrite the domain to the named domain value
	"set_to_request": Rewrite the domain to the host header of the request
new_ domai n	The domain to use when rewriting a cookie's domain to a named value.
	Type: String
	Required: false
	Default value: <none></none>

Prope rty	Description	
path_ regex	If you wish to rewrite the path portion of any cookies set by a back-end web server, provide a regular expression to match the path:	
	Type: String	
	Required: false	
	Default value: <none></none>	
	If cookie path regular expression matches, it will be replaced by this substitution.  Parameters \$1-\$9 can be used to represent bracketed parts of the regular expression.	
path_ replac	Type: String	
е	Required: false	
	Default value: <none></none>	
	Whether or not the traffic manager should modify the "secure" tag of any cookies set by a back-end web server.	
	Type: Enum(UInt)	
	Required: false	
secure	Default value: "no_modify"	
	Permitted values:	
	"no_modify": Do not modify the 'secure' tag	
	"set_secure": Set the 'secure' tag	
	"unset_secure": Unset the 'secure' tag	
Properti	Properties for the "dns" section:	
edns_	Enable/Disable use of EDNS client subnet option	
client_ subne t	Type: Boolean	
	Required: false	

Prope rty	Description
	Default value: true
	EDNS UDP size advertised in responses.
edns_	Type: UInt
udpsiz e	Required: false
	Default value: "4096"
	Maximum UDP answer size.
max_	Type: UInt
udpsiz e	Required: false
	Default value: "4096"
	Response record ordering.
	Type: Enum(String)
	Required: false
rrset_ order	Default value: "fixed"
	Permitted values:
	"cyclic": Cyclic
	"fixed": Fixed
verbo se	Whether or not the DNS Server should emit verbose logging. This is useful for diagnosing problems.
	Type: Boolean
	Required: false
	Default value: false
zones	The DNS zones

Prope rty	Description
	Type: Set(String)
	Required: false
	Default value: <none></none>
Properti	es for the "ftp" section:
data_	The source port to be used for active-mode FTP data connections. If 0, a random high port will be used, otherwise the specified port will be used. If a port below 1024 is required you must first explicitly permit use of low ports with the data_bind_low global setting.
sourc	Type: UInt
e_port	Required: false
	Default value: <none></none>
force_	Whether or not the virtual server should require that incoming FTP data connections from the client originate from the same IP address as the corresponding client control connection.
client_	Type: Boolean
secure	Required: false
	Default value: true
force_	Whether or not the virtual server should require that incoming FTP data connections from the nodes originate from the same IP address as the node.
serve	Type: Boolean
r_ secure	Required: false
	Default value: true
port_ range_ high	If non-zero, then this controls the upper bound of the port range to use for FTP data connections.
	Type: UInt

Prope rty	Description		
	Required: false		
	Default value: <none></none>		
	If non-zero, then this controls the lower bound of the port range to use for FTP data connections.		
port_ range_	Type: UInt		
low	Required: false		
	Default value: <none></none>		
	Use SSL on the data connection as well as the control connection (if not enabled it is left to the client and server to negotiate this).		
ssl_	Type: Boolean		
data	Required: false		
	Default value: true		
Properti	Properties for the "gzip" section:		
	Compression level (1-9, 1=low, 9=high).		
compr	Type: UInt		
ess_ level	Required: false		
	Default value: "1"		
	Compress web pages sent back by the server.		
enabl	Type: Boolean		
ed	Required: false		
	Default value: false		
etag_ rewrit e	How the ETag header should be manipulated when compressing content.		
	Type: Enum(String)		

Prope rty	Description
	Required: false
	Default value: "wrap"
	Permitted values:
	"delete": Delete the ETag header
	"ignore": Leave the ETag unchanged
	"weaken": Change the ETag header to specify a weak match
	"wrap": Wrap the ETag, and attempt to unwrap safe conditional requests
	MIME types to compress. Complete MIME types can be used, or a type can end in a '*' to match multiple types.
includ e_	Type: Set(String)
mime	Required: false
	Default value: "text/html text/plain"
	Maximum document size to compress (0 means unlimited).
max_	Type: UInt
size	Required: false
	Default value: "10000000"
	Minimum document size to compress.
min_ size	Type: UInt
	Required: false
	Default value: "1000"
no_	Compress documents with no given size.
size	• Type: Boolean

Prope rty	Description
	<ul><li>Required: false</li><li>Default value: true</li></ul>
Properti	es for the "http" section:
add_ cluste r_ip	Whether or not the virtual server should add an "X-Cluster-Client-Ip" header to the request that contains the remote client's IP address.  Type: Boolean Required: false Default value: true
add_ x_ forwar ded_ for	Whether or not the virtual server should append the remote client's IP address to the X-Forwarded-For header. If the header does not exist, it will be added.  Type: Boolean Required: false Default value: false
add_ x_ forwar ded_ proto	Whether or not the virtual server should add an "X-Forwarded-Proto" header to the request that contains the original protocol used by the client to connect to the traffic manager.  Type: Boolean Required: false Default value: false
autod etect_ upgra de_ heade rs	Whether the traffic manager should check for HTTP responses that confirm an HTTP connection is transitioning to the WebSockets protocol. If that such a response is detected, the traffic manager will cease any protocol-specific processing on the connection and just pass incoming data to the client/server as appropriate.  • Type: Boolean  • Required: false

Prope rty	Description
	Default value: true
	Handling of HTTP chunk overhead. When vTM receives data from a server or client that consists purely of protocol overhead (contains no payload), forwarding of such segments is delayed until useful payload data arrives (setting "lazy"). Changing this key to "eager" will make vTM incur the overhead of immediately passing such data on; it should only be used with HTTP peers whose chunk handling requires it.
chun k_	Type: Enum(String)
overh	Required: false
ead_ forwar	Default value: "lazy"
ding	Permitted values:
	"eager": Forward all data, even when no new payload information is available.
	"lazy": Only forward segments when useful payload data is available.
	If the 'Location' header matches this regular expression, rewrite the header using the 'location_replace' pattern.
locati on_	Type: String
regex	Required: false
	Default value: <none></none>
locati	If the 'Location' header matches the 'location_regex' regular expression, rewrite the header with this pattern (parameters such as \$1-\$9 can be used to match parts of the regular expression):
on_ replac	Type: String
е	Required: false
	Default value: <none></none>

Prope rty	Description
	The action the virtual server should take if the "Location" header does not match the location_regex regular expression.
	Type: Enum(UInt)
	Required: false
locati	Default value: "if_host_matches"
on_ rewrit	Permitted values:
е	"always": Rewrite the hostname to the request's "Host" header, and rewrite the protocol and port if necessary;
	"if_host_matches": Do not rewrite the hostname. Rewrite the protocol and port if the hostname matches the request's "Host" header.
	"never": Nothing;
	Auto-correct MIME types if the server sends the "default" MIME type for files.
mime_ defaul	Type: String
t	Required: false
	Default value: "text/plain"
	Auto-detect MIME types if the server does not provide them.
mime_	Type: Boolean
detect	Required: false
	Default value: false
strip_ x_ forwar ded_	Whether or not the virtual server should strip the 'X-Forwarded-Proto' header from incoming requests.
	Type: Boolean
proto	Required: false

Prope rty	Description
	Default value: true
Properti	es for the "http2" section:
conne ct_ timeo ut	The time, in seconds, to wait for a request on a new HTTP/2 connection. If no request is received within this time, the connection will be closed. This setting overrides the connect_timeout setting. If set to 0 (zero), the value of connect_timeout will be used instead.  • Type: UInt  • Required: false
	Default value: <none></none>
data_ fram e_size	This setting controls the preferred frame size used when sending body data to the client. If the client specifies a smaller maximum size than this setting, the client's maximum size will be used. Every data frame sent has at least a 9-byte header, in addition to this frame size, prepended to it.  Type: UInt Required: false Default value: "4096"
enabl ed	This setting allows the HTTP/2 protocol to be used by a HTTP virtual server. Unless use of HTTP/2 is negotiated by the client, the virtual server will fall back to HTTP 1.x automatically.  Type: Boolean Required: false Default value: true
heade r_ table_ size	This setting controls the amount of memory allowed for header compression on each HTTP/2 connection.  Type: UInt Required: false

Prope rty	Description
	Default value: "4096"
heade rs_ index_	A list of header names that should never be compressed using indexing.
	Type: Set(String)
blackli	Required: false
st	Default value: <none></none>
heade rs_ index_	The HTTP/2 HPACK compression scheme allows for HTTP headers to be compressed using indexing. Sensitive headers can be marked as "never index", which prevents them from being compressed using indexing. When this setting is Yes, only headers included in http2!headers_index_blacklist are marked as "never index". When this setting is No, all headers will be marked as "never index" unless they are included in http2!headers_index_whitelist.
defaul t	Type: Boolean
	Required: false
	Default value: true
heade rs_	A list of header names that can be compressed using indexing when the value of http2!headers_index_default is set to No.  • Type: Set(String)
index_ whiteli	
st	Required: false
	Default value: <none></none>
heade rs_ size_ limit	The maximum size, in bytes, of decompressed headers for an HTTP/2 request. If the limit is exceeded, the connection on which the request was sent will be dropped. A value of 0 disables the limit check. If a service protection class with http!max_header_length configured is associated with this service then that setting will take precedence.
	Type: UInt     Paguired: false
	Required: false

Prope rty	Description
	Default value: "262144"
http2_ client_ buffe r_ multip	The amount of memory, in multiples of the value specified by max_client_buffer, that the virtual server should use to store data sent by a client through a HTTP/2 connection. The value specified can be between 0 and 200. The value of 0 means unlimited. This setting limits buffer size for a HTTP/2 connection and does not affect buffer size for HTTP/1 connections or TCP stream connections. The number of HTTP/2 streams that can be opened in a single HTTP/2 connection is given by the http2!max_concurrent_streams. An overall cap to the amount of memory allocated for buffers for all TCP connections is given by the global max_tcp_buff_mem setting.
lier	Type: UInt
	Required: false
	Default value: <none></none>
http2_ serve r_ buffe r_ multip lier	The amount of memory, in multiples of the value specified by max_server_buffer, that the virtual server should use to store data sent to a client through HTTP/2 connection. The value specified can be between 0 and 200. The value of 0 means unlimited. This setting limits buffer size for a HTTP/2 connection and does not affect buffer size for HTTP/1 connections or TCP stream connections. The number of HTTP/2 streams that can be opened in a single HTTP/2 connection is given by the http2!max_concurrent_streams. An overall cap to the amount of memory allocated for buffers for all TCP connections is given by the global max_tcp_buff_mem setting.  • Type: UInt  • Required: false
	Default value: <none></none>
idle_ timeo ut_no_ strea ms	The time, in seconds, to wait for a new HTTP/2 request on a previously used HTTP/2 connection that has no open HTTP/2 streams. If an HTTP/2 request is not received within this time, the connection will be closed. A value of 0 (zero) will disable the timeout.  • Type: UInt  • Required: false

Prope rty	Description
	Default value: "120"
idle_ timeo ut_	The time, in seconds, to wait for data on an idle HTTP/2 connection, which has open streams, when no data has been sent recently (e.g. for long-polled requests). If data is not sent within this time, all open streams and the HTTP/2 connection will be closed. A value of 0 (zero) will disable the timeout.
open_ strea	Type: UInt
ms	Required: false
	Default value: "600"
max_ concu rrent_ strea ms	This setting controls the number of streams a client is permitted to open concurrently on a single connection.  • Type: UInt
	<ul><li>Required: false</li><li>Default value: "200"</li></ul>
max_ fram e_size	This setting controls the maximum HTTP/2 frame size clients are permitted to send to the traffic manager.  • Type: UInt  • Required: false
	Default value: "16384"
max_ heade r_ paddi ng	The maximum size, in bytes, of the random-length padding to add to HTTP/2 header frames. The padding, a random number of zero bytes up to the maximum specified.  • Type: UInt
	<ul><li>Required: false</li><li>Default value: <none></none></li></ul>

Prope rty	Description
merg e_ cooki e_ heade rs	Whether Cookie headers received from an HTTP/2 client should be merged into a single Cookie header using RFC6265 rules before forwarding to an HTTP/1.1 server. Some web applications do not handle multiple Cookie headers correctly.  • Type: Boolean  • Required: false  • Default value: true
strea m_ windo w_size	This setting controls the flow control window for each HTTP/2 stream. This will limit the memory used for buffering when the client is sending body data faster than the pool node is reading it.  Type: UInt Required: false Default value: "65535"
Properties for the "kerberos_protocol_transition" section:	
enabl ed	Whether or not the virtual server should use Kerberos Protocol Transition.  Type: Boolean Required: false Default value: false
princi pal	The Kerberos principal this virtual server should use to perform Kerberos Protocol Transition.  Type: String Required: false Default value: <none></none>
target	The Kerberos principal name of the service this virtual server targets.  • Type: String

Prope rty	Description
	Required: false
	Default value: <none></none>
Properti	es for the "log" section:
client_	Should the virtual server log failures occurring on connections to clients.
conne	Type: Boolean
ction_ failure	Required: false
S	Default value: false
	Whether or not to log connections to the virtual server to a disk on the file system.
enabl	Type: Boolean
ed	Required: false
	Default value: false
	The name of the file in which to store the request logs. The filename can contain macros which will be expanded by the traffic manager to generate the full filename.
filena	Type: String
me	Required: false
	Default value: "%zeushome%/zxtm/log/%v.log"
format	The log file format. This specifies the line of text that will be written to the log file when a connection to the traffic manager is completed. Many parameters from the connection can be recorded using macros.
	Type: String
	Required: false
	Default value: "%h %l %u %t "%r" %s %b "%{Referer}i" "%{User-agent}i""

Prope rty	Description
save_ all	Whether to log all connections by default, or log no connections by default. Specific connections can be selected for addition to or exclusion from the log using the TrafficScript function requestlog.include().
	Type: Boolean
	Required: false
	Default value: true
serve	Should the virtual server log failures occurring on connections to nodes.
r_ conne	Type: Boolean
ction_ failure	Required: false
S	Default value: false
sessio	Should the virtual server log session persistence events.
n_ persist	Type: Boolean
ence_ verbo	Required: false
se	Default value: false
	Should the virtual server log failures occurring on SSL secure negotiation.
ssl_	Type: Boolean
failure s	Required: false
	Default value: false
ssl_ resum ption_ failure s	Should the virtual server log messages when attempts to resume SSL sessions (either from the session cache or a session ticket) fail. Note that failure to resume an SSL session does not result in the SSL connection being closed, but it does cause a full SSL handshake to take place.
	Type: Boolean
	Required: false

Prope rty	Description
	Default value: false
Properti	es for the "recent_connections" section:
	Whether or not connections handled by this virtual server should be shown on the Activity > Connections page.
enabl	Type: Boolean
ed	Required: false
	Default value: true
	Whether or not all connections handled by this virtual server should be shown on the Connections page. Individual connections can be selectively shown on the Connections page using the recentconns.include() TrafficScript function.
save_ all	Type: Boolean
	Required: false
	Default value: false
Properties for the "request_tracing" section:	
	Record a trace of major connection processing events for each request and response.
enabl	Type: Boolean
ed	Required: false
	Default value: false
trace_ io	Include details of individual I/O events in request and response traces. Requires request tracing to be enabled.
	Type: Boolean
	Required: false
	Default value: false

Prope rty	Description
Properti	es for the "rtsp" section:
strea ming_ port_ range_ high	If non-zero this controls the upper bound of the port range to use for streaming data connections.  Type: UInt Required: false Default value: <none></none>
strea ming_ port_ range_ low	If non-zero this controls the lower bound of the port range to use for streaming data connections.  Type: UInt Required: false Default value: <none></none>
strea ming_ timeo ut	If non-zero data-streams associated with RTSP connections will timeout if no data is transmitted for this many seconds.  • Type: UInt  • Required: false  • Default value: "30"
Properti	es for the "sip" section:
dange rous_ reque sts	The action to take when a SIP request with body data arrives that should be routed to an external IP.  Type: Enum(String)  Required: false  Default value: "node"  Permitted values:  "forbid": Send a 403 Forbidden response to the client

Prope rty	Description
	"forward": Forward the request to its target URI (dangerous)
	"node": Send the request to a back-end node
follo	Should the virtual server follow routing information contained in SIP requests. If set to No requests will be routed to the chosen back-end node regardless of their URI or Route header.
W_	Type: Boolean
route	Required: false
	Default value: true
max_	SIP clients can have several pending requests at one time. To protect the traffic manager against DoS attacks, this setting limits the amount of memory each client can use. When the limit is reached new requests will be sent a 413 response. If the value is set to 0 (zero) the memory limit is disabled.
ction_	Type: UInt
mem	Required: false
	Default value: "65536"
	The mode that this SIP virtual server should operate in.
	Type: Enum(String)
	Required: false
	Default value: "sip_gateway"
mode	Permitted values:
	"full_gateway": All SIP requests and responses and all session data will pass through vTM. A port range to use for the session data and a timeout value for inactive data connections can be specified in the additional settings that are displayed when the Full Gateway mode is selected.

Prope rty	Description
	"route": The first SIP request in a session will pass through vTM, along with its responses, but all future requests that are part of the same session will go directly to the back-end node that was chosen by the traffic manager.
	"sip_gateway": All SIP requests and responses will pass through the traffic manager.
	Replace the Request-URI of SIP requests with the address of the selected back-end node.
rewrit	Type: Boolean
e_uri	Required: false
	Default value: false
strea	If non-zero this controls the upper bound of the port range to use for streaming data connections.
ming_ port_	Type: UInt
range_	Required: false
high	Default value: <none></none>
strea	If non-zero, then this controls the lower bound of the port range to use for streaming data connections.
ming_ port_	Type: UInt
range_	Required: false
low	Default value: <none></none>
	If non-zero a UDP stream will timeout when no data has been seen within this time.
strea ming_ timeo ut	Type: UInt
	Required: false
	Default value: "60"

Prope rty	Description
timeo ut_ messa ges	When timing out a SIP transaction, send a 'timed out' response to the client and, in the case of an INVITE transaction, a CANCEL request to the server.  Type: Boolean Required: false Default value: true
transa ction_ timeo ut	The virtual server should discard a SIP transaction when no further messages have been seen within this time.  • Type: UInt  • Required: false  • Default value: "30"
udp_ associ ate_ by_ source	Require that SIP datagrams which are part of the same transaction are received from the same address and port.  Type: Boolean Required: false Default value: true
Properties for the "smtp" section:	
expec t_ starttls	Whether or not the traffic manager should expect the connection to start off in plain text and then upgrade to SSL using STARTTLS when handling SMTP traffic.  Type: Boolean Required: false Default value: true
Properties for the "ssl" section:	

Prope rty	Description
add_ http_ heade rs	Whether or not the virtual server should add HTTP headers to each request to show the SSL connection parameters.  • Type: Boolean  • Required: false  • Default value: false
ca_ sites	This is table 'ca_sites'  Type: Table  Required: false  Primary key:  host (String): The host'keygivesthehostnameorlPdestinationaddressusedtomatchincomingTLSc onnectionstokeysoftable'ca_ sites'.ThehostcanbeaspecificDNSnameforusewiththeSNlextension,aspecificde stinationlPaddresswhennoSNImatches,oreitherofthosewithwildcard*/?charact ers.(Required)'  Sub keys:  cert_headers (Enum(String)): Which parts of the client certificate, if any, should be inserted into requests to a back-end node, as header fields. The same fields as for ssl_client_cert_headers are made available, and optionally the base64 encoded certificate itself. (Required)  Permitted values:  "all": Fields and PEM  "none": None  "simple": Fields

Prope rty	Description
	<ul> <li>client_cas (Set(String)): The certificate authorities used to verify client certificates for a particular destination site IP or SNI hostname. The specific site replaces the * (asterisk) in the key name, the value must be a valid file name in the conf/ssl/cas directory. The key can be specified multiple times to cover multiple IP addresses or SNI hostnames. (Required)</li> </ul>
	<ul> <li>request_cert (Enum(UInt)): Whether or not the virtual server should request an identifying certificate from each client connecting to particular destination IP address or SNI hostname. If a client certificate is requested this setting also determines whether the TLS handshake can continue successfully if the client does not present a certificate. (Required)</li> </ul>
	Permitted values:
	"dont_request": No
	"request": Yes, allow if absent
	"require": Yes, deny if absent
ciphe	The SSL/TLS cipher suites to allow for connections to this virtual server. Leaving this empty will make the virtual server use the globally configured cipher suites, see configuration key ssl!cipher_suites in the Global Settings section of the System tab. See there for how to specify SSL/TLS cipher suites.
r_ suites	Type: String
	Required: false
	Default value: <none></none>
client_ cert_ cas	The certificate authorities that this virtual server should trust to validate client certificates. If no certificate authorities are selected, and client certificates are requested, then all client certificates will be accepted.
	Type: Set(String)
	Required: false
	Default value: <none></none>

Prope rty	Description
client_	What HTTP headers the virtual server should add to each request to show the data in the client certificate.
	Type: Enum(String)
	Required: false
cert_	Default value: "none"
heade rs	Permitted values:
	"all": Certificate fields and certificate text
	"none": No data
	"simple": Certificate fields
ellipti	The SSL elliptic curve preference list for SSL connections to this virtual server using TLS version 1.0 or higher. Leaving this empty will make the virtual server use the globally configured curve preference list. The named curves P256, P384 and P521 may be configured.
c_ curves	Type: List(String)
	Required: false
	Default value: <none></none>
	Whether or not the Fallback SCSV sent by TLS clients is honored by this virtual server.  Choosing the global setting means the value of configuration key ssl!honor_fallback_scsv from the Global Settings section of the System tab will be enforced.
hono	Type: Enum(String)
r_ fallbac k_scsv	Required: false
	Default value: "use_default"
	Permitted values:
	"disabled": Disable Fallback SCSV

Prope rty	Description
	"enabled": Enable Fallback SCSV
	"use_default": Use the global setting for Fallback SCSV
issue d_	When the virtual server verifies certificates signed by these certificate authorities, it doesn't check the 'not after' date, i.e., they are considered valid even after their expiration date has passed (but not if they have been revoked).
certs_	Type: Set(String)
never_ expire	Required: false
	Default value: <none></none>
issue d_ certs_ never_ expir e_ depth	This setting gives the number of certificates in a certificate chain beyond those listed as issued_certs_never_expire whose certificate expiry will not be checked. For example "0" will result in the expiry checks being made for certificates issued by issued_certs_never_expire certificates, "1" will result in no expiry checks being performed for the certificates directly issued by issued_certs_never_expire certificates, "2" will avoid checking expiry for certificates issued by certificates issued by the issued_certs_never_expire certificates as well, and so on.  • Type: UInt  • Required: false  • Default value: "1"
ocsp_ enable	Whether or not the traffic manager should use OCSP to check the revocation status of client certificates.  Type: Boolean Required: false Default value: false
ocsp_	A table of certificate issuer specific OCSP settings.
issuers	• Type: Table

Prope rty	Description
	Required: false
	Primary key:
	<ul> <li>issuer (String): The name of an issuer (or DEFAULT for default OCSP settings).</li> <li>(Required)</li> </ul>
	Sub keys:
	<ul> <li>aia (Boolean): Whether the traffic manager should use AIA information contained in a client certificate to determine which OCSP responder to contact.</li> </ul>
	<ul> <li>nonce (Enum(String)): How to use the OCSP nonce extension, which protects against OCSP replay attacks. Some OCSP servers do not support nonces.</li> </ul>
	Permitted values:
	"off": No nonce check
	"on": Use nonce, server does not have to reply with nonce
	"strict": Use nonce, server must reply with nonce
	<ul> <li>required (Enum(String)): Whether we should do an OCSP check for this issuer, and whether it is required or optional.</li> </ul>
	Permitted values:
	"none": None
	"optional": OCSP check optional
	"strict": OCSP check required
	<ul> <li>responder_cert (String): The expected responder certificate.</li> </ul>
	• signer (String): The certificate with which to sign the request, if any.
	<ul> <li>url (String): Which OCSP responders this virtual server should use to verify client certificates.</li> </ul>

Prope rty	Description
ocsp_ max_ respo nse_ age	The number of seconds for which an OCSP response is considered valid if it has not yet exceeded the time specified in the 'nextUpdate' field. If set to 0 (zero) then OCSP responses are considered valid until the time specified in their 'nextUpdate' field.  • Type: UInt  • Required: false  • Default value: <none></none>
ocsp_ staplin g	If OCSP URIs are present in certificates used by this virtual server, then enabling this option will allow the traffic manager to provide OCSP responses for these certificates as part of the handshake, if the client sends a TLS status_request extension in the ClientHello.  • Type: Boolean  • Required: false  • Default value: false
ocsp_ time_ tolera nce	The number of seconds outside the permitted range for which the 'thisUpdate' and 'nextUpdate' fields of an OCSP response are still considered valid.  • Type: UInt  • Required: false  • Default value: "30"
ocsp_ timeo ut	The number of seconds after which OCSP requests will be timed out.  • Type: UInt  • Required: false  • Default value: "10"
reque st_ client_ cert	Whether or not the virtual server should request an identifying SSL certificate from each client.  • Type: Enum(UInt)

Prope rty	Description
	Required: false
	Default value: "dont_request"
	Permitted values:
	"dont_request": Do not request a client certificate
	"request": Request, but do not require a client certificate
	"require": Require a client certificate
	Whether or not to send an SSL/TLS "close alert" when the traffic manager is initiating an SSL socket disconnection.
send_ close_	Type: Boolean
alerts	Required: false
	Default value: true
serve	The SSL certificates and corresponding private keys.
r_cert_ alt_	Type: List(String)
certifi	Required: false
cates	Default value: <none></none>
	The default SSL certificate to use for this virtual server.
serve r_cert_	Type: String
defaul t	Required: false
(	Default value: <none></none>
serve r_cert_ host_	Host specific SSL server certificate mappings.
	Type: Table
mappi ng	Required: false

Prope rty	Description
	Primary key:
	<ul> <li>host (String): Host which this entry refers to. (Required)</li> </ul>
	Sub keys:
	<ul> <li>certificate (String): The SSL server certificate for a particular destination site IP. (Required)</li> </ul>
	<ul> <li>alt_certificates (List(String)): The SSL server certificates for a particular destination site IP.</li> </ul>
	Whether or not use of the session cache is enabled for this virtual server. Choosing the global setting means the value of configuration key ssl!session_cache_enabled from the Global Settings section of the System tab will be enforced.
	Type: Enum(String)
sessio n_	Required: false
cache_ enabl ed	Default value: "use_default"
	Permitted values:
	"disabled": Disable use of the session cache
	"enabled": Enable use of the session cache
	"use_default": Use the global setting for use of the session cache
sessio n_ ticket s_ enabl ed	Whether or not use of session tickets is enabled for this virtual server. Choosing the global setting means the value of configuration key ssl!tickets!enabled from the Global Settings section of the System tab will be enforced.
	Type: Enum(String)
	Required: false
	Default value: "use_default"
	Permitted values:

Prope rty	Description
	"disabled": Disable use of the session tickets
	"enabled": Enable use of the session tickets
	"use_default": Use the global setting for use of session tickets
signat ure_ algorit hms	The SSL signature algorithms preference list for SSL connections to this virtual server using TLS version 1.2 or higher. Leaving this empty will make the virtual server use the globally configured preference list, signature_algorithms in the ssl section of the global_settings resource. See there and in the online help for how to specify SSL signature algorithms.  • Type: String  • Required: false  • Default value: <none></none>
suppo rt_ssl3	Whether or not SSLv3 is enabled for this virtual server. Choosing the global setting means the value of configuration key ssl!support_ssl3 from the Global Settings section of the System tab will be enforced.  Type: Enum(String)  Required: false  Default value: "use_default"  Permitted values:
	"disabled": Disable SSLv3  "enabled": Enable SSLv3  "use_default": Use the global setting for SSLv3
suppo rt_tls1	Whether or not TLSv1.0 is enabled for this virtual server. Choosing the global setting means the value of configuration key ssl!support_tls1 from the Global Settings section of the System tab will be enforced.  • Type: Enum(String)  • Required: false

Prope rty	Description
	Default value: "use_default"
	Permitted values:
	"disabled": Disable TLSv1.0
	"enabled": Enable TLSv1.0
	"use_default": Use the global setting for TLSv1.0
	Whether or not TLSv1.1 is enabled for this virtual server. Choosing the global setting means the value of configuration key ssl!support_tls1_1 from the Global Settings section of the System tab will be enforced.
	Type: Enum(String)
suppo	Required: false
rt_	Default value: "use_default"
tls1_1	Permitted values:
	"disabled": Disable TLSv1.1
	"enabled": Enable TLSv1.1
	"use_default": Use the global setting for TLSv1.1
	Whether or not TLSv1.2 is enabled for this virtual server. Choosing the global setting means the value of configuration key ssl!support_tls1_2 from the Global Settings section of the System tab will be enforced.
suppo	Type: Enum(String)
rt_ tls1_2	Required: false
	Default value: "use_default"
	Permitted values:
	"disabled": Disable TLSv1.2

Prope rty	Description
	"enabled": Enable TLSv1.2
	"use_default": Use the global setting for TLSv1.2
	Whether or not TLSv1.3 is enabled for this virtual server. Choosing the global setting means the value of configuration key ssl!support_tls1_3 from the Global Settings section of the System tab will be enforced.
	Type: Enum(String)
suppo	Required: false
rt_	Default value: "use_default"
tls1_3	Permitted values:
	"disabled": Disable TLSv1.3
	"enabled": Enable TLSv1.3
	"use_default": Use the global setting for TLSv1.3
	If the traffic manager is receiving traffic sent from another traffic manager, then enabling this option will allow it to decode extra information on the true origin of the SSL connection. This information is supplied by the first traffic manager.
trust_ magic	Type: Boolean
magic	Required: false
	Default value: false
Properti	es for the "syslog" section:
enabl ed	Whether or not to log connections to the virtual server to a remote syslog host.
	Type: Boolean
	Required: false
	Default value: false

Prope rty	Description	
format	The log format for the remote syslog. This specifies the line of text that will be sent to the remote syslog when a connection to the traffic manager is completed. Many parameters from the connection can be recorded using macros.	
	Type: String	
	Required: false	
	Default value: "%h %l %u %t "%r" %s %b "%{Referer}i" "%{User-agent}i""	
	The remote host and port (default is 514) to send request log lines to.	
ip_	Type: String	
end_ point	Required: false	
	Default value: <none></none>	
	Maximum length in bytes of a message sent to the remote syslog. Messages longer than this will be truncated before they are sent.	
msg_ len_	Type: UInt	
limit	Required: false	
	Default value: "2048"	
Properti	Properties for the "tcp" section:	
close_	Whether or not connections from clients should be closed with a RST packet, rather than a FIN packet. This avoids the TIME_WAIT state, which on rare occasions allows wandering duplicate packets to be safely ignored.	
with_	Type: Boolean	
rst	Required: false	
	Default value: false	
nosis	Whether or not Nagle's algorithm should be used for TCP connections.	
nagle	Type: Boolean	

Prope rty	Description		
	Required: false		
	Default value: false		
proxy_	If set to Yes the traffic manager will send the client FIN to the back-end server and wait for a server response instead of closing the connection immediately. This is only necessary for protocols that require half-close support to function correctly, such as "rsh". If the traffic manager is responding to the request itself, setting this key to Yes will cause the traffic manager to continue writing the response even after it has received a FIN from the client.		
close	Type: Boolean		
	Required: false		
	Default value: false		
Properti	Properties for the "transaction_export" section:		
	Whether to export a restricted set of metadata about transactions processed by this virtual server. If enabled, more verbose information such as client and server headers and request tracing events will be omitted from the exported data.		
brief	Type: Boolean		
	Required: false		
	Default value: false		
	Export metadata about transactions handled by this service to the globally configured endpoint. Data will be exported only if the global transaction_export!enabled setting is enabled.		
enabl ed	Type: Boolean		
	Required: false		
	Default value: true		
hi_res	Whether the transaction processing timeline included in the metadata export is recorded with a high, microsecond, resolution. If set to No, timestamps will be recorded with a resolution of milliseconds.		

Prope rty	Description
	Type: Boolean
	Required: false
	Default value: false
http_	The set of HTTP header names for which corresponding values should be redacted from the metadata exported by this virtual server.
heade r_	Type: Set(String)
blackli	Required: false
st	Default value: "Authorization"
Propertion	es for the "udp" section:
end_ point_ persist	Whether UDP datagrams received from the same IP address and port are sent to the same pool node if they match an existing UDP session. Sessions are defined by the protocol being handled, for example SIP datagrams are grouped based on the value of the Call-ID header.  • Type: Boolean
ence	Required: false
	Default value: true
	Whether or not UDP datagrams should be distributed across all traffic manager processes, if this behaviour is not normally selected automatically due to other settings.
port_ smp	Type: Boolean
зпр	Required: false
	Default value: false
rbuff_ size	If this setting is non-zero, the virtual server will set the socket receive buffer size to this number of bytes. If set, this will override the so_rbuff_size setting. An OS-specified limit on socket buffer sizes such as given by sysctl net.core.rmem_max can be exceeded using this setting.

Prope rty	Description	
	Type: UInt	
	Required: false	
	Default value: <none></none>	
respo nse_ datagr ams_	The virtual server should discard any UDP connection and reclaim resources when the node has responded with this number of datagrams. For simple request/response protocols this can be often set to 1. If set to -1, the connection will not be discarded until the timeout is reached.  • Type: Int	
expect ed	Required: false	
	Default value: "1"	
	Whether the traffic manager should try to use SO_REUSEPORT for distributing incoming UDP datagrams across multiple processes (if kernel support is detected) or whether the legacy (pre-20.2) multi-processing mode should be used.  • Type: Enum(String)  • Required: false	
smp_ mode	Default value: "auto"	
	Permitted values:	
	"auto": auto	
	"legacy": legacy	
timeo ut	The virtual server should discard any UDP connection and reclaim resources when no further UDP traffic has been seen within this time.	
	<ul><li>Type: UInt</li><li>Required: false</li></ul>	
	Default value: "7"	

Prope rty	Description	
wbuff_ size	If this setting is non-zero, the virtual server will set the socket send buffer size to this number of bytes. If set, this will override the so_wbuff_size setting. An OS-specified limit on socket buffer sizes such as given by sysctl net.core.wmem_max can be exceeded using this setting.  • Type: UInt  • Required: false  • Default value: <none></none>	
Properti	es for the "web_cache" section:	
	The "Cache-Control" header to add to every cached HTTP response, no-cache or maxage=600 for example.	
contro I_out	Type: String	
1_000	Required: false	
	Default value: <none></none>	
	If set to Yes the traffic manager will attempt to cache web server responses.	
enabl	Type: Boolean	
ed	Required: false	
	Default value: false	
	Time period to cache error pages for.	
error_ page_ time	Type: UInt	
	Required: false	
	Default value: "30"	
	Maximum time period to cache web pages for.	
max_ time	Type: UInt	
	Required: false	

Prope rty	Description
	Default value: "600"
refres h_time	If a cached page is about to expire within this time, the traffic manager will start to forward some new requests on to the web servers. A maximum of one request per second will be forwarded; the remainder will continue to be served from the cache. This prevents "bursts" of traffic to your web servers when an item expires from the cache. Setting this value to 0 will stop the traffic manager updating the cache before it expires.  • Type: UInt  • Required: false  • Default value: "2"

#### **Web Accelerator Profile**

URI Endpoint: /api/tm/8.3/config/active/aptimizer/profiles

A Web Accelerator profile can be applied to an HTTP virtual server to enable automatic web content optimization.

Property	Description
background_after	If Web Accelerator can finish optimizing the resource within this time limit then serve the optimized content to the client, otherwise complete the optimization in the background and return the original content to the client. If set to 0, Web Accelerator will always wait for the optimization to complete before sending a response to the client.
	Type: UInt
	<ul><li>Required: false</li><li>Default value: <none></none></li></ul>

Property	Description
background_on_additional_ resources	If a web page contains resources that have not yet been optimized, fetch and optimize those resources in the background and send a partially optimized web page to clients until all resources on that page are ready.  Type: Boolean Required: false Default value: false
mode	Set the Web Accelerator mode to turn acceleration on or off.  • Type: Enum(String)  • Required: false  • Default value: "active"  • Permitted values:  "active": On - Web Accelerator acceleration is enabled  "idle": Off - Acceleration is disabled, but requests for Web Accelerator resources are served  "stealth": Stealth - Acceleration is controlled by a cookie
show_info_bar	Show the Web Accelerator information bar on optimized web pages. This requires HTML optimization to be enabled in the acceleration settings.  Type: Boolean Required: false Default value: false

### **SNMP Counter Values**

#### **Actions**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/actions/\*

Actions statistics values.

Counter	Description
	Number of times this action has been processed.
processed	Type: UInt
	SNMP name: "actionsProcessed"

### Asp session cache

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/cache/asp\_session\_cache

Asp session cache statistics values.

Counter	Description
	The total number of ASP sessions stored in the cache.
entries	Type: UInt
	SNMP name: "aspSessionCacheEntries"
	The maximum number of ASP sessions in the cache.
entries_max	Type: UInt
	SNMP name: "aspSessionCacheEntriesMax"
	The percentage of ASP session lookups that succeeded.
hit_rate	Type: UInt
	SNMP name: "aspSessionCacheHitRate"

Counter	Description
	Number of times a ASP session entry has been successfully found in the cache.
hits	Type: UInt
	SNMP name: "aspSessionCacheHits"
	Number of times a ASP session entry has been looked up in the cache.
lookups	Type: UInt
	SNMP name: "aspSessionCacheLookups"
	Number of times a ASP session entry has not been available in the cache.
misses	Type: UInt
	SNMP name: "aspSessionCacheMisses"
	The age of the oldest ASP session in the cache (in seconds).
oldest	Type: UInt
	SNMP name: "aspSessionCacheOldest"

### **Bandwidth**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/bandwidth/\*

Bandwidth statistics values.

Counter	Description
	Bytes output by connections assigned to this bandwidth class.
bytes_out	• Type: UInt64
	SNMP name: "bandwidthClassBytesOut"
guarantee	Guaranteed bandwidth class limit (kbits/s). Currently unused.

Counter	Description
	Type: UInt
	SNMP name: "bandwidthClassGuarantee"
	Maximum bandwidth class limit (kbits/s).
maximum	• Type: UInt
	SNMP name: "bandwidthClassMaximum"

# **Cloud api credentials**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/cloud\_api\_credentials/\*

Cloud api credentials statistics values.

Counter	Description
node_creations	The number of instance creation API requests made with this set of cloud credentials.  Type: UInt  SNMP name: "cloudcredentialsNodeCreations"
node_deletions	The number of instance destruction API requests made with this set of cloud credentials.
	Type: UInt
	SNMP name: "cloudcredentialsNodeDeletions"
status_requests	The number of status API requests made with this set of cloud credentials.
	Type: UInt
	SNMP name: "cloudcredentialsStatusRequests"

### **Connection rate limit**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/connection\_rate\_limit/\*

Connection rate limit statistics values.

ounter	Description
conns_entered	Connections that have entered the rate class and have been queued.
	Type: UInt
	SNMP name: "rateClassConnsEntered"
	Connections that have left the rate class.
conns_left	Type: UInt
	SNMP name: "rateClassConnsLeft"
	The average rate that requests are passing through this rate class.
current_rate	Type: UInt
	SNMP name: "rateClassCurrentRate"
	Requests dropped from this rate class without being processed (e.g. timeouts).
dropped	Type: UInt
	SNMP name: "rateClassDropped"
max_rate_per_min	The maximum rate that requests may pass through this rate class (requests/min).
	Type: UInt
	SNMP name: "rateClassMaxRatePerMin"
max_rate_per_sec	The maximum rate that requests may pass through this rate class (requests/sec).
	Type: UInt
	SNMP name: "rateClassMaxRatePerSec"

ounter	Description
	The current number of requests queued by this rate class.
queue_length	Type: UInt
	SNMP name: "rateClassQueueLength"

#### **Events**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/events/\*

Events statistics values.

Counter	Description
	Number of times this event configuration has matched.
matched	Type: UInt
	SNMP name: "eventsMatched"

#### **Glb** services

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/glb\_services/\*

Glb services statistics values.

Counter	Description
discarded	Number of A records this GLB Service has discarded.
	Type: UInt
	SNMP name: "glbServiceDiscarded"
responses	Number of A records this GLB Service has altered.
	Type: UInt
	SNMP name: "glbServiceResponses"

Counter	Description
unmodified	Number of A records this GLB Service has passed through unmodified.
	Type: UInt
	SNMP name: "glbServiceUnmodified"

#### **Globals**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/globals

Globals statistics values.

Counter	Description
analytics_transactions_ dropped	Count of transaction metadata records that have been dropped
	Type: UInt
	SNMP name: "analyticsTransactionsDropped"
	Count of transaction metadata records that have been exported
analytics_transactions_ exported	Type: UInt
	SNMP name: "analyticsTransactionsExported"
	Number of bytes queued in the transaction export transmit buffers.
analytics_transactions_ memory_usage	Type: UInt
	SNMP name: "analyticsTransactionsMemoryUsage"
data_entries	Number of entries in the TrafficScript data.get()/set() storage.
	Type: UInt
	SNMP name: "dataEntries"
data_memory_usage	Number of bytes used in the TrafficScript data.get()/set() storage.

Counter	Description
	Type: UInt
	SNMP name: "dataMemoryUsage"
	Events seen by the traffic Manager's event handling process.
events_seen	Type: UInt
	SNMP name: "eventsSeen"
	The peak bytes received from clients per second in the last hour.
hourly_peak_bytes_in_per_ second	Type: UInt
	SNMP name: "hourlyPeakBytesInPerSecond"
	The peak bytes sent to clients per second in the last hour.
hourly_peak_bytes_out_per_ second	Type: UInt
	SNMP name: "hourlyPeakBytesOutPerSecond"
	The peak requests per second in the last hour.
hourly_peak_requests_per_ second	Type: UInt
	SNMP name: "hourlyPeakRequestsPerSecond"
	The peak ssl connections per second in the last hour.
hourly_peak_ssl_ connections_per_second	Type: UInt
	SNMP name: "hourlyPeakSSLConnectionsPerSecond"
	Total number of idle HTTP connections to all nodes (used for future HTTP requests).
num_idle_connections	Type: UInt
	SNMP name: "numIdleConnections"
number shild are seen	The number of traffic manager child processes.
number_child_processes	Type: UInt

Counter	Description
	SNMP name: "numberChildProcesses"
number_dnsa_cache_hits	Requests for DNS A records resolved from the traffic manager's local cache.
	Type: UInt
	SNMP name: "numberDNSACacheHits"
	Requests for DNS A records (hostname->IP address) made by the traffic manager.
number_dnsa_requests	Type: UInt
	SNMP name: "numberDNSARequests"
	Requests for DNS PTR records resolved from the traffic manager's local cache.
number_dnsptr_cache_hits	Type: UInt
	SNMP name: "numberDNSPTRCacheHits"
	Requests for DNS PTR records (IP address->hostname) made by the traffic manager.
number_dnsptr_requests	Type: UInt
	SNMP name: "numberDNSPTRRequests"
	Malformed SNMP requests received.
number_snmp_bad_ requests	Type: UInt
	SNMP name: "numberSNMPBadRequests"
number_snmp_get_bulk_ requests	SNMP GetBulkRequests received.
	Type: UInt
	SNMP name: "numberSNMPGetBulkRequests"
number_snmp_get_next_ requests	SNMP GetNextRequests received.

Counter	Description
	Type: UInt
	SNMP name: "numberSNMPGetNextRequests"
	SNMP GetRequests received.
number_snmp_get_requests	Type: UInt
	SNMP name: "numberSNMPGetRequests"
	SNMP requests dropped due to access restrictions.
number_snmp_ unauthorised_requests	Type: UInt
·	SNMP name: "numberSNMPUnauthorisedRequests"
	Bytes decrypted with 3DES.
ssl_cipher_3des_decrypts	Type: UInt
	SNMP name: "sslCipher3DESDecrypts"
	Bytes encrypted with 3DES.
ssl_cipher_3des_encrypts	Type: UInt
	SNMP name: "sslCipher3DESEncrypts"
	Bytes decrypted with AES.
ssl_cipher_aes_decrypts	Type: UInt
	SNMP name: "sslCipherAESDecrypts"
	Bytes encrypted with AES.
ssl_cipher_aes_encrypts	Type: UInt
	SNMP name: "sslCipherAESEncrypts"
	Bytes decrypted with AES-GCM.
ssl_cipher_aes_gcm_ decrypts	Type: UInt
	SNMP name: "sslCipherAESGCMDecrypts"

Counter	Description
ssl_cipher_aes_gcm_ encrypts	Bytes encrypted with AES-GCM.
	Type: UInt
	SNMP name: "sslCipherAESGCMEncrypts"
	Bytes decrypted with a symmetric cipher.
ssl_cipher_decrypts	Type: UInt
	SNMP name: "sslCipherDecrypts"
	Bytes decrypted with DES.
ssl_cipher_des_decrypts	Type: UInt
	SNMP name: "sslCipherDESDecrypts"
	Bytes encrypted with DES.
ssl_cipher_des_encrypts	Type: UInt
	SNMP name: "sslCipherDESEncrypts"
	Number of Diffie Hellman key agreements.
ssl_cipher_dh_agreements	Type: UInt
	SNMP name: "sslCipherDHAgreements"
	Number of Diffie Hellman keys generated.
ssl_cipher_dh_generates	Type: UInt
	SNMP name: "sslCipherDHGenerates"
	Number of DSA signing operations.
ssl_cipher_dsa_signs	Type: UInt
	SNMP name: "sslCipherDSASigns"
	Number of DSA verifications.
ssl_cipher_dsa_verifies	Type: UInt

Counter	Description
	SNMP name: "sslCipherDSAVerifies"
ssl_cipher_ecdh_ agreements	Number of Elliptic Curve Diffie Hellman key agreements.
	Type: UInt
	SNMP name: "sslCipherECDHAgreements"
	Number of Elliptic Curve Diffie Hellman keys generated.
ssl_cipher_ecdh_generates	Type: UInt
	SNMP name: "sslCipherECDHGenerates"
	Number of ECDSA signing operations.
ssl_cipher_ecdsa_signs	Type: UInt
	SNMP name: "sslCipherECDSASigns"
	Number of ECDSA verifications.
ssl_cipher_ecdsa_verifies	Type: UInt
	SNMP name: "sslCipherECDSAVerifies"
	Bytes encrypted with a symmetric cipher.
ssl_cipher_encrypts	Type: UInt
	SNMP name: "sslCipherEncrypts"
	Bytes decrypted with RC4.
ssl_cipher_rc4_decrypts	Type: UInt
	SNMP name: "sslCipherRC4Decrypts"
ssl_cipher_rc4_encrypts	Bytes encrypted with RC4.
	Type: UInt
	SNMP name: "sslCipherRC4Encrypts"
ssl_cipher_rsa_decrypts	Number of RSA decrypts.

Counter	Description
	Type: UInt
	SNMP name: "sslCipherRSADecrypts"
	Number of external RSA decrypts.
ssl_cipher_rsa_decrypts_ external	Type: UInt
	SNMP name: "sslCipherRSADecryptsExternal"
	Number of RSA encrypts.
ssl_cipher_rsa_encrypts	Type: UInt
	SNMP name: "sslCipherRSAEncrypts"
	Number of external RSA encrypts.
ssl_cipher_rsa_encrypts_ external	Type: UInt
	SNMP name: "sslCipherRSAEncryptsExternal"
	Number of times a client certificate has expired.
ssl_client_cert_expired	Type: UInt
	SNMP name: "sslClientCertExpired"
	Number of times a client certificate was invalid.
ssl_client_cert_invalid	Type: UInt
	SNMP name: "sslClientCertInvalid"
ssl_client_cert_not_sent	Number of times a client certificate was required but not supplied.
	Type: UInt
	SNMP name: "sslClientCertNotSent"
ssl_client_cert_revoked	Number of times a client certificate was revoked.
	Type: UInt
	SNMP name: "sslClientCertRevoked"

Counter	Description
ssl_connections	Number of SSL connections negotiated.
	Type: UInt
	SNMP name: "sslConnections"
ssl_handshake_sslv3	Number of SSLv3 handshakes.
	Type: UInt
	SNMP name: "sslHandshakeSSLv3"
	Number of TLSv1.0 handshakes.
ssl_handshake_tlsv1	Type: UInt
	SNMP name: "sslHandshakeTLSv1"
ssl_handshake_tlsv11	Number of TLSv1.1 handshakes.
	Type: UInt
	SNMP name: "sslHandshakeTLSv11"
	Number of TLSv1.2 handshakes.
ssl_handshake_tlsv12	Type: UInt
	SNMP name: "sslHandshakeTLSv12"
ssl_handshake_tlsv13	Number of TLSv1.3 handshakes.
	Type: UInt
	SNMP name: "sslHandshakeTLSv13"
ssl_session_id_mem_cache_ hit	Number of times the SSL session id was found in the cache and
	reused.
	Type: UInt
	SNMP name: "sslSessionIDMemCacheHit"
ssl_session_id_mem_cache_ miss	Number of times the SSL session id was not found in the cache.

Counter	Description
	Type: UInt
	SNMP name: "sslSessionIDMemCacheMiss"
	Percentage of time that the CPUs are busy.
sys_cpu_busy_percent	Type: UInt
	SNMP name: "sysCPUBusyPercent"
	Percentage of time that the CPUs are idle.
sys_cpu_idle_percent	Type: UInt
	SNMP name: "sysCPUIdlePercent"
	Percentage of time that the CPUs are busy running system code.
sys_cpu_system_busy_ percent	Type: UInt
'	SNMP name: "sysCPUSystemBusyPercent"
	Percentage of time that the CPUs are busy running user-space code.
sys_cpu_user_busy_percent	Type: UInt
	SNMP name: "sysCPUUserBusyPercent"
	Number of free file descriptors.
sys_fds_free	Type: UInt
	SNMP name: "sysFDsFree"
sys_mem_buffered	Buffer memory (MBytes).
	Type: UInt
	SNMP name: "sysMemBuffered"
sys_mem_free	Free memory (MBytes).
	Type: UInt
	SNMP name: "sysMemFree"

Counter	Description
sys_mem_in_use	Memory used (MBytes).
	Type: UInt
	SNMP name: "sysMemInUse"
	Total swap space (MBytes).
sys_mem_swap_total	Type: UInt
	SNMP name: "sysMemSwapTotal"
	Amount of swap space in use (MBytes).
sys_mem_swapped	Type: UInt
	SNMP name: "sysMemSwapped"
	Total memory (MBytes).
sys_mem_total	Type: UInt
	SNMP name: "sysMemTotal"
time_last_config_update	The time (in hundredths of a second) since the configuration of traffic manager was updated (this value will wrap if no configuration changes are made for 497 days).
time_iast_eomig_apaate	Type: UInt
	SNMP name: "timeLastConfigUpdate"
total_backend_server_errors	Total errors returned from the backend servers.
	Type: UInt
	SNMP name: "totalBackendServerErrors"
total_bad_dns_packets	Total number of malformed DNS response packets encountered from the backend servers.
	Type: UInt
	SNMP name: "totalBadDNSPackets"

Counter	Description
total_bytes_in	Bytes received by the traffic manager from clients.
	Type: UInt64
	SNMP name: "totalBytesIn"
	Bytes sent by the traffic manager to clients.
total_bytes_out	Type: UInt64
	SNMP name: "totalBytesOut"
	Total number of TCP connections received.
total_conn	Type: UInt
	SNMP name: "totalConn"
	Number of TCP connections currently established.
total_current_conn	Type: UInt
	SNMP name: "totalCurrentConn"
	Total number of DNS response packets handled.
total_dns_responses	Type: UInt
	SNMP name: "totalDNSResponses"
total_requests	Total number of TCP requests received.
	Type: UInt
	SNMP name: "totalRequests"
total_transactions	Total number of TCP requests being processed, after applying TPS limits.
	Type: UInt
	SNMP name: "totalTransactions"
total_udp_bytes_in_ dropped	UDP bytes received by the traffic manager from clients but failed to be sent to backend servers.

Counter	Description
	Type: UInt64  SNMP name: "totalUDPBytesInDropped"
	SNMP name: "totalUDPBytesInDropped"
total_udp_bytes_out_ dropped	UDP bytes received by the traffic manager from backend servers but failed to be sent to clients.
	Type: UInt64
	SNMP name: "totalUDPBytesOutDropped"
up_time	The time (in hundredths of a second) that vTM software has been operational for (this value will wrap if it has been running for more than 497 days).
	Type: UInt
	SNMP name: "upTime"

## **Ip** gateway

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/traffic\_ips/ip\_gateway

Ip gateway statistics values.

Counter	Description
arp_message	Number of ARP messages sent for raised Traffic IP Addresses.
	Type: UInt
	SNMP name: "trafficIPARPMessage"
gateway_ping_requests	Number of ping requests sent to the gateway machine.
	Type: UInt
	SNMP name: "trafficIPGatewayPingRequests"
gateway_ping_responses	Number of ping responses received from the gateway machine.
	Type: UInt

Counter	Description
	SNMP name: "trafficIPGatewayPingResponses"
node_ping_requests	Number of ping requests sent to the backend nodes.
	Type: UInt
	SNMP name: "trafficIPNodePingRequests"
	Number of ping responses received from the backend nodes.
node_ping_responses	Type: UInt
	SNMP name: "trafficIPNodePingResponses"
number_inet46	The number of traffic IP addresses on this system (includes IPv4 and IPv6 addresses).
	Type: UInt
	SNMP name: "trafficIPNumberInet46"
number_raised_inet46	The number of traffic IP addresses currently raised on this system (includes IPv4 and IPv6 addresses).
	Type: UInt
	SNMP name: "trafficIPNumberRaisedInet46"
ping_response_errors	Number of ping response errors.
	Type: UInt
	SNMP name: "trafficIPPingResponseErrors"

## **Ip** session cache

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/cache/ip\_session\_cache

Ip session cache statistics values.

Counter	Description
entries	The total number of IP sessions stored in the cache.

Counter	Description
	Type: UInt
	SNMP name: "ipSessionCacheEntries"
	The maximum number of IP sessions in the cache.
entries_max	Type: UInt
	SNMP name: "ipSessionCacheEntriesMax"
	Number of times an expired IP session entry has been dropped on lookup.
expiries	Type: UInt
	SNMP name: "ipSessionCacheExpiries"
	The percentage of IP session lookups that succeeded.
hit_rate	Type: UInt
	SNMP name: "ipSessionCacheHitRate"
	Number of times a IP session entry has been successfully found in the cache.
hits	Type: UInt
	SNMP name: "ipSessionCacheHits"
	Number of times a IP session entry has been looked up in the cache.
lookups	Type: UInt
	SNMP name: "ipSessionCacheLookups"
misses	Number of times a IP session entry has not been available in the cache.
	Type: UInt
	SNMP name: "ipSessionCacheMisses"
oldest	The age of the oldest IP session in the cache (in seconds).

Counter	Description
	Type: UInt
	SNMP name: "ipSessionCacheOldest"

### J2ee session cache

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/cache/j2ee\_session\_cache

J2ee session cache statistics values.

Counter	Description
entries	The total number of J2EE sessions stored in the cache.
	Type: UInt
	SNMP name: "j2eeSessionCacheEntries"
	The maximum number of J2EE sessions in the cache.
entries_max	Type: UInt
	SNMP name: "j2eeSessionCacheEntriesMax"
expiries	Number of times an expired J2EE session entry has been dropped on lookup.
	Type: UInt
	SNMP name: "j2eeSessionCacheExpiries"
hit_rate	The percentage of J2EE session lookups that succeeded.
	Type: UInt
	SNMP name: "j2eeSessionCacheHitRate"
hits	Number of times a J2EE session entry has been successfully found in the cache.
	Type: UInt
	SNMP name: "j2eeSessionCacheHits"

Counter	Description
lookups	Number of times a J2EE session entry has been looked up in the cache.
	Type: UInt
	SNMP name: "j2eeSessionCacheLookups"
misses	Number of times a J2EE session entry has not been available in the cache.
	Type: UInt
	SNMP name: "j2eeSessionCacheMisses"
oldest	The age of the oldest J2EE session in the cache (in seconds).
	Type: UInt
	SNMP name: "j2eeSessionCacheOldest"

# Listen ips

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/listen\_ips/\*

Listen ips statistics values.

Counter	Description
bytes_in	Bytes sent to this listening IP.
	• Type: UInt64
	SNMP name: "listenIPBytesIn"
bytes_out	Bytes sent from this listening IP.
	• Type: UInt64
	SNMP name: "listenIPBytesOut"
current_conn	TCP connections currently established to this listening IP.
	Type: UInt

Counter	Description
	SNMP name: "listenIPCurrentConn"
max_conn	Maximum number of simultaneous TCP connections this listening IP has processed at any one time.
	Type: UInt
	SNMP name: "listenIPMaxConn"
total_requests	Requests sent to this listening IP.
	Type: UInt64
	SNMP name: "listenIPTotalRequests"

#### Locations

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/locations/\*

Locations statistics values.

Counter	Description
load	The mean load metric for this location.
	Type: UInt
	SNMP name: "locationLoad"
responses	Number of A records that have been altered to point to this location.
	Type: UInt
	SNMP name: "locationResponses"

### **Network interface**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/network\_interface/\*

Network interface statistics values.

Counter	Description
collisions	The number of collisions reported by this interface.
	Type: UInt
	SNMP name: "interfaceCollisions"
	Bytes received by this interface.
rx_bytes	• Type: UInt64
	SNMP name: "interfaceRxBytes"
	The number of receive errors reported by this interface.
rx_errors	• Type: UInt
	SNMP name: "interfaceRxErrors"
rx_packets	The number of packets received by this interface.
	• Type: UInt
	SNMP name: "interfaceRxPackets"
	Bytes transmitted by this interface.
tx_bytes	Type: UInt64
	SNMP name: "interfaceTxBytes"
tx_errors	The number of transmit errors reported by this interface.
	Type: UInt
	SNMP name: "interfaceTxErrors"
	The number of packets transmitted by this interface.
tx_packets	• Type: UInt
	SNMP name: "interfaceTxPackets"

# Node

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/nodes/node/\*

#### Node statistics values.

Counter	Description
bytes_from_node_hi	Bytes received from this node ( high 32bits ).
	Type: UInt
	SNMP name: "nodeBytesFromNodeHi"
	Bytes received from this node ( low 32bits ).
bytes_from_node_lo	Type: UInt
	SNMP name: "nodeBytesFromNodeLo"
	Bytes sent to this node ( high 32bits ).
bytes_to_node_hi	Type: UInt
	SNMP name: "nodeBytesToNodeHi"
	Bytes sent to this node ( low 32bits ).
bytes_to_node_lo	Type: UInt
	SNMP name: "nodeBytesToNodeLo"
	Requests currently established to this node. ( does not include idle keepalives ).
current_conn	Type: UInt
	SNMP name: "nodeCurrentConn"
current_requests	Connections currently established to this node.
	Type: UInt
	SNMP name: "nodeCurrentRequests"
errors	Number of timeouts, connection problems and other errors for this node.
	Type: UInt
	SNMP name: "nodeErrors"

Counter	Description
failures	Failures of this node.
	Type: UInt
	SNMP name: "nodeFailures"
	Requests that created a new connection to this node.
new_conn	Type: UInt
	SNMP name: "nodeNewConn"
	Requests that reused an existing pooled/keepalive connection rather than creating a new TCP connection.
pooled_conn	Type: UInt
	SNMP name: "nodePooledConn"
	The port this node listens on.
port	Type: UInt
	SNMP name: "nodePort"
	Maximum response time (ms) in the last second for this node.
response_max	Type: UInt
	SNMP name: "nodeResponseMax"
	Mean response time (ms) in the last second for this node.
response_mean	Type: UInt
	SNMP name: "nodeResponseMean"
response_min	Minimum response time (ms) in the last second for this node.
	Type: UInt
	SNMP name: "nodeResponseMin"
state	The state of this node.

Counter	Description
	Type: Enum(String)
	SNMP name: "nodeState"
	Permitted values:
	"alive": alive(1)
	"dead": dead(2)
	"unknown": unknown(3)
	Requests sent to this node.
total_conn	Type: UInt
	SNMP name: "nodeTotalConn"

### **Node inet46**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/nodes/node\_inet46/\*

Node inet46 statistics values.

Counter	Description
bytes_from_node	Bytes received from this node.
	• Type: UInt64
	SNMP name: "nodelnet46BytesFromNode"
bytes_to_node	Bytes sent to this node.
	Type: UInt64
	SNMP name: "nodelnet46BytesToNode"
current_conn	Current connections established to this node, includes idle connections and connections being established.
	Type: UInt

Counter	Description
	SNMP name: "nodeInet46CurrentConn"
	Active connections established to this node, does not include idle connections.
current_requests	Type: UInt
	SNMP name: "nodeInet46CurrentRequests"
	Number of timeouts, connection problems and other errors for this node.
errors	Type: UInt
	SNMP name: "nodeInet46Errors"
	Failures of this node.
failures	Type: UInt
	SNMP name: "nodeInet46Failures"
	Number of idle HTTP connections to this node.
idle_conns	Type: UInt
	SNMP name: "nodeInet46IdleConns"
	Requests that created a new connection to this node.
new_conn	Type: UInt
	SNMP name: "nodelnet46NewConn"
pooled_conn	Requests that reused an existing pooled/keepalive connection rather than creating a new TCP connection.
	Type: UInt
	SNMP name: "nodeInet46PooledConn"
port	The port this node listens on.
port	Type: UInt

Counter	Description
	SNMP name: "nodelnet46Port"
	Maximum response time (ms) in the last second for this node.
response_max	Type: UInt
	SNMP name: "nodelnet46ResponseMax"
	Mean response time (ms) in the last second for this node.
response_mean	Type: UInt
	SNMP name: "nodeInet46ResponseMean"
	Minimum response time (ms) in the last second for this node.
response_min	Type: UInt
	SNMP name: "nodeInet46ResponseMin"
	The state of this node.
	Type: Enum(String)
	SNMP name: "nodeInet46State"
state	Permitted values:
	"alive": alive(1)
	"dead": dead(2)
	"unknown": unknown(3)
	Requests sent to this node.
total_conn	Type: UInt
	SNMP name: "nodeInet46TotalConn"

### **Per location service**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/per\_location\_service/\*

Per location service statistics values.

Counter	Description
	The draining state of this location for this GLB Service.
	Type: Enum(String)
	SNMP name: "perLocationServiceDraining"
draining	Permitted values:
	"draining": draining(1)
	"active": active(2)
	The frontend state of this location for this GLB Service.
	Type: Enum(String)
frontend_state	SNMP name: "perLocationServiceFrontendState"
Trontena_state	Permitted values:
	"alive": alive(1)
	"dead": dead(2)
	The load metric for this location for this GLB Service.
load	Type: UInt
	SNMP name: "perLocationServiceLoad"
	The monitor state of this location for this GLB Service.
	Type: Enum(String)
monitor_state	SNMP name: "perLocationServiceMonitorState"
monitor_state	Permitted values:
	"alive": alive(1)
	"dead": dead(2)
responses	Number of A records that have been altered to point to this location for this GLB Service.

Counter	Description
	Type: UInt
	SNMP name: "perLocationServiceResponses"
	The state of this location for this GLB Service.
state	Type: Enum(String)
	SNMP name: "perLocationServiceState"
	Permitted values:
	"alive": alive(1)
	"dead": dead(2)

### Per node service level

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/per\_node\_slm/per\_node\_service\_level/\*

Per node service level statistics values.

Counter	Description
node_port	The port number of this node.
	Type: UInt
	SNMP name: "perNodeServiceLevelNodePort"
response_max	Maximum response time (ms) in the last second for this SLM class to this node.
	Type: UInt
	SNMP name: "perNodeServiceLevelResponseMax"
response_mean	Mean response time (ms) in the last second for this SLM class to this node.
	Type: UInt

Counter	Description
	SNMP name: "perNodeServiceLevelResponseMean"
response_min	Minimum response time (ms) in the last second for this SLM class to this node.
	Type: UInt
	SNMP name: "perNodeServiceLevelResponseMin"
total_conn	Requests handled by this SLM class to this node.
	Type: UInt
	SNMP name: "perNodeServiceLevelTotalConn"
total_non_conf	Non-conforming requests handled by this SLM class to this node.
	Type: UInt
	SNMP name: "perNodeServiceLevelTotalNonConf"

# Per node service level inet46

 $URI\ Endpoint: \ /api/tm/8.3/status/local\_tm/statistics/per\_node\_slm/per\_node\_service\_level\_inet46/*$ 

Per node service level inet46 statistics values.

Counter	Description
node_port	The port number of this node.
	Type: UInt
	SNMP name: "perNodeServiceLevelInet46NodePort"
response_max	Maximum response time (ms) in the last second for this SLM class to this node.
	Type: UInt
	SNMP name: "perNodeServiceLevelInet46ResponseMax"

Counter	Description
response_mean	Mean response time (ms) in the last second for this SLM class to this node.
	Type: UInt
	SNMP name: "perNodeServiceLevelInet46ResponseMean"
response_min	Minimum response time (ms) in the last second for this SLM class to this node.
	Type: UInt
	SNMP name: "perNodeServiceLevelInet46ResponseMin"
total_conn	Requests handled by this SLM class to this node.
	Type: UInt
	SNMP name: "perNodeServiceLevelInet46TotalConn"
total_non_conf	Non-conforming requests handled by this SLM class to this node.
	Type: UInt
	SNMP name: "perNodeServiceLevelInet46TotalNonConf"

# Per pool node

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/nodes/per\_pool\_node/\*

Per pool node statistics values.

Counter	Description
bytes_from_node	Bytes received from this node.
	Type: UInt64
	SNMP name: "perPoolNodeBytesFromNode"
bytes_to_node	Bytes sent to this node.
	Type: UInt64

Counter	Description
	SNMP name: "perPoolNodeBytesToNode"
current_conn	Current connections established to a node, includes idle connections and connections being established.
	Type: UInt
	SNMP name: "perPoolNodeCurrentConn"
	Active connections established to this node, does not include idle connections.
current_requests	Type: UInt
	SNMP name: "perPoolNodeCurrentRequests"
	Number of timeouts, connection problems and other errors for this node.
errors	Type: UInt
	SNMP name: "perPoolNodeErrors"
	Failures of this node.
failures	Type: UInt
	SNMP name: "perPoolNodeFailures"
	Number of idle HTTP connections to this node.
idle_conns	Type: UInt
	SNMP name: "perPoolNodeIdleConns"
new_conn	Requests that created a new connection to this node.
	Type: UInt
	SNMP name: "perPoolNodeNewConn"
node nort	The port that this node listens on.
node_port	Type: UInt

Counter	Description
	SNMP name: "perPoolNodeNodePort"
	Requests that reused an existing pooled/keepalive connection rather than creating a new TCP connection.
pooled_conn	Type: UInt
	SNMP name: "perPoolNodePooledConn"
	Maximum response time (ms) in the last second for this node.
response_max	Type: UInt
	SNMP name: "perPoolNodeResponseMax"
	Mean response time (ms) in the last second for this node.
response_mean	Type: UInt
	SNMP name: "perPoolNodeResponseMean"
	Minimum response time (ms) in the last second for this node.
response_min	Type: UInt
	SNMP name: "perPoolNodeResponseMin"
	The state of this node.
state	Type: Enum(String)
	SNMP name: "perPoolNodeState"
	Permitted values:
	"alive": alive(1)
	"dead": dead(2)
	"unknown": unknown(3)
	"draining": draining(4)
	"drainingtodelete": drainingtodelete(5)

Counter	Description
total_conn	Requests sent to this node.  • Type: UInt
	SNMP name: "perPoolNodeTotalConn"

# **Pools**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/pools/\*

Pools statistics values.

Counter	Description
	The load-balancing algorithm the pool uses.
	Type: Enum(String)
	SNMP name: "poolAlgorithm"
	Permitted values:
	"roundrobin": roundrobin(1)
algorithm	"weightedRoundRobin": weightedRoundRobin(2)
	"perceptive": perceptive(3)
	"leastConnections": leastConnections(4)
	"fastestResponseTime":
	fastestResponseTime(5)
	"random": random(6)
	"weightedLeastConnections":
	weightedLeastConnections(7)
butos in	Bytes received by this pool from nodes.
bytes_in	• Type: UInt64

Counter	Description
	SNMP name: "poolBytesIn"
	Bytes sent by this pool to nodes.
bytes_out	Type: UInt64
	SNMP name: "poolBytesOut"
	Total connections currently queued to this pool.
conns_queued	Type: UInt
	SNMP name: "poolConnsQueued"
	The number of nodes in this pool that are disabled.
disabled	Type: UInt
	SNMP name: "poolDisabled"
	The number of nodes in this pool which are draining.
draining	Type: UInt
	SNMP name: "poolDraining"
	Number of HTTP 1xx responses returned by this pool.
http1xx_responses	Type: UInt64
	SNMP name: "poolHTTP1xxResponses"
	Number of HTTP 2xx responses returned by this pool.
http2xx_responses	Type: UInt64
	SNMP name: "poolHTTP2xxResponses"
	Number of HTTP 3xx responses returned by this pool.
http3xx_responses	Type: UInt64
	SNMP name: "poolHTTP3xxResponses"
http4xx_responses	Number of HTTP 4xx responses returned by this pool.

Counter	Description
	Type: UInt64
	SNMP name: "poolHTTP4xxResponses"
	Number of times the pool received an HTTP 503 response from a node and retried it against a different node.
http503_retries	Type: UInt64
	SNMP name: "poolHTTP503Retries"
	Number of HTTP 5xx responses returned by this pool.
http5xx_responses	Type: UInt64
	SNMP name: "poolHTTP5xxResponses"
	Maximum time, measured in milliseconds, for which a connection was queued over the last second.
max_queue_time	Type: UInt
	SNMP name: "poolMaxQueueTime"
	Mean time, measured in milliseconds, for which a connection was queued over the last second.
mean_queue_time	Type: UInt
	SNMP name: "poolMeanQueueTime"
min_queue_time	Minimum time, measured in milliseconds, for which a connection was queued over the last second.
	Type: UInt
	SNMP name: "poolMinQueueTime"
	The number of nodes registered with this pool.
nodes	Type: UInt
	SNMP name: "poolNodes"

Counter	Description
	The session persistence method this pool uses
	Type: Enum(String)
	SNMP name: "poolPersistence"
	Permitted values:
	"none": none(1)
persistence	"ip": ip(2)
	"rule": rule(3)
	"transparent": transparent(4)
	"applicationCookie": applicationCookie(5)
	"xZeusBackend": xZeusBackend(6)
	"ssl": ssl(7)
	Total connections that timed-out while queued.
queue_timeouts	Type: UInt
	SNMP name: "poolQueueTimeouts"
session_migrated	Sessions migrated to a new node because the desired node was unavailable.
	Type: UInt
	SNMP name: "poolSessionMigrated"
	The state of this pool.
state	Type: Enum(String)
	SNMP name: "poolState"
	Permitted values:
	"active": active(1)

Counter	Description
	"disabled": disabled(2)
	"draining": draining(3)
	"unused": unused(4)
	"unknown": unknown(5)
	Requests sent to this pool.
total_conn	Type: UInt
	SNMP name: "poolTotalConn"

# **Rule authenticators**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/rule\_authenticators/\*

Rule authenticators statistics values.

Counter	Description
errors	Number of connection errors that have occurred when trying to connect to an authentication server.
	Type: UInt
	SNMP name: "authenticatorErrors"
fails	Number of times this Authenticator has failed to authenticate.
	Type: UInt
	SNMP name: "authenticatorFails"
passes	Number of times this Authenticator has successfully authenticated.
	Type: UInt
	SNMP name: "authenticatorPasses"
requests	Number of times this Authenticator has been asked to authenticate.

Counter	Description
	Type: UInt
	SNMP name: "authenticatorRequests"

# **Rules**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/rules/\*

Rules statistics values.

Counter	Description
aborts	Number of times this TrafficScript rule has aborted.
	Type: UInt
	SNMP name: "ruleAborts"
	Number of times this TrafficScript rule has discarded the connection.
discards	Type: UInt
	SNMP name: "ruleDiscards"
execution_time_warnings	Number of times this TrafficScript rule has exceeded the execution time warning threshold.
	Type: UInt
	SNMP name: "ruleExecutionTimeWarnings"
executions	Number of times this TrafficScript rule has been executed.
	Type: UInt
	SNMP name: "ruleExecutions"
pool_select	Number of times this TrafficScript rule has selected a pool to use.
	Type: UInt

Counter	Description
	SNMP name: "rulePoolSelect"
responds	Number of times this TrafficScript rule has responded directly to the client.
	Type: UInt
	SNMP name: "ruleResponds"
retries	Number of times this TrafficScript rule has forced the request to be retried.
	Type: UInt
	SNMP name: "ruleRetries"

### **Service level monitors**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/service\_level\_monitors/\*

Service level monitors statistics values.

Counter	Description
conforming	Percentage of requests associated with this SLM class that are conforming
	Type: UInt
	SNMP name: "serviceLevelConforming"
current_conns	The number of connections currently associated with this SLM class.
	• Type: UInt
	SNMP name: "serviceLevelCurrentConns"
is_o_k	Indicates if this SLM class is currently conforming.
	Type: Enum(String)
	SNMP name: "serviceLevelIsOK"

Counter	Description
	Permitted values:
	"notok": notok(1)
	"ok": ok(2)
	Maximum response time (ms) in the last second for this SLM class.
response_max	Type: UInt
	SNMP name: "serviceLevelResponseMax"
	Mean response time (ms) in the last second for this SLM class.
response_mean	Type: UInt
	SNMP name: "serviceLevelResponseMean"
	Minimum response time (ms) in the last second for this SLM class.
response_min	Type: UInt
	SNMP name: "serviceLevelResponseMin"
	Requests handled by this SLM class.
total_conn	Type: UInt
	SNMP name: "serviceLevelTotalConn"
	Non-conforming requests handled by this SLM class.
total_non_conf	Type: UInt
	SNMP name: "serviceLevelTotalNonConf"

# **Service protection**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/service\_protection/\*

Service protection statistics values.

Counter	Description
last_refusal_time	The time (in hundredths of a second) since this service protection class last refused a connection (this value will wrap if no connections are refused in more than 497 days).  • Type: UInt
	SNMP name: "serviceProtLastRefusalTime"
refusal_binary	Connections refused by this service protection class because the request contained disallowed binary content.  • Type: UInt
	SNMP name: "serviceProtRefusalBinary"
	Connections refused by this service protection class because the top 10 source IP addresses issued too many concurrent connections.
refusal_conc10_ip	Type: UInt
	SNMP name: "serviceProtRefusalConc10IP"
	Connections refused by this service protection class because the source IP address issued too many concurrent connections.
refusal_conc1_ip	Type: UInt
	SNMP name: "serviceProtRefusalConc1IP"
refusal_conn_rate	Connections refused by this service protection class because the source IP address issued too many connections within 60 seconds.
	Type: UInt
	SNMP name: "serviceProtRefusalConnRate"
	Connections refused by this service protection class because the source IP address was banned.
refusal_ip	Type: UInt
	SNMP name: "serviceProtRefusalIP"

Counter	Description
refusal_rfc2396	Connections refused by this service protection class because the HTTP request was not RFC 2396 compliant.
	Type: UInt
	SNMP name: "serviceProtRefusalRFC2396"
refusal_size	Connections refused by this service protection class because the request was larger than the defined limits allowed.
	Type: UInt
	SNMP name: "serviceProtRefusalSize"
total_refusal	Connections refused by this service protection class.
	Type: UInt
	SNMP name: "serviceProtTotalRefusal"

### Ssl cache

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/cache/ssl\_cache

Ssl cache statistics values.

Counter	Description
entries	The total number of SSL sessions stored in the server cache.
	• Type: UInt
	SNMP name: "sslCacheEntries"
entries_max	The maximum number of SSL entries in the server cache.
	Type: UInt
	SNMP name: "sslCacheEntriesMax"
hit_rate	The percentage of SSL server cache lookups that succeeded.
	Type: UInt

Counter	Description
	SNMP name: "sslCacheHitRate"
	Number of times a SSL entry has been successfully found in the server cache.
hits	Type: UInt
	SNMP name: "sslCacheHits"
	Number of times a SSL entry has been looked up in the server cache.
lookups	Type: UInt
	SNMP name: "sslCacheLookups"
misses	Number of times a SSL entry has not been available in the server cache.
	Type: UInt
	SNMP name: "sslCacheMisses"
oldest	The age of the oldest SSL session in the server cache (in seconds).
	Type: UInt
	SNMP name: "sslCacheOldest"

# Ssl ocsp stapling

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/ssl\_ocsp\_stapling

Ssl ocsp stapling statistics values.

Counter	Description
	The number of entries in the OCSP stapling cache.
cache_count	Type: UInt
	SNMP name: "sslOcspStaplingCacheCount"
count	The number of outgoing OCSP requests for OCSP stapling.

Counter	Description
	Type: UInt
	SNMP name: "sslOcspStaplingCount"
	The number of failed outgoing OCSP requests for OCSP stapling.
failure_count	Type: UInt
	SNMP name: "sslOcspStaplingFailureCount"
	The number of 'good' OCSP responses for OCSP stapling.
good_count	Type: UInt
	SNMP name: "sslOcspStaplingGoodCount"
	The number of 'revoked' OCSP responses for OCSP stapling.
revoked_count	Type: UInt
	SNMP name: "sslOcspStaplingRevokedCount"
success_count	The number of successful outgoing OCSP requests for OCSP stapling.
	Type: UInt
	SNMP name: "sslOcspStaplingSuccessCount"
unknown_count	The number of 'unknown' OCSP requests for OCSP stapling.
	Type: UInt
	SNMP name: "sslOcspStaplingUnknownCount"

# Ssl session cache

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/cache/ssl\_session\_cache

Ssl session cache statistics values.

Counter	Description
	The total number of SSL session persistence entries stored in the cache.
entries	Type: UInt
	SNMP name: "sslSessionCacheEntries"
	The maximum number of SSL session persistence entries in the cache.
entries_max	Type: UInt
	SNMP name: "sslSessionCacheEntriesMax"
	The percentage of SSL session persistence lookups that succeeded.
hit_rate	Type: UInt
	SNMP name: "sslSessionCacheHitRate"
	Number of times a SSL session persistence entry has been successfully found in the cache.
hits	Type: UInt
	SNMP name: "sslSessionCacheHits"
	Number of times a SSL session persistence entry has been looked up in the cache.
lookups	Type: UInt
	SNMP name: "sslSessionCacheLookups"
misses	Number of times a SSL session persistence entry has not been available in the cache.
	Type: UInt
	SNMP name: "sslSessionCacheMisses"
oldest	The age of the oldest SSL session in the cache (in seconds).
	Type: UInt

Counter	Description
	SNMP name: "sslSessionCacheOldest"

# **Traffic ip**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/traffic\_ips/traffic\_ip/\*

Traffic ip statistics values.

Counter	Description
	Whether this traffic IP address is currently being hosted by this traffic manager.
	Type: Enum(String)
state	SNMP name: "trafficIPState"
	Permitted values:
	"raised": raised(1)
	"lowered": lowered(2)
time	The time (in hundredths of a second) since trafficIPState last changed (this value will wrap if the state hasn't changed for 497 days).
	Type: UInt
	SNMP name: "trafficIPTime"

# **Traffic ip inet46**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/traffic\_ips/traffic\_ip\_inet46/\*

Traffic ip inet46 statistics values.

Counter	Description
state	Whether this traffic IP address is currently being hosted by this traffic manager.
	Type: Enum(String)
	SNMP name: "trafficIPInet46State"
	Permitted values:
	"raised": raised(1)
	"lowered": lowered(2)
time	The time (in hundredths of a second) since trafficIPState last changed (this value will wrap if the state hasn't changed for 497 days).
	Type: UInt
	SNMP name: "trafficIPInet46Time"

# **Uni session cache**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/cache/uni\_session\_cache

Uni session cache statistics values.

Counter	Description
entries	The total number of universal sessions stored in the cache.
	Type: UInt
	SNMP name: "uniSessionCacheEntries"
	The maximum number of universal sessions in the cache.
entries_max	Type: UInt
	SNMP name: "uniSessionCacheEntriesMax"

Counter	Description
expiries	Number of times an expired universal session entry has been dropped on lookup.
	Type: UInt
	SNMP name: "uniSessionCacheExpiries"
	The percentage of universal session lookups that succeeded.
hit_rate	Type: UInt
	SNMP name: "uniSessionCacheHitRate"
	Number of times a universal session entry has been successfully found in the cache.
hits	Type: UInt
	SNMP name: "uniSessionCacheHits"
	Number of times a universal session entry has been looked up in the cache.
lookups	Type: UInt
	SNMP name: "uniSessionCacheLookups"
misses	Number of times a universal session entry has not been available in the cache.
	Type: UInt
	SNMP name: "uniSessionCacheMisses"
oldest	The age of the oldest universal session in the cache (in seconds).
	Type: UInt
	SNMP name: "uniSessionCacheOldest"

# **User counters 32**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/extras/user\_counters\_32

User counters 32 statistics values.

Counter	Description
	The value of the user counter.
counter	Type: UInt
	SNMP name: "userCounterValue"

#### **User counters 64**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/extras/user\_counters\_64

User counters 64 statistics values.

Counter	Description
	The value of the 64-bit user counter.
counter	Type: UInt64
	SNMP name: "userCounter64Value"

### **Virtual servers**

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/virtual\_servers/\*

Virtual servers statistics values.

Counter	Description
auth_saml_redirects	Number of times a user agent was redirected to SAML Identity Provider.
	Type: UInt64
	SNMP name: "virtualserverAuthSamlRedirects"
auth_saml_responses	Number of times a SAML Response was processed.
	• Type: UInt64

Counter	Description
	SNMP name: "virtualserverAuthSamlResponses"
auth_saml_responses_ accepted	Number of times a SAML Response was accepted.
	Type: UInt64
	SNMP name: "virtualserverAuthSamlResponsesAccepted"
	Number of times a SAML Response was rejected.
auth_saml_responses_ rejected	• Type: UInt64
	SNMP name: "virtualserverAuthSamlResponsesRejected"
auth_sessions_created	Number of times an authentication session was created.
	• Type: UInt64
	SNMP name: "virtualserverAuthSessionsCreated"
auth_sessions_rejected	Number of times an authentication session was rejected.
	• Type: UInt64
	SNMP name: "virtualserverAuthSessionsRejected"
auth_sessions_used	Number of times an authentication session was used.
	Type: UInt64
	SNMP name: "virtualserverAuthSessionsUsed"
bytes_in	Bytes received by this virtual server from clients.
	Type: UInt64
	SNMP name: "virtualserverBytesIn"
bytes_out	Bytes sent by this virtual server to clients.
	Type: UInt64
	SNMP name: "virtualserverBytesOut"

Counter	Description
cert_status_requests	Number of incoming TLS handshakes for this virtual server with certificate status requests.
	Type: UInt
	SNMP name: "virtualserverCertStatusRequests"
cert_status_responses	Number of incoming TLS handshakes for this virtual server to which certificate status responses were attached.
	Type: UInt
	SNMP name: "virtualserverCertStatusResponses"
connect_timed_out	Connections closed by this virtual server because the 'connect_ timeout' interval was exceeded.
	Type: UInt
	SNMP name: "virtualserverConnectTimedOut"
connection_errors	Number of transaction or protocol errors in this virtual server.
	Type: UInt
	SNMP name: "virtualserverConnectionErrors"
	Number of connection failures in this virtual server.
connection_failures	Type: UInt
	SNMP name: "virtualserverConnectionFailures"
current_conn	TCP connections currently established to this virtual server.
	Type: UInt
	SNMP name: "virtualserverCurrentConn"
data_timed_out	Connections closed by this virtual server because the 'timeout' interval was exceeded.  • Type: UInt

Counter	Description
Counter	·
	SNMP name: "virtualserverDataTimedOut"
direct_replies	Direct replies from this virtual server, without forwarding to a node.
	Type: UInt
	SNMP name: "virtualserverDirectReplies"
discard	Connections discarded by this virtual server.
	Type: UInt
	SNMP name: "virtualserverDiscard"
gzip	Responses which have been compressed by content compression.
	Type: UInt
	SNMP name: "virtualserverGzip"
gzip_bytes_saved	Bytes of network traffic saved by content compression.
	• Type: UInt64
	SNMP name: "virtualserverGzipBytesSaved"
http1xx_responses	Number of HTTP 1xx responses returned by this virtual server.
	• Type: UInt64
	SNMP name: "virtualserverHTTP1xxResponses"
http2xx_responses	Number of HTTP 2xx responses returned by this virtual server.
	Type: UInt64
	SNMP name: "virtualserverHTTP2xxResponses"
http3xx_responses	Number of HTTP 3xx responses returned by this virtual server.
	Type: UInt64
	SNMP name: "virtualserverHTTP3xxResponses"
http4xx_responses	Number of HTTP 4xx responses returned by this virtual server.

Counter	Description
	Type: UInt64
	SNMP name: "virtualserverHTTP4xxResponses"
	Number of HTTP 5xx responses returned by this virtual server.
http5xx_responses	Type: UInt64
	SNMP name: "virtualserverHTTP5xxResponses"
	Number of HTTP 2xx responses returned from webcache by this virtual server.
http_cache2xx_responses	Type: UInt64
	SNMP name: "virtualserverHTTPCache2xxResponses"
	Number of HTTP 3xx responses returned from webcache by this virtual server.
http_cache3xx_responses	Type: UInt64
	SNMP name: "virtualserverHTTPCache3xxResponses"
	Number of HTTP 4xx responses returned from webcache by this virtual server.
http_cache4xx_responses	Type: UInt64
	SNMP name: "virtualserverHTTPCache4xxResponses"
http_cache5xx_responses	Number of HTTP 5xx responses returned from webcache by this virtual server.
	Type: UInt64
	SNMP name: "virtualserverHTTPCache5xxResponses"
	Percentage hit rate of the web cache for this virtual server.
http_cache_hit_rate	Type: UInt
	SNMP name: "virtualserverHttpCacheHitRate"

Counter	Description
http_cache_hits	HTTP responses sent directly from the web cache by this virtual server.
	Type: UInt
	SNMP name: "virtualserverHttpCacheHits"
	HTTP requests that are looked up in the web cache by this virtual server.
http_cache_lookups	Type: UInt
	SNMP name: "virtualserverHttpCacheLookups"
	Number of HTTP 2xx responses generated by this virtual server.
http_generated2xx_ responses	Type: UInt64
	SNMP name: "virtualserverHTTPGenerated2xxResponses"
	Number of HTTP 3xx responses generated by this virtual server.
http_generated3xx_ responses	Type: UInt64
	SNMP name: "virtualserverHTTPGenerated3xxResponses"
	Number of HTTP 4xx responses generated by this virtual server.
http_generated4xx_ responses	Type: UInt64
	SNMP name: "virtualserverHTTPGenerated4xxResponses"
	Number of HTTP 5xx responses generated by this virtual server.
http_generated5xx_ responses	Type: UInt64
responses	SNMP name: "virtualserverHTTPGenerated5xxResponses"
http_rewrite_cookie	HTTP Set-Cookie headers, supplied by a node, that have been rewritten.
	Type: UInt
	SNMP name: "virtualserverHttpRewriteCookie"

Counter	Description
http_rewrite_location	HTTP Location headers, supplied by a node, that have been rewritten.
	Type: UInt
	SNMP name: "virtualserverHttpRewriteLocation"
	Number of HTTP 1xx responses returned from a backend server or TrafficScript rule by this virtual server.
http_server1xx_responses	• Type: UInt64
	SNMP name: "virtualserverHTTPServer1xxResponses"
	Number of HTTP 2xx responses returned from a backend server or TrafficScript rule by this virtual server.
http_server2xx_responses	Type: UInt64
	SNMP name: "virtualserverHTTPServer2xxResponses"
	Number of HTTP 3xx responses returned from a backend server or TrafficScript rule by this virtual server.
http_server3xx_responses	Type: UInt64
	SNMP name: "virtualserverHTTPServer3xxResponses"
http_server4xx_responses	Number of HTTP 4xx responses returned from a backend server or TrafficScript rule by this virtual server.
	• Type: UInt64
	SNMP name: "virtualserverHTTPServer4xxResponses"
http_server5xx_responses	Number of HTTP 5xx responses returned from a backend server or TrafficScript rule by this virtual server.
	• Type: UInt64
	SNMP name: "virtualserverHTTPServer5xxResponses"

Counter	Description
keepalive_timed_out	Connections closed by this virtual server because the 'keepalive_ timeout' interval was exceeded.
	Type: UInt
	SNMP name: "virtualserverKeepaliveTimedOut"
	Maximum number of simultaneous TCP connections this virtual server has processed at any one time.
max_conn	Type: UInt
	SNMP name: "virtualserverMaxConn"
	Connections closed by this virtual server because the 'max_ transaction_duration' interval was exceeded.
max_duration_timed_out	Type: UInt
	SNMP name: "virtualserverMaxDurationTimedOut"
	The port the virtual server listens on.
port	Type: UInt
	SNMP name: "virtualserverPort"
processing_timed_out	Connections closed by this virtual server because the 'timeout' interval was exceeded while waiting for rules or external processing.
	Type: UInt
	SNMP name: "virtualserverProcessingTimedOut"
protocol	The protocol the virtual server is operating.
	Type: Enum(String)
	SNMP name: "virtualserverProtocol"
	Permitted values:
	"http": http(1)

Counter	Description
	"https": https(2)
	"ftp": ftp(3)
	"imaps": imaps(4)
	"imapv2": imapv2(5)
	"imapv3": imapv3(6)
	"imapv4": imapv4(7)
	"pop3": pop3(8)
	"pop3s": pop3s(9)
	"smtp": smtp(10)
	"ldap": ldap(11)
	"Idaps": Idaps(12)
	"telnet": telnet(13)
	"sslforwarding": sslforwarding(14)
	"udpstreaming": udpstreaming(15)
	"udp": udp(16)
	"dns": dns(17)
	"genericserverfirst": genericserverfirst(18)
	"genericclientfirst": genericclientfirst(19)
	"dnstcp": dnstcp(20)
	"sipudp": sipudp(21)
	"siptcp": siptcp(22)
	"rtsp": rtsp(23)

Counter	Description
	"stream": stream(24)
	"l4acceltcp": l4acceltcp(25)
	"l4acceludp": l4acceludp(26)
	"l4accelgeneric": l4accelgeneric(27)
	"l4accelstateless": l4accelstateless(28)
	Number of SIP requests rejected due to them exceeding the maximum amount of memory allocated to the connection.
sip_rejected_requests	Type: UInt
	SNMP name: "virtualserverSIPRejectedRequests"
	Total number of SIP INVITE requests seen by this virtual server.
sip_total_calls	Type: UInt
	SNMP name: "virtualserverSIPTotalCalls"
	Number of times a lookup for an existing SSL session was performed.
ssl_cache_lookup	Type: UInt64
	SNMP name: "virtualserverSslCacheLookup"
	Number of times a lookup failed to find an existing SSL session.
ssl_cache_miss	Type: UInt64
	SNMP name: "virtualserverSslCacheMiss"
ssl_cache_rejected	Number of times an SSL session was found in the cache but rejected and not resumed.
	Type: UInt64
	SNMP name: "virtualserverSslCacheRejected"
	Number of times an SSL session was resumed from the cache.
ssl_cache_resumed	Type: UInt64

Counter	Description
	SNMP name: "virtualserverSslCacheResumed"
ssl_cache_saved	Number of times an SSL session was saved to the cache.
	Type: UInt64
	SNMP name: "virtualserverSslCacheSaved"
	Number of times a HelloRetryRequest message was sent to TLS clients.
ssl_hello_retry_requested	• Type: UInt64
	SNMP name: "virtualserverSslHelloRetryRequested"
	Number of times a new SSL session was created.
ssl_new_session	• Type: UInt64
	SNMP name: "virtualserverSslNewSession"
	Number of SSL session tickets that were rejected because they had expired.
ssl_ticket_expired	Type: UInt64
	SNMP name: "virtualserverSslTicketExpired"
	Number of SSL session tickets that were issued to clients.
ssl_ticket_issued	• Type: UInt64
	SNMP name: "virtualserverSslTicketIssued"
	Number of SSL session tickets that could not be decrypted because the ticket key they referenced could not be found.
ssl_ticket_key_not_found	• Type: UInt64
	SNMP name: "virtualserverSslTicketKeyNotFound"
	Number of SSL session tickets received.
ssl_ticket_received	Type: UInt64

Counter	Description
	SNMP name: "virtualserverSslTicketReceived"
	Number of SSL session tickets that were rejected for a reason other than because they had expired.
ssl_ticket_rejected	Type: UInt64
	SNMP name: "virtualserverSslTicketRejected"
	Number of SSL session tickets that were successfully used to resume a session.
ssl_ticket_resumed	Type: UInt64
	SNMP name: "virtualserverSslTicketResumed"
	UDP datagrams processed by this virtual server.
total_dgram	Type: UInt
	SNMP name: "virtualserverTotalDgram"
	HTTP/1.x Requests received by this virtual server.
total_http1_requests	• Type: UInt64
	SNMP name: "virtualserverTotalHTTP1Requests"
	HTTP/2 Requests received by this virtual server.
total_http2_requests	• Type: UInt64
	SNMP name: "virtualserverTotalHTTP2Requests"
	HTTP Requests received by this virtual server.
total_http_requests	Type: UInt64
	SNMP name: "virtualserverTotalHTTPRequests"
	Requests received by this virtual server.
total_requests	Type: UInt64
	SNMP name: "virtualserverTotalRequests"

Counter	Description
udp_bytes_in_dropped	UDP bytes received by this virtual server from clients but failed to be sent to backend servers.
	Type: UInt64
	SNMP name: "virtualserverUDPBytesInDropped"
udp_bytes_out_dropped	UDP bytes received by this virtual server from backend servers but failed to be sent to clients.
	Type: UInt64
	SNMP name: "virtualserverUDPBytesOutDropped"
udp_timed_out	Connections closed by this virtual server because the 'udp_timeout' interval was exceeded.
	Type: UInt
	SNMP name: "virtualserverUdpTimedOut"

#### Web cache

URI Endpoint: /api/tm/8.3/status/local\_tm/statistics/cache/web\_cache

Web cache statistics values.

Counter	Description
entries	The number of items in the web cache.
	Type: UInt
	SNMP name: "webCacheEntries"
	The percentage of web cache lookups that succeeded.
hit_rate	Type: UInt
	SNMP name: "webCacheHitRate"

Counter	Description
	Number of times a page has been successfully found in the web cache.
hits	Type: UInt64
	SNMP name: "webCacheHits"
	Number of times a page has been looked up in the web cache.
lookups	Type: UInt64
	SNMP name: "webCacheLookups"
	The maximum number of items in the web cache.
max_entries	Type: UInt
	SNMP name: "webCacheMaxEntries"
	The maximum amount of memory the web cache can use in kilobytes.
mem_maximum	Type: UInt
	SNMP name: "webCacheMemMaximum"
	Total memory used by the web cache in kilobytes.
mem_used	Type: UInt
	SNMP name: "webCacheMemUsed"
	Number of times a page has not been found in the web cache.
misses	• Type: UInt64
	SNMP name: "webCacheMisses"
oldest	The age of the oldest item in the web cache (in seconds).
	Type: UInt
	SNMP name: "webCacheOldest"
url_store_allocated	Amount of allocated space in the web cache URL store.

Counter	Description
	Type: UInt64
	SNMP name: "webCacheURLStoreAllocated"
	Amount of free space in the web cache URL store.
url_store_free	• Type: UInt64
	SNMP name: "webCacheURLStoreFree"
	Total amount of space in the web cache URL store.
url_store_size	Type: UInt64
	SNMP name: "webCacheURLStoreSize"
	Total number of allocations for the web cache URL store.
url_store_total_allocations	• Type: UInt64
	SNMP name: "webCacheURLStoreTotalAllocations"
url_store_total_failures	Total number of allocation failures for the web cache URL store.
	• Type: UInt64
	SNMP name: "webCacheURLStoreTotalFailures"
url_store_total_frees	Total number of blocks freed in the web cache URL store.
	• Type: UInt64
	SNMP name: "webCacheURLStoreTotalFrees"

# **System Information Resources**

# **Backups**

URI Endpoint: /api/tm/8.3/status/local\_tm/backups/full/\*

Full backups.

Property	Description	
Properties for the "backup" section:		
description	Description of the backup	
	Type: String	
time_stamp	Time the backup was created. Expressed as a UTC value.	
	Type: Int	
version	Version of the traffic manager used to create the backup	
	Type: String	

### Information

URI Endpoint: /api/tm/8.3/status/local\_tm/information

Static information for the system.

Property	Description
platform	The type of platform on which the Traffic Manager instance is running on.
	Type: String
tm_version	Version number of the Traffic Manager instance.
	Type: String
uuid	The universally unique identifier for the Traffic Manager instance.
	Type: String

#### **State**

URI Endpoint: /api/tm/8.3/status/local\_tm/state

State information for the traffic manager.

Property	Description	
Properties for the "state" section:		
error_level	The error_level of the traffic manager.	
	Type: Enum(String)	
	Permitted values:	
	"ok": System has no problems	
	"warn": System has minor issues	
	"error": System has major issues	
	"fatal": System has issues which causes it to die/crash/fail to startup	
	List of configuration errors for the traffic manager	
errors	Type: Set(String)	
	A table of nodes which have failed on the traffic manager	
	Type: Table	
	Required: false	
failed_nodes	Primary key:	
	node (String): A node which has failed (Required)	
	Sub keys:	
	<ul> <li>pools (Set(String)): List of pools which use this node.</li> </ul>	
license	Current active license or Community_Edition	
	Type: String	
pools		
	• Type: Table	
	Required: false	

Property	Description
	Primary key:
	name (String): Name of the pool (Required)
	Sub keys:
	failure_pool (String): Failure pool associated with this pool.
	active_nodes (Set(String)): List of nodes which are in the active state.
	draining_nodes (Set(String)): List of nodes which are in the draining state.
	disabled_nodes (Set(String)): List of nodes which are in the disabled state.
tip_errors	List of traffic IP errors for the traffic manager
	Type: Set(String)
virtual_servers	A table of virtual server status
	• Type: Table
	Required: false
	Primary key:
	name (String): Name of the virtual server (Required)
	Sub keys:
	pool (String): Pool associated with this virtual server.
	port (UInt): Port the virtual server listens on.
	throughput (UInt64): Through put for the virtual server.
	ts_redirect_pools (Set(String)): List of pools which may be selected by Traffic Script Request Rules.

# **Handling Updates to the REST API**

# **REST API Support in the Traffic Manager**

The Traffic Manager typically supports several major versions of its REST API in any one release, and can additionally support several minor versions of each major version. The Traffic Manager employs this system to facilitate upgrading from an older supported version to a newer version with the least possible constraints on development time. Ivanti operates a policy of always warning about the impending removal of an API version in the release notes of the preceding Traffic Manager release.

The REST API version number is split into a major and minor component, and is two sets of digits separated by a dot. Using BNF notation, the follows rules apply:

```
<REST API version> ::= <major> "." <minor>
<major> ::= <non-negative integer>
<minor> ::= <non-negative integer>
```

Ivanti typically increments the version number in each release of the Traffic Manager, with the extent of the increment dependent on the changes introduced to the API since the preceding release. A significant API update necessitates incrementing the major component of the version number (with the minor version reset to 0). For example, from 3.4 to 4.0. A smaller API change increments only the minor component by 1, for example, from 3.4 to 3.5.

Major changes typically occur in the following situations:

- Removing or renaming a resource.
- Removing or renaming a property within a resource.
- Adding a property without a default to an existing resource.

Minor changes typically occur in the following situations:

- Adding a new resource to the API.
- Adding a new property with a default value to an existing JSON resource.

For more information, contact Pulse Secure Technical Support.

# **Updating Your Applications to Use a New Version of the API**

If you are considering adopting a new version of the Traffic Manager REST API for your existing scripts and applications, Ivanti strongly recommends you take the following steps in order to minimize the impact of the update:

- Avoid hard-coding the API version number in multiple places in a script or application.
- Avoid mixing requests to different major API versions across a single Traffic Manager cluster.
   For example, it is unsafe to access a resource at a 3.x API version in one script and a 4.x API version in another.

### **Changes Involving a Minor API Update**

For upgrades involving a minor increment to a currently used major version, for example 3.4 to 3.5, PUTs and GETs made to the previous API version are expected to operate as intended with the newer API version. Ivanti recommends you verify that the client behaves as expected when any new keys or resources are returned.

### **Changes Involving a Major API Update**

For upgrades involving a new major API version, for example 3.11 to 4.0, first audit your scripts and applications to determine the list of resources and properties you are accessing. Next, refer to REST API Change History for the change history since your current version up to and including the desired new version. Compare your set of accessed resources and properties to the changes listed and note where a resource or properties has been affected, with specific reference to any renames or deletes. Finally, modify your scripts and applications accordingly.

# **REST API Change History**

Pulse Secure Virtual Traffic Manager release 21.4 includes version 8.3 of the REST API.

This appendix lists the changes introduced in each supported API version. Applications that were developed against older versions of the Traffic Manager REST API might be affected by the updates listed here. Use the information contained in this appendix to identify the necessary updates.

# **Changes in Version 8.3**

The following properties in 'Virtual Server' (/api/tm/8.3/config/active/virtual\_servers) have been added:

Property 'ssl/ca\_sites' was added.

# **Changes in Version 8.2**

The following properties in 'Global Settings' (/api/tm/8.2/config/active/global\_settings) have been added:

Property 'basic/max\_tcp\_buff\_mem' was added.

The following properties in 'Virtual Server' (/api/tm/8.2/config/active/virtual\_servers) have been added:

- Property 'http2/http2\_client\_buffer\_multiplier' was added.
- Property 'http2/http2\_server\_buffer\_multiplier' was added.

The following properties in 'Traffic Manager' (/api/tm/8.2/config/active/traffic\_managers) have been added:

- Property 'admin/hsts\_enable' was added.
- Property 'admin/hsts\_max\_age' was added.

### **Changes in Version 8.1**

The following properties in 'Virtual Server' (/api/tm/8.1/config/active/virtual\_servers) have been added:

- Property 'udp/rbuff\_size' was added.
- Property 'udp/smp\_mode' was added.
- Property 'udp/wbuff\_size' was added.

The following properties in 'Globals' (/api/tm/8.1/status/local\_tm/statistics/globals) have been added:

- Property 'statistics/total\_udp\_bytes\_in\_dropped' was added.
- Property 'statistics/total\_udp\_bytes\_out\_dropped' was added.

The following properties in 'Global Settings' (/api/tm/8.1/config/active/global\_settings) have been added:

- Property 'connection/udp\_read\_multiple' was added.
- Property 'zoneinfo/directory' was added.

The following properties in 'Virtual servers' (/api/tm/8.1/status/local\_tm/statistics/virtual\_servers/\*) have been added:

- Property 'statistics/udp\_bytes\_in\_dropped' was added.
- Property 'statistics/udp\_bytes\_out\_dropped' was added.

### **Changes in Version 8.0**

The following resources were added:

Resource 'Admin SSL Trusted Certificate' (/api/tm/8.0/config/active/ssl/admin\_cas)

The following properties in 'User Authenticator' (/api/tm/8.0/config/active/user\_authenticators) have been added:

Property 'ldap/ssl' was added.

### **Changes in Version 7.1**

The following properties in 'Global Settings' (/api/tm/7.1/config/active/global\_settings) have been added:

Property 'basic/http2\_conn\_frame\_queue\_limit' was added.

# **Changes in Version 7.0**

The following properties in 'lp session cache' (/api/tm/7.0/status/local\_tm/statistics/cache/ip\_session\_cache) have been added:

Property 'statistics/expiries' was added.

The following properties in 'J2ee session cache' (/api/tm/7.0/status/local\_tm/statistics/cache/j2ee\_session\_cache) have been added:

Property 'statistics/expiries' was added.

The following properties in 'Virtual Server' (/api/tm/7.0/config/active/virtual\_servers) have been added:

Property 'sip/udp\_associate\_by\_source' was added.

The following properties in 'Uni session cache' (/api/tm/7.0/status/local\_tm/statistics/cache/uni\_session\_cache) have been added:

Property 'statistics/expiries' was added.

The following properties in 'Global Settings' (/api/tm/7.0/config/active/global\_settings) have been added:

- Property 'session/ip\_cache\_expiry' was added.
- Property 'session/j2ee\_cache\_expiry' was added.
- Property 'session/universal\_cache\_expiry' was added.

The following properties in 'Global Settings' (/api/tm/7.0/config/active/global\_settings) have been removed:

- Property 'admin/ssl\_prevent\_timing\_side\_channels' was removed.
- Property 'ssl/prevent\_timing\_side\_channels' was removed.

### **Changes in Version 6.2**

The following properties in 'Traffic Manager' (/api/tm/6.2/config/active/traffic\_managers) have been added:

- Property 'appliance/managegceroutes' was added.
- Property 'appliance/manageresolved' was added.
- Property 'remote\_licensing/is\_template' was added.
- Property 'remote\_licensing/registration\_identifier' was added.
- Property 'soap/max\_requests' was added.

The following properties in 'Global Settings' (/api/tm/6.2/config/active/global\_settings) have been added:

- Property 'gce/action\_timeout' was added.
- Property 'remote\_licensing/comm\_channel\_enabled' was added.
- Property 'remote\_licensing/comm\_channel\_port' was added.
- Property 'remote\_licensing/server\_certificate\_secondary' was added.
- Property 'rest\_api/maxfds' was added.
- Property 'ssl/middlebox\_compatibility' was added.
- Property 'watchdog/timeout' was added.

The following properties in 'Information' (/api/tm/6.2/status/local\_tm/information) have been added:

• Property 'information/platform' was added.

The following properties in 'Pool' (/api/tm/6.2/config/active/pools) have been added:

- Property 'connection/max\_transactions\_per\_node' was added.
- Property 'ssl/middlebox\_compatibility' was added.
- Property 'ssl/ssl\_fixed\_client\_certificate' was added.
- Property 'ssl/support\_tls1\_3' was added.

### **Changes in Version 6.1**

The following properties in 'Session Persistence Class' (/api/tm/6.1/config/active/persistence) have been added:

- Property 'basic/transparent\_always\_set\_cookie' was added.
- Property 'basic/transparent\_directives' was added.

The following properties in 'Virtual Server' (/api/tm/6.1/config/active/virtual\_servers) have been added:

Property 'ssl/support\_tls1\_3' was added.

The following properties in 'Globals' (/api/tm/6.1/status/local\_tm/statistics/globals) have been added:

Property 'statistics/ssl\_handshake\_tlsv13' was added.

The following properties in 'Virtual servers' (/api/tm/6.1/status/local\_tm/statistics/virtual\_servers/\*) have been added:

Property 'statistics/ssl\_hello\_retry\_requested' was added.

The following properties in 'Global Settings' (/api/tm/6.1/config/active/global\_settings) have been added:

- Property 'admin/support\_tls1\_3' was added.
- Property 'fault\_tolerance/multicast\_version' was added.
- Property 'ssl/log\_keys' was added.
- Property 'ssl/support\_tls1\_3' was added.
- Property 'telemetry/autotest\_schedule' was added.

The following properties in 'Traffic Manager' (/api/tm/6.1/config/active/traffic\_managers) have been renamed:

 Property 'basic/developer\_mode\_accepted' was renamed to 'basic/community\_edition\_ accepted'.

# **Changes in Version 6.0**

The following properties in 'Virtual Server' (/api/tm/6.0/config/active/virtual\_servers) have been added:

• Property 'basic/proxy\_protocol\_optional' was added.

The following properties in 'Pools' (/api/tm/6.0/status/local\_tm/statistics/pools/\*) have been added:

- Property 'statistics/http1xx\_responses' was added.
- Property 'statistics/http2xx\_responses' was added.
- Property 'statistics/http3xx\_responses' was added.
- Property 'statistics/http4xx\_responses' was added.
- Property 'statistics/http503\_retries' was added.
- Property 'statistics/http5xx\_responses' was added.

The following properties in 'GLB Service' (/api/tm/6.0/config/active/glb\_services) have been added:

• Property 'basic/optimistic\_location\_health' was added.

The following properties in 'Virtual servers' (/api/tm/6.0/status/local\_tm/statistics/virtual\_servers/\*) have been added:

- Property 'statistics/http1xx\_responses' was added.
- Property 'statistics/http2xx\_responses' was added.
- Property 'statistics/http3xx\_responses' was added.
- Property 'statistics/http4xx\_responses' was added.
- Property 'statistics/http5xx\_responses' was added.
- Property 'statistics/http\_cache2xx\_responses' was added.
- Property 'statistics/http\_cache3xx\_responses' was added.
- Property 'statistics/http\_cache4xx\_responses' was added.
- Property 'statistics/http\_cache5xx\_responses' was added.
- Property 'statistics/http\_generated2xx\_responses' was added.
- Property 'statistics/http\_generated3xx\_responses' was added.
- Property 'statistics/http\_generated4xx\_responses' was added.
- Property 'statistics/http\_generated5xx\_responses' was added.
- Property 'statistics/http\_server1xx\_responses' was added.
- Property 'statistics/http\_server2xx\_responses' was added.
- Property 'statistics/http\_server3xx\_responses' was added.
- Property 'statistics/http\_server4xx\_responses' was added.
- Property 'statistics/http\_server5xx\_responses' was added.

The following properties in 'Traffic Manager' (/api/tm/6.0/config/active/traffic\_managers) have been added:

- Property 'appliance/dnscache' was added.
- Property 'appliance/dnssec' was added.

The following properties in 'Web cache' (/api/tm/6.0/status/local\_tm/statistics/cache/web\_cache) have been removed:

- Property 'statistics/hits\_hi' was removed.
- Property 'statistics/hits\_lo' was removed.
- Property 'statistics/lookups\_hi' was removed.
- Property 'statistics/lookups\_lo' was removed.
- Property 'statistics/misses\_hi' was removed.
- Property 'statistics/misses\_lo' was removed.

The following properties in 'Pools' (/api/tm/6.0/status/local\_tm/statistics/pools/\*) have been removed:

- Property 'statistics/bw\_limit\_bytes\_drop' was removed.
- Property 'statistics/bw\_limit\_bytes\_drop\_hi' was removed.
- Property 'statistics/bw\_limit\_bytes\_drop\_lo' was removed.
- Property 'statistics/bw\_limit\_pkts\_drop' was removed.
- Property 'statistics/bw\_limit\_pkts\_drop\_hi' was removed.
- Property 'statistics/bw\_limit\_pkts\_drop\_lo' was removed.
- Property 'statistics/bytes\_in\_hi' was removed.
- Property 'statistics/bytes\_in\_lo' was removed.
- Property 'statistics/bytes\_out\_hi' was removed.
- Property 'statistics/bytes\_out\_lo' was removed.

The following properties in 'Globals' (/api/tm/6.0/status/local\_tm/statistics/globals) have been removed:

- Property 'statistics/ssl\_handshake\_sslv2' was removed.
- Property 'statistics/ssl\_session\_id\_disk\_cache\_hit' was removed.
- Property 'statistics/ssl\_session\_id\_disk\_cache\_miss' was removed.
- Property 'statistics/total\_bytes\_in\_hi' was removed.

- Property 'statistics/total\_bytes\_in\_lo' was removed.
- Property 'statistics/total\_bytes\_out\_hi' was removed.
- Property 'statistics/total\_bytes\_out\_lo' was removed.

The following properties in 'State' (/api/tm/6.0/status/local\_tm/state) have been removed:

- Property 'data\_plane\_acceleration/capable' was removed.
- Property 'data\_plane\_acceleration/configured' was removed.
- Property 'data\_plane\_acceleration/failed\_to\_start' was removed.
- Property 'data\_plane\_acceleration/running' was removed.

The following properties in 'Bandwidth' (/api/tm/6.0/status/local\_tm/statistics/bandwidth/\*) have been removed:

- Property 'statistics/bytes\_drop' was removed.
- Property 'statistics/bytes\_drop\_hi' was removed.
- Property 'statistics/bytes\_drop\_lo' was removed.
- Property 'statistics/bytes\_out\_hi' was removed.
- Property 'statistics/bytes\_out\_lo' was removed.
- Property 'statistics/pkts\_drop' was removed.
- Property 'statistics/pkts\_drop\_hi' was removed.
- Property 'statistics/pkts\_drop\_lo' was removed.

The following properties in 'Node inet46' (/api/tm/6.0/status/local\_tm/statistics/nodes/node\_inet46/\*) have been removed:

- Property 'statistics/bytes\_from\_node\_hi' was removed.
- Property 'statistics/bytes\_from\_node\_lo' was removed.
- Property 'statistics/bytes\_to\_node\_hi' was removed.
- Property 'statistics/bytes\_to\_node\_lo' was removed.

The following properties in 'Virtual Server' (/api/tm/6.0/config/active/virtual\_servers) have been removed:

- Property 'basic/bypass\_data\_plane\_acceleration' was removed.
- Property 'l4accel/rst\_on\_service\_failure' was removed.
- Property 'l4accel/service\_ip\_snat' was removed.
- Property 'l4accel/state\_sync' was removed.
- Property 'l4accel/tcp\_msl' was removed.
- Property 'l4accel/timeout' was removed.
- Property 'l4accel/udp\_count\_requests' was removed.
- Property 'l4stateless/initial\_ring\_size' was removed.
- Property 'l4stateless/num\_replicas' was removed.
- Property 'udp/udp\_end\_transaction' was removed.

The following properties in 'Per pool node' (/api/tm/6.0/status/local\_tm/statistics/nodes/per\_pool\_node/\*) have been removed:

- Property 'statistics/bytes\_from\_node\_hi' was removed.
- Property 'statistics/bytes\_from\_node\_lo' was removed.
- Property 'statistics/bytes\_to\_node\_hi' was removed.
- Property 'statistics/bytes\_to\_node\_lo' was removed.
- Property 'statistics/I4\_stateless\_buckets' was removed.
- Property 'statistics/pkts\_from\_node' was removed.
- Property 'statistics/pkts\_from\_node\_hi' was removed.
- Property 'statistics/pkts\_from\_node\_lo' was removed.
- Property 'statistics/pkts\_to\_node' was removed.
- Property 'statistics/pkts\_to\_node\_hi' was removed.
- Property 'statistics/pkts\_to\_node\_lo' was removed.

The following properties in 'Virtual servers' (/api/tm/6.0/status/local\_tm/statistics/virtual\_servers/\*) have been removed:

- Property 'statistics/auth\_saml\_redirects\_hi' was removed.
- Property 'statistics/auth\_saml\_redirects\_lo' was removed.
- Property 'statistics/auth\_saml\_responses\_accepted\_hi' was removed.
- Property 'statistics/auth\_saml\_responses\_accepted\_lo' was removed.
- Property 'statistics/auth\_saml\_responses\_hi' was removed.
- Property 'statistics/auth\_saml\_responses\_lo' was removed.
- Property 'statistics/auth\_saml\_responses\_rejected\_hi' was removed.
- Property 'statistics/auth\_saml\_responses\_rejected\_lo' was removed.
- Property 'statistics/auth\_sessions\_created\_hi' was removed.
- Property 'statistics/auth\_sessions\_created\_lo' was removed.
- Property 'statistics/auth\_sessions\_rejected\_hi' was removed.
- Property 'statistics/auth\_sessions\_rejected\_lo' was removed.
- Property 'statistics/auth\_sessions\_used\_hi' was removed.
- Property 'statistics/auth\_sessions\_used\_lo' was removed.
- Property 'statistics/bw\_limit\_bytes\_drop' was removed.
- Property 'statistics/bw\_limit\_bytes\_drop\_hi' was removed.
- Property 'statistics/bw\_limit\_bytes\_drop\_lo' was removed.
- Property 'statistics/bw\_limit\_pkts\_drop' was removed.
- Property 'statistics/bw\_limit\_pkts\_drop\_hi' was removed.
- Property 'statistics/bw\_limit\_pkts\_drop\_lo' was removed.
- Property 'statistics/bytes\_in\_hi' was removed.
- Property 'statistics/bytes\_in\_lo' was removed.
- Property 'statistics/bytes\_out\_hi' was removed.

- Property 'statistics/bytes\_out\_lo' was removed.
- Property 'statistics/gzip\_bytes\_saved\_hi' was removed.
- Property 'statistics/gzip\_bytes\_saved\_lo' was removed.
- Property 'statistics/pkts\_in' was removed.
- Property 'statistics/pkts\_in\_hi' was removed.
- Property 'statistics/pkts\_in\_lo' was removed.
- Property 'statistics/pkts\_out' was removed.
- Property 'statistics/pkts\_out\_hi' was removed.
- Property 'statistics/pkts\_out\_lo' was removed.
- Property 'statistics/ssl\_cache\_lookup\_hi' was removed.
- Property 'statistics/ssl\_cache\_lookup\_lo' was removed.
- Property 'statistics/ssl\_cache\_miss\_hi' was removed.
- Property 'statistics/ssl\_cache\_miss\_lo' was removed.
- Property 'statistics/ssl\_cache\_rejected\_hi' was removed.
- Property 'statistics/ssl\_cache\_rejected\_lo' was removed.
- Property 'statistics/ssl\_cache\_resumed\_hi' was removed.
- Property 'statistics/ssl\_cache\_resumed\_lo' was removed.
- Property 'statistics/ssl\_cache\_saved\_hi' was removed.
- Property 'statistics/ssl\_cache\_saved\_lo' was removed.
- Property 'statistics/ssl\_new\_session\_hi' was removed.
- Property 'statistics/ssl\_new\_session\_lo' was removed.
- Property 'statistics/ssl\_ticket\_expired\_hi' was removed.
- Property 'statistics/ssl\_ticket\_expired\_lo' was removed.
- Property 'statistics/ssl\_ticket\_issued\_hi' was removed.

- Property 'statistics/ssl\_ticket\_issued\_lo' was removed.
- Property 'statistics/ssl\_ticket\_key\_not\_found\_hi' was removed.
- Property 'statistics/ssl\_ticket\_key\_not\_found\_lo' was removed.
- Property 'statistics/ssl\_ticket\_received\_hi' was removed.
- Property 'statistics/ssl\_ticket\_received\_lo' was removed.
- Property 'statistics/ssl\_ticket\_rejected\_hi' was removed.
- Property 'statistics/ssl\_ticket\_rejected\_lo' was removed.
- Property 'statistics/ssl\_ticket\_resumed\_hi' was removed.
- Property 'statistics/ssl\_ticket\_resumed\_lo' was removed.
- Property 'statistics/total\_conn' was removed.
- Property 'statistics/total\_http1\_requests\_hi' was removed.
- Property 'statistics/total\_http1\_requests\_lo' was removed.
- Property 'statistics/total\_http2\_requests\_hi' was removed.
- Property 'statistics/total\_http2\_requests\_lo' was removed.
- Property 'statistics/total\_http\_requests\_hi' was removed.
- Property 'statistics/total\_http\_requests\_lo' was removed.
- Property 'statistics/total\_requests\_hi' was removed.
- Property 'statistics/total\_requests\_lo' was removed.
- Property 'statistics/total\_tcp\_reset' was removed.
- Property 'statistics/total\_udp\_unreachables' was removed.

The following properties in 'Global Settings' (/api/tm/6.0/config/active/global\_settings) have been removed:

- Property 'basic/data\_plane\_acceleration\_cores' was removed.
- Property 'basic/data\_plane\_acceleration\_mode' was removed.
- Property 'data\_plane\_acceleration/tcp\_delay\_ack' was removed.

- Property 'data\_plane\_acceleration/tcp\_win\_scale' was removed.
- Property 'fault\_tolerance/l4accel\_child\_timeout' was removed.
- Property 'fault\_tolerance/l4accel\_sync\_port' was removed.
- Property 'l4accel/max\_concurrent\_connections' was removed.
- Property 'source\_nat/clist\_locks' was removed.
- Property 'source\_nat/ip\_limit' was removed.
- Property 'source\_nat/ip\_local\_port\_range\_high' was removed.
- Property 'source\_nat/portmaphashtable\_locks' was removed.
- Property 'source\_nat/shared\_pool\_size' was removed.

The following properties in 'Listen ips' (/api/tm/6.0/status/local\_tm/statistics/listen\_ips/\*) have been removed:

- Property 'statistics/bytes\_in\_hi' was removed.
- Property 'statistics/bytes\_in\_lo' was removed.
- Property 'statistics/bytes\_out\_hi' was removed.
- Property 'statistics/bytes\_out\_lo' was removed.
- Property 'statistics/total\_conn' was removed.
- Property 'statistics/total\_requests\_hi' was removed.
- Property 'statistics/total\_requests\_lo' was removed.

The following properties in 'lp gateway' (/api/tm/6.0/status/local\_tm/statistics/traffic\_ips/ip\_gateway) have been removed:

- Property 'statistics/number' was removed.
- Property 'statistics/number\_raised' was removed.

The following properties in 'Pool' (/api/tm/6.0/config/active/pools) have been removed:

Property 'l4accel/snat' was removed.

The following properties in 'Traffic IP Group' (/api/tm/6.0/config/active/traffic\_ip\_groups) have been removed:

Property 'basic/backend\_traffic\_ips' was removed.

The following properties in 'Traffic Manager' (/api/tm/6.0/config/active/traffic\_managers) have been removed:

- Property 'appliance/managedpa' was removed.
- Property 'basic/num\_I4\_children' was removed.
- Property 'basic/num\_I7\_children' was removed.
- Property 'fault\_tolerance/lss\_dedicated\_ips' was removed.
- Property 'iop/enable\_lb' was removed.
- Property 'iop/is\_standalone' was removed.
- Property 'iop/l4\_event\_driven\_mode' was removed.
- Property 'iop/I7\_event\_driven\_mode' was removed.
- Property 'iop/linux\_interface' was removed.
- Property 'iop/num\_hugepages' was removed.
- Property 'iop/num\_mbufs\_per\_mpool' was removed.
- Property 'iop/send\_to\_linux' was removed.
- Property 'iop/size\_hugepage' was removed.

The following properties in 'Network interface' (/api/tm/6.0/status/local\_tm/statistics/network\_interface/\*) have been removed:

- Property 'statistics/rx\_bytes\_hi' was removed.
- Property 'statistics/rx\_bytes\_lo' was removed.
- Property 'statistics/tx\_bytes\_hi' was removed.
- Property 'statistics/tx\_bytes\_lo' was removed.

The following properties for 'Monitor' (/api/tm/6.0/config/active/monitors) have had flags change:

- Property 'basic/machine' has had the following flags added: [ HTML ]
- Property 'basic/scope' has had the following flags added: [ HTML ]
- Property 'http/authentication' has had the following flags added: [ HTML ]
- Property 'http/body\_regex' has had the following flags added: [ HTML ]
- Property 'http/path' has had the following flags added: [ HTML ]
- Property 'http/status\_regex' has had the following flags added: [ HTML ]
- Property 'script/program' has had the following flags added: [ HTML ]
- Table property 'script/arguments' field 'description' has had the following flags added: [ HTML ]
- Table property 'script/arguments' field 'value' has had the following flags added: [ HTML ]

The following properties for 'Virtual Server' (/api/tm/6.0/config/active/virtual\_servers) have had flags change:

- Property 'auth/saml\_idp' has had the following flags added: [ HTML ]
- Property 'basic/connect\_timeout' has had the following flags added: [ HTML ]
- Property 'basic/max\_concurrent\_connections' has had the following flags added: [ HTML ]
- Property 'connection/keepalive\_timeout' has had the following flags added: [ HTML ]
- Property 'connection/max\_client\_buffer' has had the following flags added: [ HTML ]
- Property 'connection/max\_server\_buffer' has had the following flags added: [ HTML ]
- Property 'connection/max\_transaction\_duration' has had the following flags added: [ HTML ]
- Property 'connection/timeout' has had the following flags added: [ HTML ]
- Property 'connection\_errors/error\_file' has had the following flags added: [ HTML ]
- Property 'ftp/data\_source\_port' has had the following flags added: [ HTML ]
- Property 'http/location\_replace' has had the following flags added: [ HTML ]
- Property 'http/location\_rewrite' has had the following flags added: [ HTML ]
- Property 'http2/connect\_timeout' has had the following flags added: [ HTML ]
- Property 'http2/headers\_index\_default' has had the following flags added: [ HTML ]

- Property 'http2/headers\_index\_whitelist' has had the following flags added: [ HTML ]
- Property 'http2/headers\_size\_limit' has had the following flags added: [ HTML ]
- Property 'http2/idle\_timeout\_no\_streams' has had the following flags added: [ HTML ]
- Property 'http2/idle\_timeout\_open\_streams' has had the following flags added: [ HTML ]
- Property 'http2/max\_header\_padding' has had the following flags added: [ HTML ]
- Property 'log/filename' has had the following flags added: [ HTML ]
- Property 'log/format' has had the following flags added: [ HTML ]
- Property 'log/save\_all' has had the following flags added: [ HTML ]
- Property 'log/server\_connection\_failures' has had the following flags added: [ HTML ]
- Property 'recent\_connections/enabled' has had the following flags added: [ HTML ]
- Property 'recent\_connections/save\_all' has had the following flags added: [ HTML ]
- Property 'sip/follow\_route' has had the following flags added: [ HTML ]
- Property 'sip/max\_connection\_mem' has had the following flags added: [ HTML ]
- Property 'ssl/cipher\_suites' has had the following flags added: [ HTML ]
- Property 'ssl/elliptic\_curves' has had the following flags added: [ HTML ]
- Property 'ssl/honor\_fallback\_scsv' has had the following flags added: [ HTML ]
- Property 'ssl/ocsp\_max\_response\_age' has had the following flags added: [ HTML ]
- Property 'ssl/send\_close\_alerts' has had the following flags added: [ HTML ]
- Property 'ssl/session\_cache\_enabled' has had the following flags added: [ HTML ]
- Property 'ssl/session\_tickets\_enabled' has had the following flags added: [ HTML ]
- Property 'ssl/signature\_algorithms' has had the following flags added: [ HTML ]
- Property 'ssl/support\_ssl3' has had the following flags added: [ HTML ]
- Property 'ssl/support\_tls1' has had the following flags added: [ HTML ]
- Property 'ssl/support\_tls1\_1' has had the following flags added: [ HTML ]

- Property 'ssl/support\_tls1\_2' has had the following flags added: [ HTML ]
- Property 'ssl/trust\_magic' has had the following flags added: [ HTML ]
- Property 'syslog/format' has had the following flags added: [ HTML ]
- Property 'tcp/proxy\_close' has had the following flags added: [ HTML ]
- Property 'transaction\_export/enabled' has had the following flags added: [ HTML ]
- Property 'transaction\_export/hi\_res' has had the following flags added: [ HTML ]
- Property 'udp/end\_point\_persistence' has had the following flags added: [ HTML ]
- Property 'udp/response\_datagrams\_expected' has had the following flags added: [ HTML ]
- Property 'web\_cache/control\_out' has had the following flags added: [ HTML ]
- Property 'web\_cache/enabled' has had the following flags added: [ HTML ]
- Property 'web\_cache/refresh\_time' has had the following flags added: [ HTML ]

The following properties for 'Pool' (/api/tm/6.0/config/active/pools) have had flags change:

- Property 'auto\_scaling/extraargs' has had the following flags removed: [ EXPERT ]
- Property 'basic/max\_timed\_out\_connection\_attempts' has had the following flags added: [
   HTML ]
- Property 'basic/node\_connection\_attempts' has had the following flags added: [ HTML ]
- Property 'basic/node\_delete\_behavior' has had the following flags added: [ HTML ]
- Property 'basic/passive\_monitoring' has had the following flags added: [ HTML ]
- Property 'dns\_autoscale/enabled' has had the following flags added: [ HTML ]
- Property 'dns\_autoscale/hostnames' has had the following flags added: [ HTML ]
- Property 'ssl/cipher\_suites' has had the following flags added: [ HTML ]
- Property 'ssl/elliptic\_curves' has had the following flags added: [ HTML ]
- Property 'ssl/enhance' has had the following flags added: [ HTML ]
- Property 'ssl/send\_close\_alerts' has had the following flags added: [ HTML ]
- Property 'ssl/session\_cache\_enabled' has had the following flags added: [ HTML ]

- Property 'ssl/session\_tickets\_enabled' has had the following flags added: [ HTML ]
- Property 'ssl/signature\_algorithms' has had the following flags added: [ HTML ]
- Property 'ssl/support\_ssl3' has had the following flags added: [ HTML ]
- Property 'ssl/support\_tls1' has had the following flags added: [ HTML ]
- Property 'ssl/support\_tls1\_1' has had the following flags added: [HTML]
- Property 'ssl/support\_tls1\_2' has had the following flags added: [ HTML ]
- Property 'udp/accept\_from' has had the following flags added: [ HTML ]
- Property 'udp/accept\_from\_mask' has had the following flags added: [ HTML ]

The following properties for 'TrafficScript Authenticator' (/api/tm/6.0/config/active/rule\_authenticators) have had flags change:

Property 'ldap/filter' has had the following flags added: [ HTML ]

The following properties for 'Alerting Action' (/api/tm/6.0/config/active/actions) have had flags change:

- Property 'log/file' has had the following flags added: [ HTML ]
- Table property 'program/arguments' field 'description' has had the following flags added: [
   HTML ]
- Table property 'program/arguments' field 'value' has had the following flags added: [ HTML ]

The following properties for 'Traffic Manager' (/api/tm/6.0/config/active/traffic\_managers) have had flags change:

- Property 'appliance/name\_servers' has had the following flags added: [ HTML ]
- Property 'appliance/search\_domains' has had the following flags added: [ HTML ]
- Property 'appliance/timezone' has had the following flags added: [ HTML ]
- Property 'appliance/vlans' has had the following flags added: [ HTML ]
- Property 'cluster\_comms/allow\_update' has had the following flags added: [ HTML ]
- Property 'cluster\_comms/bind\_ip' has had the following flags added: [ HTML ]
- Property 'cluster\_comms/port' has had the following flags added: [ HTML ]

- Property 'fault\_tolerance/bgp\_router\_id' has had the following flags added: [ HTML ]
- Property 'fault\_tolerance/ospfv2\_ip' has had the following flags added: [ HTML ]
- Property 'rest\_api/port' has had the following flags added: [ HTML ]
- Property 'snmp/allow' has had the following flags added: [ HTML ]
- Property 'snmp/auth\_password' has had the following flags added: [ HTML ]
- Property 'snmp/bind\_ip' has had the following flags added: [ HTML ]
- Property 'snmp/port' has had the following flags added: [ HTML ]
- Property 'snmp/priv\_password' has had the following flags added: [ HTML ]
- Table property 'appliance/hosts' field 'ip\_address' has had the following flags added: [ HTML ]
- Table property 'appliance/if' field 'autoneg' has had the following flags added: [ HTML ]
- Table property 'appliance/if' field 'duplex' has had the following flags added: [ HTML ]
- Table property 'appliance/if' field 'mode' has had the following flags added: [ HTML ]
- Table property 'appliance/if' field 'speed' has had the following flags added: [ HTML ]
- Table property 'appliance/ip' field 'addr' has had the following flags added: [ HTML ]
- Table property 'appliance/ip' field 'isexternal' has had the following flags added: [ HTML ]
- Table property 'appliance/ip' field 'mask' has had the following flags added: [ HTML ]
- Table property 'appliance/routes' field 'gw' has had the following flags added: [ HTML ]
- Table property 'appliance/routes' field 'if' has had the following flags added: [ HTML ]
- Table property 'appliance/routes' field 'mask' has had the following flags added: [ HTML ]

The following properties for 'Global Settings' (/api/tm/6.0/config/active/global\_settings) have had flags change:

- Property 'admin/ssl3\_ciphers' has had the following flags added: [ HTML ]
- Property 'admin/ssl3\_min\_rehandshake\_interval' has had the following flags added: [ HTML ]
- Property 'admin/ssl\_elliptic\_curves' has had the following flags added: [ HTML ]
- Property 'admin/ssl\_max\_handshake\_message\_size' has had the following flags added: [ HTML ]

- Property 'admin/ssl\_signature\_algorithms' has had the following flags added: [ HTML ]
- Property 'appliance/return\_path\_routing\_enabled' has had the following flags added: [ HTML ]
- Property 'auditlog/via\_eventd' has had the following flags added: [ HTML ]
- Property 'auditlog/via\_syslog' has had the following flags added: [ HTML ]
- Property 'basic/license\_servers' has had the following flags added: [ HTML ]
- Property 'basic/monitor\_memory\_size' has had the following flags added: [ HTML ]
- Property 'basic/shared\_pool\_size' has had the following flags added: [ HTML ]
- Property 'basic/so\_rbuff\_size' has had the following flags added: [ HTML ]
- Property 'basic/so\_wbuff\_size' has had the following flags added: [ HTML ]
- Property 'basic/socket\_optimizations' has had the following flags added: [ HTML ]
- Property 'cluster\_comms/allow\_update\_default' has had the following flags added: [ HTML ]
- Property 'cluster\_comms/allowed\_update\_hosts' has had the following flags added: [ HTML ]
- Property 'cluster\_comms/state\_sync\_interval' has had the following flags added: [ HTML ]
- Property 'connection/idle\_connections\_max' has had the following flags added: [ HTML ]
- Property 'connection/listen\_queue\_size' has had the following flags added: [ HTML ]
- Property 'connection/max\_accepting' has had the following flags added: [ HTML ]
- Property 'dns/hosts' has had the following flags added: [ HTML ]
- Property 'dns/hostsfirst' has had the following flags added: [ HTML ]
- Property 'dns/resolv' has had the following flags added: [ HTML ]
- Property 'ec2/metadata\_server' has had the following flags added: [ HTML ]
- Property 'ec2/query\_server' has had the following flags added: [ HTML ]
- Property 'fault\_tolerance/frontend\_check\_ips' has had the following flags added: [ HTML ]
- Property 'ftp/data\_bind\_low' has had the following flags added: [ HTML ]
- Property 'historical\_activity/keep\_days' has had the following flags added: [ HTML ]

- Property 'java/enabled' has had the following flags added: [ HTML ]
- Property 'java/lib' has had the following flags added: [ HTML ]
- Property 'log/error\_level' has had the following flags added: [ HTML ]
- Property 'log\_export/max\_event\_message\_size' has had the following flags added: [ HTML ]
- Property 'log\_export/max\_request\_size' has had the following flags added: [ HTML ]
- Property 'log\_export/max\_response\_size' has had the following flags added: [ HTML ]
- Property 'log\_export/request\_timeout' has had the following flags added: [ HTML ]
- Property 'protection/conncount\_size' has had the following flags added: [ HTML ]
- Property 'recent\_connections/max\_per\_process' has had the following flags added: [ HTML ]
- Property 'recent\_connections/snapshot\_size' has had the following flags added: [ HTML ]
- Property 'remote\_licensing/registration\_server' has had the following flags added: [ HTML ]
- Property 'rest\_api/http\_compress\_min' has had the following flags added: [ HTML ]
- Property 'rest\_api/http\_keep\_alive\_timeout' has had the following flags added: [ HTML ]
- Property 'rest\_api/http\_max\_resource\_body\_length' has had the following flags added: [ HTML ]
- Property 'rest\_api/http\_max\_write\_buffer' has had the following flags added: [ HTML ]
- Property 'rest\_api/http\_session\_timeout' has had the following flags added: [ HTML ]
- Property 'security/login\_banner\_accept' has had the following flags added: [ HTML ]
- Property 'security/login\_delay' has had the following flags added: [ HTML ]
- Property 'security/max\_login\_attempts' has had the following flags added: [ HTML ]
- Property 'security/max\_login\_external' has had the following flags added: [ HTML ]
- Property 'security/max\_login\_suspension\_time' has had the following flags added: [ HTML ]
- Property 'security/password\_changes\_per\_day' has had the following flags added: [ HTML ]
- Property 'security/password\_min\_length' has had the following flags added: [ HTML ]
- Property 'security/password\_min\_numeric\_chars' has had the following flags added: [ HTML ]

- Property 'security/password\_min\_special\_chars' has had the following flags added: [ HTML ]
- Property 'security/password\_min\_uppercase\_chars' has had the following flags added: [ HTML ]
- Property 'security/password\_reuse\_after' has had the following flags added: [ HTML ]
- Property 'security/track\_unknown\_users' has had the following flags added: [ HTML ]
- Property 'ssl/cache\_size' has had the following flags added: [ HTML ]
- Property 'ssl/cipher\_suites' has had the following flags added: [ HTML ]
- Property 'ssl/client\_cache\_expiry' has had the following flags added: [ HTML ]
- Property 'ssl/client\_cache\_size' has had the following flags added: [ HTML ]
- Property 'ssl/crl\_mem\_size' has had the following flags added: [ HTML ]
- Property 'ssl/elliptic\_curves' has had the following flags added: [ HTML ]
- Property 'ssl/max\_handshake\_message\_size' has had the following flags added: [ HTML ]
- Property 'ssl/min\_rehandshake\_interval' has had the following flags added: [ HTML ]
- Property 'ssl/ocsp\_stapling\_mem\_size' has had the following flags added: [ HTML ]
- Property 'ssl/signature\_algorithms' has had the following flags added: [ HTML ]
- Property 'trafficscript/data\_local\_size' has had the following flags added: [ HTML ]
- Property 'trafficscript/data\_size' has had the following flags added: [ HTML ]
- Property 'trafficscript/execution\_time\_warning' has had the following flags added: [ HTML ]
- Property 'trafficscript/memory\_warning' has had the following flags added: [ HTML ]
- Property 'trafficscript/variable\_pool\_use' has had the following flags added: [ HTML ]
- Property 'web\_cache/disk' has had the following flags added: [ HTML ]
- Property 'web\_cache/disk\_dir' has had the following flags added: [ HTML ]
- Property 'web\_cache/max\_file\_size' has had the following flags added: [ HTML ]
- Property 'web\_cache/size' has had the following flags added: [ HTML ]
- Table property 'ip/appliance\_returnpath' field 'ipv4' has had the following flags added: [ HTML ]

Table property 'ip/appliance\_returnpath' field 'ipv6' has had the following flags added: [ HTML ]

The following properties for 'User Authenticator' (/api/tm/6.0/config/active/user\_authenticators) have had flags change:

- Property 'ldap/base\_dn' has had the following flags added: [ HTML ]
- Property 'ldap/bind\_dn' has had the following flags added: [ HTML ]
- Property 'ldap/dn\_method' has had the following flags added: [ HTML ]
- Property 'ldap/fallback\_group' has had the following flags added: [ HTML ]
- Property 'ldap/filter' has had the following flags added: [ HTML ]
- Property 'ldap/group\_attribute' has had the following flags added: [ HTML ]
- Property 'ldap/group\_field' has had the following flags added: [ HTML ]
- Property 'ldap/group\_filter' has had the following flags added: [ HTML ]
- Property 'Idap/port' has had the following flags added: [ HTML ]
- Property 'ldap/search\_dn' has had the following flags added: [ HTML ]
- Property 'ldap/search\_password' has had the following flags added: [ HTML ]
- Property 'ldap/server' has had the following flags added: [ HTML ]
- Property 'ldap/timeout' has had the following flags added: [ HTML ]

The following properties for 'Kerberos Principal' (/api/tm/6.0/config/active/kerberos/principals) have had flags change:

Property 'basic/kdcs' has had the following flags added: [ HTML ]

The following properties for 'Rate Shaping Class' (/api/tm/6.0/config/active/rate) have had flags change:

- Property 'basic/max\_rate\_per\_minute' has had the following flags added: [ HTML ]
- Property 'basic/max\_rate\_per\_second' has had the following flags added: [ HTML ]

The following properties for 'Event Type' (/api/tm/6.0/config/active/event\_types) have had flags change:

Property 'basic/actions' has had the following flags added: [ HTML ]

Property 'basic/built\_in' has had the following flags added: [ HTML ]

The following properties for 'Protection Class' (/api/tm/6.0/config/active/protection) have had flags change:

- Property 'basic/log\_time' has had the following flags added: [ HTML ]
- Property 'concurrent\_connections/max\_10\_connections' has had the following flags added: [
   HTML ]
- Property 'concurrent\_connections/max\_1\_connections' has had the following flags added: [
   HTML ]
- Property 'concurrent\_connections/min\_connections' has had the following flags added: [ HTML ]
- Property 'concurrent\_connections/per\_process\_connection\_count' has had the following flags added: [ HTML ]
- Property 'connection\_rate/max\_connection\_rate' has had the following flags added: [ HTML ]
- Property 'connection\_rate/rate\_timer' has had the following flags added: [ HTML ]
- Property 'http/max\_body\_length' has had the following flags added: [ HTML ]
- Property 'http/max\_header\_length' has had the following flags added: [ HTML ]
- Property 'http/max\_request\_length' has had the following flags added: [ HTML ]
- Property 'http/max\_url\_length' has had the following flags added: [ HTML ]

The following properties for 'Session Persistence Class' (/api/tm/6.0/config/active/persistence) have had flags change:

Property 'basic/delete' has had the following flags added: [ HTML ]

The following properties for 'Traffic IP Group' (/api/tm/6.0/config/active/traffic\_ip\_groups) have had flags change:

- Property 'basic/enabled' has had the following flags added: [ HTML ]
- Property 'basic/keeptogether' has had the following flags added: [ HTML ]
- Property 'basic/mode' has had the following flags added: [ HTML ]

Table property 'basic/ip\_mapping' field 'traffic\_manager' has had the following flags added: [
HTML]

The following properties for 'User Group' (/api/tm/6.0/config/active/user\_groups) have had flags change:

- Property 'basic/password\_expire\_time' has had the following flags added: [ HTML ]
- Property 'basic/timeout' has had the following flags added: [ HTML ]

# **Changes in Version 5.2**

The following resources were added:

• Resource 'Service Discovery Plugins' (/api/tm/5.2/config/active/servicediscovery)

The following properties in 'Global Settings' (/api/tm/5.2/config/active/global\_settings) have been added:

- Property 'ssl/validate\_server\_certificates\_catalog' was added.
- Property 'telemetry/enabled' was added.
- Property 'telemetry/internal\_use' was added.
- Property 'telemetry/test\_schedule' was added.
- Property 'telemetry/url' was added.

The following properties in 'Traffic Manager' (/api/tm/5.2/config/active/traffic\_managers) have been added:

Property 'appliance/disable\_kpti' was added.

The following properties in 'Pool' (/api/tm/5.2/config/active/pools) have been added:

- Property 'service\_discovery/enabled' was added.
- Property 'service\_discovery/interval' was added.
- Property 'service\_discovery/plugin' was added.
- Property 'service\_discovery/plugin\_args' was added.
- Property 'service\_discovery/timeout' was added.

Property 'ssl/session\_tickets\_enabled' was added.

The following properties for 'Global Settings' (/api/tm/5.2/config/active/global\_settings) have had flags change:

Property 'remote\_licensing/owner\_secret' has had the following flags added: [TSR\_IGNORE]

# **Changes in Version 5.1**

The following resources were added:

Resource 'Trusted SAML Identity Provider' (/api/tm/5.1/config/active/saml/trustedidps)

The following properties in 'Virtual Server' (/api/tm/5.1/config/active/virtual\_servers) have been added:

- Property 'auth/saml\_idp' was added.
- Property 'auth/saml\_nameid\_format' was added.
- Property 'auth/saml\_sp\_acs\_url' was added.
- Property 'auth/saml\_sp\_entity\_id' was added.
- Property 'auth/saml\_time\_tolerance' was added.
- Property 'auth/session\_cookie\_attributes' was added.
- Property 'auth/session\_cookie\_name' was added.
- Property 'auth/session\_log\_external\_state' was added.
- Property 'auth/session\_timeout' was added.
- Property 'auth/type' was added.
- Property 'auth/verbose' was added.

The following properties in 'Global Settings' (/api/tm/5.1/config/active/global\_settings) have been added:

- · Property 'auth/saml\_key\_lifetime' was added.
- Property 'auth/saml\_key\_rotation\_interval' was added.

The following properties in 'Virtual servers' (/api/tm/5.1/status/local\_tm/statistics/virtual\_servers/\*) have been added:

- Property 'statistics/auth\_saml\_redirects' was added.
- Property 'statistics/auth\_saml\_redirects\_hi' was added.
- Property 'statistics/auth\_saml\_redirects\_lo' was added.
- Property 'statistics/auth\_saml\_responses' was added.
- Property 'statistics/auth\_saml\_responses\_accepted' was added.
- Property 'statistics/auth\_saml\_responses\_accepted\_hi' was added.
- Property 'statistics/auth\_saml\_responses\_accepted\_lo' was added.
- Property 'statistics/auth\_saml\_responses\_hi' was added.
- Property 'statistics/auth\_saml\_responses\_lo' was added.
- Property 'statistics/auth\_saml\_responses\_rejected' was added.
- Property 'statistics/auth\_saml\_responses\_rejected\_hi' was added.
- Property 'statistics/auth\_saml\_responses\_rejected\_lo' was added.
- Property 'statistics/auth\_sessions\_created' was added.
- Property 'statistics/auth\_sessions\_created\_hi' was added.
- Property 'statistics/auth\_sessions\_created\_lo' was added.
- Property 'statistics/auth\_sessions\_rejected' was added.
- Property 'statistics/auth\_sessions\_rejected\_hi' was added.
- Property 'statistics/auth\_sessions\_rejected\_lo' was added.
- Property 'statistics/auth\_sessions\_used' was added.
- Property 'statistics/auth\_sessions\_used\_hi' was added.
- Property 'statistics/auth\_sessions\_used\_lo' was added.

## **Changes in Version 5.0**

The following resources were added:

Resource 'SSL Ticket Key' (/api/tm/5.0/config/active/ssl/ticket\_keys)

The following properties in 'Pool' (/api/tm/5.0/config/active/pools) have been added:

Property 'ssl/session\_cache\_enabled' was added.

The following properties in 'Traffic Manager' (/api/tm/5.0/config/active/traffic\_managers) have been added:

- Property 'appliance/disable\_cloud\_init' was added.
- Property 'appliance/managereservedports' was added.
- Property 'appliance/manageservices' was added.

The following properties in 'Global Settings' (/api/tm/5.0/config/active/global\_settings) have been added:

- Property 'ec2/metadata\_server' was added.
- Property 'ec2/query\_server' was added.
- Property 'ssl/cache\_enabled' was added.
- Property 'ssl/client\_cache\_enabled' was added.
- Property 'ssl/client\_cache\_expiry' was added.
- Property 'ssl/client\_cache\_size' was added.
- Property 'ssl/client\_cache\_tickets\_enabled' was added.
- Property 'ssl/tickets\_enabled' was added.
- Property 'ssl/tickets\_reissue\_policy' was added.
- Property 'ssl/tickets\_ticket\_expiry' was added.
- Property 'ssl/tickets\_ticket\_key\_expiry' was added.
- Property 'ssl/tickets\_ticket\_key\_rotation' was added.
- Property 'ssl/tickets\_time\_tolerance' was added.

The following properties in 'Virtual Server' (/api/tm/5.0/config/active/virtual\_servers) have been added:

- Property 'log/ssl\_resumption\_failures' was added.
- Property 'ssl/session\_cache\_enabled' was added.

Property 'ssl/session\_tickets\_enabled' was added.

The following properties in 'Globals' (/api/tm/5.0/status/local\_tm/statistics/globals) have been added:

- Property 'statistics/ssl\_handshake\_tlsv1' was added.
- Property 'statistics/ssl\_handshake\_tlsv11' was added.
- Property 'statistics/ssl\_handshake\_tlsv12' was added.

The following properties in 'Virtual servers' (/api/tm/5.0/status/local\_tm/statistics/virtual\_servers/\*) have been added:

- Property 'statistics/ssl\_cache\_lookup' was added.
- Property 'statistics/ssl\_cache\_lookup\_hi' was added.
- Property 'statistics/ssl\_cache\_lookup\_lo' was added.
- Property 'statistics/ssl\_cache\_miss' was added.
- Property 'statistics/ssl\_cache\_miss\_hi' was added.
- Property 'statistics/ssl\_cache\_miss\_lo' was added.
- Property 'statistics/ssl\_cache\_rejected' was added.
- Property 'statistics/ssl\_cache\_rejected\_hi' was added.
- Property 'statistics/ssl\_cache\_rejected\_lo' was added.
- Property 'statistics/ssl\_cache\_resumed' was added.
- Property 'statistics/ssl\_cache\_resumed\_hi' was added.
- Property 'statistics/ssl\_cache\_resumed\_lo' was added.
- Property 'statistics/ssl\_cache\_saved' was added.
- Property 'statistics/ssl\_cache\_saved\_hi' was added.
- Property 'statistics/ssl\_cache\_saved\_lo' was added.
- Property 'statistics/ssl\_new\_session' was added.
- Property 'statistics/ssl\_new\_session\_hi' was added.
- Property 'statistics/ssl\_new\_session\_lo' was added.

- Property 'statistics/ssl\_ticket\_expired' was added.
- Property 'statistics/ssl\_ticket\_expired\_hi' was added.
- Property 'statistics/ssl\_ticket\_expired\_lo' was added.
- Property 'statistics/ssl\_ticket\_issued' was added.
- Property 'statistics/ssl\_ticket\_issued\_hi' was added.
- Property 'statistics/ssl\_ticket\_issued\_lo' was added.
- Property 'statistics/ssl\_ticket\_key\_not\_found' was added.
- Property 'statistics/ssl\_ticket\_key\_not\_found\_hi' was added.
- Property 'statistics/ssl\_ticket\_key\_not\_found\_lo' was added.
- Property 'statistics/ssl\_ticket\_received' was added.
- Property 'statistics/ssl\_ticket\_received\_hi' was added.
- Property 'statistics/ssl\_ticket\_received\_lo' was added.
- Property 'statistics/ssl\_ticket\_rejected' was added.
- Property 'statistics/ssl\_ticket\_rejected\_hi' was added.
- Property 'statistics/ssl\_ticket\_rejected\_lo' was added.
- Property 'statistics/ssl\_ticket\_resumed' was added.
- Property 'statistics/ssl\_ticket\_resumed\_hi' was added.
- Property 'statistics/ssl\_ticket\_resumed\_lo' was added.

The following properties in 'Pool' (/api/tm/5.0/config/active/pools) have been removed:

Property 'ssl/ssl\_support\_ssl2' was removed.

The following properties in 'Traffic Manager' (/api/tm/5.0/config/active/traffic\_managers) have been removed:

- Property 'appliance/force\_hardware' was removed.
- Property 'appliance/shim\_client\_id' was removed.
- Property 'appliance/shim\_client\_key' was removed.

- Property 'appliance/shim\_enabled' was removed.
- Property 'appliance/shim\_ips' was removed.
- Property 'appliance/shim\_load\_balance' was removed.
- Property 'appliance/shim\_log\_level' was removed.
- Property 'appliance/shim\_mode' was removed.
- Property 'appliance/shim\_portal\_url' was removed.
- Property 'appliance/shim\_proxy\_host' was removed.
- Property 'appliance/shim\_proxy\_port' was removed.

The following properties in 'Virtual Server' (/api/tm/5.0/config/active/virtual\_servers) have been removed:

- Property 'ssl/prefer\_sslv3' was removed.
- Property 'ssl/ssl\_support\_ssl2' was removed.

The following properties in 'Global Settings' (/api/tm/5.0/config/active/global\_settings) have been removed:

- Property 'admin/support\_ssl2' was removed.
- Property 'appliance/manage\_ncipher' was removed.
- Property 'appliance/nethsm\_esn' was removed.
- Property 'appliance/nethsm\_hash' was removed.
- Property 'appliance/nethsm\_ip' was removed.
- Property 'appliance/nethsm\_ncipher\_rfs' was removed.
- Property 'ssl/support\_ssl2' was removed.
- Property 'trafficscript/array\_elements' was removed.

The following properties in 'Globals' (/api/tm/5.0/status/local\_tm/statistics/globals) have been removed:

Property 'statistics/ssl\_handshake\_t\_l\_sv1' was removed.

- Property 'statistics/ssl\_handshake\_t\_l\_sv11' was removed.
- Property 'statistics/ssl\_handshake\_t\_l\_sv12' was removed.

The following properties in 'Alerting Action' (/api/tm/5.0/config/active/actions) have been renamed:

• Property 'log/from' was renamed to 'email/from'.

The following properties in 'Protection Class' (/api/tm/5.0/config/active/protection) have been renamed:

- Property 'basic/per\_process\_connection\_count' was renamed to 'concurrent\_connections/per\_ process\_connection\_count'.
- Property 'connection\_limiting/max\_10\_connections' was renamed to 'concurrent\_ connections/max\_10\_connections'.
- Property 'connection\_limiting/max\_1\_connections' was renamed to 'concurrent\_ connections/max\_1\_connections'.
- Property 'connection\_limiting/max\_connection\_rate' was renamed to 'connection\_rate/max\_ connection\_rate'.
- Property 'connection\_limiting/min\_connections' was renamed to 'concurrent\_connections/min\_ connections'.
- Property 'connection\_limiting/rate\_timer' was renamed to 'connection\_rate/rate\_timer'.

The following properties in 'Virtual Server' (/api/tm/5.0/config/active/virtual\_servers) have been renamed:

- Property 'basic/add\_cluster\_ip' was renamed to 'http/add\_cluster\_ip'.
- Property 'basic/add\_x\_forwarded\_for' was renamed to 'http/add\_x\_forwarded\_for'.
- Property 'basic/add\_x\_forwarded\_proto' was renamed to 'http/add\_x\_forwarded\_proto'.
- Property 'basic/auto\_upgrade\_protocols' was renamed to 'http/auto\_upgrade\_protocols'.
- Property 'basic/autodetect\_upgrade\_headers' was renamed to 'http/autodetect\_upgrade\_headers'.
- Property 'basic/close\_with\_rst' was renamed to 'tcp/close\_with\_rst'.
- Property 'basic/completionrules' was renamed to 'basic/completion\_rules'.

- Property 'basic/ftp\_force\_server\_secure' was renamed to 'ftp/force\_server\_secure'.
- Property 'basic/mss' was renamed to 'tcp/mss'.
- Property 'basic/so\_nagle' was renamed to 'tcp/nagle'.
- Property 'basic/ssl\_client\_cert\_headers' was renamed to 'ssl/client\_cert\_headers'.
- Property 'basic/ssl\_honor\_fallback\_scsv' was renamed to 'ssl/honor\_fallback\_scsv'.
- Property 'basic/strip\_x\_forwarded\_proto' was renamed to 'http/strip\_x\_forwarded\_proto'.
- Property 'basic/udp\_end\_transaction' was renamed to 'udp/udp\_end\_transaction'.
- Property 'ssl/ssl\_ciphers' was renamed to 'ssl/cipher\_suites'.
- Property 'ssl/ssl\_support\_ssl3' was renamed to 'ssl/support\_ssl3'.
- Property 'ssl/ssl\_support\_tls1' was renamed to 'ssl/support\_tls1'.
- Property 'ssl/ssl\_support\_tls1\_1' was renamed to 'ssl/support\_tls1\_1'.
- Property 'ssl/ssl\_support\_tls1\_2' was renamed to 'ssl/support\_tls1\_2'.

The following properties in 'Global Settings' (/api/tm/5.0/config/active/global\_settings) have been renamed:

- Property 'admin/support\_tls11' was renamed to 'admin/support\_tls1\_1'.
- Property 'admin/support\_tls12' was renamed to 'admin/support\_tls1\_2'.
- Property 'ospfv2/router\_dead\_interval' was renamed to 'ospfv2/dead\_interval'.
- Property 'ssl/ssl3\_allow\_rehandshake' was renamed to 'ssl/allow\_rehandshake'.
- Property 'ssl/ssl3\_ciphers' was renamed to 'ssl/cipher\_suites'.
- Property 'ssl/ssl3\_diffie\_hellman\_client\_min\_key\_length' was renamed to 'ssl/diffie\_hellman\_client\_min\_modulus\_size'.
- Property 'ssl/ssl3\_diffie\_hellman\_key\_length' was renamed to 'ssl/diffie\_hellman\_modulus\_size'.
- Property 'ssl/ssl3\_min\_rehandshake\_interval' was renamed to 'ssl/min\_rehandshake\_interval'.

The following properties in 'Pool' (/api/tm/5.0/config/active/pools) have been renamed:

• Property 'ssl/ssl\_ciphers' was renamed to 'ssl/cipher\_suites'.

- Property 'ssl/ssl\_support\_ssl3' was renamed to 'ssl/support\_ssl3'.
- Property 'ssl/ssl\_support\_tls1' was renamed to 'ssl/support\_tls1'.
- Property 'ssl/ssl\_support\_tls1\_1' was renamed to 'ssl/support\_tls1\_1'.
- Property 'ssl/ssl\_support\_tls1\_2' was renamed to 'ssl/support\_tls1\_2'.

The following properties for 'Global Settings' (/api/tm/5.0/config/active/global\_settings) have had flags change:

 Property 'ssl/min\_rehandshake\_interval' has had the following flags removed: [LOCATION\_ IGNORE]

## **Changes in Version 4.0**

The following resources were added:

Resource 'Log Export' (/api/tm/4.0/config/active/log\_export)

The following properties in 'Global Settings' (/api/tm/4.0/config/active/global\_settings) have been added:

- Property 'log\_export/auth\_hec\_token' was added.
- Property 'log\_export/auth\_http' was added.
- Property 'log\_export/auth\_password' was added.
- Property 'log\_export/auth\_username' was added.
- Property 'log\_export/enabled' was added.
- Property 'log\_export/endpoint' was added.
- Property 'log\_export/max\_event\_message\_size' was added.
- Property 'log\_export/max\_request\_bandwidth' was added.
- Property 'log\_export/max\_request\_size' was added.
- Property 'log\_export/max\_response\_size' was added.
- Property 'log\_export/maximum\_error\_raising\_period' was added.
- Property 'log\_export/minimum\_error\_raising\_period' was added.

- Property 'log\_export/request\_timeout' was added.
- Property 'log\_export/tls\_verify' was added.
- Property 'transaction\_export/auto\_brief' was added.
- Property 'transaction\_export/enabled' was added.
- Property 'transaction\_export/endpoint' was added.
- Property 'transaction\_export/failure\_interval' was added.
- Property 'transaction\_export/memory' was added.
- Property 'transaction\_export/reconnect\_interval' was added.
- Property 'transaction\_export/tls' was added.
- Property 'transaction\_export/tls\_timeout' was added.
- Property 'transaction\_export/tls\_verify' was added.

The following properties in 'Bandwidth' (/api/tm/4.0/status/local\_tm/statistics/bandwidth/\*) have been added:

- Property 'statistics/bytes\_drop' was added.
- Property 'statistics/bytes\_drop\_hi' was added.
- Property 'statistics/bytes\_drop\_lo' was added.
- Property 'statistics/pkts\_drop' was added.
- Property 'statistics/pkts\_drop\_hi' was added.
- Property 'statistics/pkts\_drop\_lo' was added.

The following properties in 'Virtual servers' (/api/tm/4.0/status/local\_tm/statistics/virtual\_servers/\*) have been added:

- Property 'statistics/bw\_limit\_bytes\_drop' was added.
- Property 'statistics/bw\_limit\_bytes\_drop\_hi' was added.
- Property 'statistics/bw\_limit\_bytes\_drop\_lo' was added.
- Property 'statistics/bw\_limit\_pkts\_drop' was added.

- Property 'statistics/bw\_limit\_pkts\_drop\_hi' was added.
- Property 'statistics/bw\_limit\_pkts\_drop\_lo' was added.
- Property 'statistics/pkts\_in' was added.
- Property 'statistics/pkts\_in\_hi' was added.
- Property 'statistics/pkts\_in\_lo' was added.
- Property 'statistics/pkts\_out' was added.
- Property 'statistics/pkts\_out\_hi' was added.
- Property 'statistics/pkts\_out\_lo' was added.

The following properties in 'Pools' (/api/tm/4.0/status/local\_tm/statistics/pools/\*) have been added:

- Property 'statistics/bw\_limit\_bytes\_drop' was added.
- Property 'statistics/bw\_limit\_bytes\_drop\_hi' was added.
- Property 'statistics/bw\_limit\_bytes\_drop\_lo' was added.
- Property 'statistics/bw\_limit\_pkts\_drop' was added.
- Property 'statistics/bw\_limit\_pkts\_drop\_hi' was added.
- Property 'statistics/bw\_limit\_pkts\_drop\_lo' was added.

The following properties in 'Per pool node' (/api/tm/4.0/status/local\_tm/statistics/nodes/per\_pool\_node/\*) have been added:

- Property 'statistics/l4\_stateless\_buckets' was added.
- Property 'statistics/pkts\_from\_node' was added.
- Property 'statistics/pkts\_from\_node\_hi' was added.
- Property 'statistics/pkts\_from\_node\_lo' was added.
- Property 'statistics/pkts\_to\_node' was added.
- Property 'statistics/pkts\_to\_node\_hi' was added.
- Property 'statistics/pkts\_to\_node\_lo' was added.

The following properties in 'Globals' (/api/tm/4.0/status/local\_tm/statistics/globals) have been added:

- Property 'statistics/analytics\_transactions\_dropped' was added.
- Property 'statistics/analytics\_transactions\_exported' was added.
- Property 'statistics/analytics\_transactions\_memory\_usage' was added.

The following properties in 'Virtual Server' (/api/tm/4.0/config/active/virtual\_servers) have been added:

- Property 'basic/strip\_x\_forwarded\_proto' was added.
- Property 'transaction\_export/brief' was added.
- Property 'transaction\_export/enabled' was added.
- Property 'transaction\_export/hi\_res' was added.
- Property 'transaction\_export/http\_header\_blacklist' was added.

# **Changes in Version 3.11**

The following properties in 'Global Settings' (/api/tm/3.11/config/active/global\_settings) have been added:

- Property 'fault\_tolerance/autofailback\_delay' was added.
- Property 'rest\_api/block\_for\_future\_max' was added.
- Property 'rest\_api/http\_compress\_min' was added.
- Property 'rest\_api/http\_keep\_alive\_timeout' was added.
- Property 'rest\_api/http\_max\_resource\_body\_length' was added.
- Property 'rest\_api/http\_max\_write\_buffer' was added.
- Property 'rest\_api/http\_session\_timeout' was added.

The following properties in 'Virtual Server' (/api/tm/3.11/config/active/virtual\_servers) have been added:

- Property 'basic/proxy\_protocol' was added.
- Property 'ssl/issued\_certs\_never\_expire\_depth' was added.

The following properties in 'State' (/api/tm/3.11/status/local\_tm/state) have been added:

Property 'state/pools' was added.

• Table property 'state/virtual\_servers' field 'ts\_redirect\_pools' was added.

The following properties in 'Traffic Manager' (/api/tm/3.11/config/active/traffic\_managers) have been added:

- Property 'fault\_tolerance/lss\_dedicated\_ips' was added.
- Table property 'appliance/if' field 'mode' was added.

The type of the following properties in 'State' (/api/tm/3.11/status/local\_tm/state) has changed:

• Table property 'state/virtual\_servers' field 'throughput' changed type from 'Unsigned integer' to 'Unsigned integer 64'.

The following properties for 'Global Settings' (/api/tm/3.11/config/active/global\_settings) have had flags change:

- Property 'data\_plane\_acceleration/tcp\_delay\_ack' has had the following flags added:
   [ RESTART\_SOFTWARE ]
- Property 'data\_plane\_acceleration/tcp\_win\_scale' has had the following flags added:
   [ RESTART\_SOFTWARE ]

#### **Changes in Version 3.10**

The following properties in 'Monitor' (/api/tm/3.10/config/active/monitors) have been added:

- Property 'basic/factory' was added.
- Property 'basic/health\_only' was added.

The following properties in 'Traffic Manager' (/api/tm/3.10/config/active/traffic\_managers) have been added:

• Property 'basic/developer\_mode\_accepted' was added.

The following properties in 'Virtual Server' (/api/tm/3.10/config/active/virtual\_servers) have been added:

- Property 'basic/max\_concurrent\_connections' was added.
- Property 'basic/rules\_on\_connect' was added.
- Property 'basic/udp\_end\_transaction' was added.

- Property 'gzip/chunk' was added.
- Property 'http2/headers\_size\_limit' was added.
- Property 'l4accel/service\_ip\_snat' was added.
- Property 'l4stateless/initial\_ring\_size' was added.
- Property 'l4stateless/num\_replicas' was added.

The following properties in 'Protection Class' (/api/tm/3.10/config/active/protection) have been added:

Property 'basic/linger\_time' was added.

The following properties in 'Global Settings' (/api/tm/3.10/config/active/global\_settings) have been added:

- Property 'data\_plane\_acceleration/tcp\_delay\_ack' was added.
- Property 'data\_plane\_acceleration/tcp\_win\_scale' was added.
- Property 'ec2/awstool\_timeout' was added.
- Property 'ec2/metadata\_timeout' was added.
- Property 'l4accel/max\_concurrent\_connections' was added.
- Property 'remote\_licensing/owner' was added.
- Property 'remote\_licensing/owner\_secret' was added.
- Property 'remote\_licensing/policy\_id' was added.

# **Changes in Version 3.9**

The following resources were added:

Resource 'Backups' (/api/tm/3.9/status/local\_tm/backups/full/\*)

The following properties in 'Virtual Server' (/api/tm/3.9/config/active/virtual\_servers) have been added:

- Property 'basic/bypass\_data\_plane\_acceleration' was added.
- Property 'l4accel/rst\_on\_service\_failure' was added.
- Property 'l4accel/state\_sync' was added.

- Property 'l4accel/tcp\_msl' was added.
- Property 'l4accel/timeout' was added.
- Property 'l4accel/udp\_count\_requests' was added.
- Property 'ssl/max\_key\_size' was added.
- Property 'ssl/min\_key\_size' was added.

The following properties in 'Traffic Manager' (/api/tm/3.9/config/active/traffic\_managers) have been added:

- Property 'appliance/managedpa' was added.
- Property 'basic/num\_l4\_children' was added.
- Property 'basic/num\_I7\_children' was added.
- Property 'iop/is\_standalone' was added.
- Property 'iop/l4\_event\_driven\_mode' was added.
- Property 'iop/I7\_event\_driven\_mode' was added.
- Property 'iop/linux\_interface' was added.
- Property 'iop/num\_mbufs\_per\_mpool' was added.
- Property 'iop/send\_to\_linux' was added.

The following properties in 'Traffic IP Group' (/api/tm/3.9/config/active/traffic\_ip\_groups) have been added:

Property 'basic/snat\_ipaddresses' was added.

The following properties in 'Pool' (/api/tm/3.9/config/active/pools) have been added:

• Property 'l4accel/snat' was added.

The following properties in 'Global Settings' (/api/tm/3.9/config/active/global\_settings) have been added:

- Property 'basic/data\_plane\_acceleration\_cores' was added.
- Property 'basic/data\_plane\_acceleration\_mode' was added.

- Property 'fault\_tolerance/l4accel\_child\_timeout' was added.
- Property 'fault\_tolerance/l4accel\_sync\_port' was added.
- Property 'source\_nat/clist\_locks' was added.
- Property 'source\_nat/ip\_limit' was added.
- Property 'source\_nat/ip\_local\_port\_range\_high' was added.
- Property 'source\_nat/portmaphashtable\_locks' was added.
- Property 'source\_nat/shared\_pool\_size' was added.

The following properties in 'Virtual servers' (/api/tm/3.9/status/local\_tm/statistics/virtual\_servers/\*) have been added:

- Property 'statistics/total\_tcp\_reset' was added.
- Property 'statistics/total\_udp\_unreachables' was added.

The following properties in 'Session Persistence Class' (/api/tm/3.9/config/active/persistence) have been added:

- Property 'basic/subnet\_mask\_len\_v4' was added.
- Property 'basic/subnet\_mask\_len\_v6' was added.

The following properties for 'Pool' (/api/tm/3.9/config/active/pools) have had flags change:

• Property 'ssl/ssl\_support\_ssl2' has had the following flags added: [ SOAP\_IGNORE ]

The following properties for 'Global Settings' (/api/tm/3.9/config/active/global\_settings) have had flags change:

- Property 'admin/support\_ssl2' has had the following flags added: [SOAP\_IGNORE]
- Property 'ssl/support\_ssl2' has had the following flags added: [ SOAP\_IGNORE ]

The following properties for 'Virtual Server' (/api/tm/3.9/config/active/virtual\_servers) have had flags change:

Property 'ssl/ssl\_support\_ssl2' has had the following flags added: [SOAP\_IGNORE]

## **Changes in Version 3.8**

The following properties in 'Virtual Server' (/api/tm/3.8/config/active/virtual\_servers) have been added:

- Property 'log/always\_flush' was added.
- Property 'ssl/server\_cert\_alt\_certificates' was added.
- Table property 'ssl/server\_cert\_host\_mapping' field 'alt\_certificates' was added.

The following properties in 'Pool' (/api/tm/3.8/config/active/pools) have been added:

- Property 'basic/lard\_size' was added.
- Property 'udp/response\_timeout' was added.

The following properties in 'Event Type' (/api/tm/3.8/config/active/event\_types) have been added:

Property 'basic/log2mainlog' was added.

The following properties in 'Traffic Manager' (/api/tm/3.8/config/active/traffic\_managers) have been added:

- Property 'basic/use\_mx' was added.
- Property 'remote\_licensing/email\_address' was added.
- Property 'remote\_licensing/message' was added.

The following properties in 'Globals' (/api/tm/3.8/status/local\_tm/statistics/globals) have been added:

- Property 'statistics/ssl\_cipher\_ecdsa\_signs' was added.
- Property 'statistics/ssl\_cipher\_ecdsa\_verifies' was added.

The following properties in 'Global Settings' (/api/tm/3.8/config/active/global\_settings) have been added:

- Property 'dns/checktime' was added.
- Property 'dns/hosts' was added.
- Property 'dns/hostsfirst' was added.
- Property 'dns/maxasynctries' was added.
- Property 'dns/resolv' was added.

- Property 'fault\_tolerance/child\_timeout' was added.
- Property 'http/max\_chunk\_header\_length' was added.
- Property 'remote\_licensing/registration\_server' was added.
- Property 'remote\_licensing/script\_timeout' was added.
- Property 'remote\_licensing/server\_certificate' was added.
- Property 'ssl\_hardware/nworkers' was added.
- Property 'ssl\_hardware/queuelen' was added.
- Property 'web\_cache/blocksize' was added.
- Property 'web\_cache/max\_byte\_range\_segments' was added.
- Property 'web\_cache/min\_size\_accept\_range' was added.

#### **Changes in Version 3.7**

The following resources were added:

• Resource 'State' (/api/tm/3.7/status/local\_tm/state)

The following properties in 'Virtual Server' (/api/tm/3.7/config/active/virtual\_servers) have been added:

Property 'basic/mss' was added.

The following properties in 'Traffic IP Group' (/api/tm/3.7/config/active/traffic\_ip\_groups) have been added:

Property 'basic/ip\_assignment\_mode' was added.

The following properties in 'Traffic Manager' (/api/tm/3.7/config/active/traffic\_managers) have been added:

- Property 'appliance/ipmi\_lan\_access' was added.
- Property 'appliance/ipmi\_lan\_addr' was added.
- Property 'appliance/ipmi\_lan\_gateway' was added.
- Property 'appliance/ipmi\_lan\_ipsrc' was added.
- Property 'appliance/ipmi\_lan\_mask' was added.

Property 'basic/appliance\_card' was added.

## **Changes in Version 3.6**

The following properties in 'Traffic Manager' (/api/tm/3.6/config/active/traffic\_managers) have been added:

- Property 'appliance/ipv6\_forwarding' was added.
- Property 'appliance/ssh\_password\_allowed' was added.

The following properties in 'Virtual Server' (/api/tm/3.6/config/active/virtual\_servers) have been added:

- Property 'dns/edns\_client\_subnet' was added.
- Property 'http2/connect\_timeout' was added.
- Property 'http2/data\_frame\_size' was added.
- Property 'http2/enabled' was added.
- Property 'http2/header\_table\_size' was added.
- Property 'http2/idle\_timeout\_no\_streams' was added.
- Property 'http2/idle\_timeout\_open\_streams' was added.
- Property 'http2/max\_concurrent\_streams' was added.
- Property 'http2/max\_frame\_size' was added.
- Property 'http2/max\_header\_padding' was added.
- Property 'http2/neverindex\_blacklist' was added.
- Property 'http2/neverindex\_default' was added.
- Property 'http2/neverindex\_whitelist' was added.
- Property 'http2/stream\_window\_size' was added.

The following properties in 'Global Settings' (/api/tm/3.6/config/active/global\_settings) have been added:

- Property 'auditlog/via\_eventd' was added.
- Property 'basic/cluster\_identifier' was added.

- Property 'basic/http2\_no\_cipher\_blacklist\_check' was added.
- Property 'web\_cache/max\_handles' was added.

## **Changes in Version 3.5**

The following resources were added:

Resource 'BGP Neighbor' (/api/tm/3.5/config/active/bgpneighbors)

The following properties in 'Virtual Server' (/api/tm/3.5/config/active/virtual\_servers) have been added:

- Property 'basic/auto\_upgrade\_protocols' was added.
- Property 'basic/autodetect\_upgrade\_headers' was added.
- Property 'basic/transparent' was added.

The following properties in 'Traffic Manager' (/api/tm/3.5/config/active/traffic\_managers) have been added:

- Property 'fault\_tolerance/bgp\_router\_id' was added.
- Property 'iptables/config\_enabled' was added.
- Property 'iptrans/chain' was added.
- Property 'iptrans/fwmark' was added.
- Property 'iptrans/iptables\_enabled' was added.
- Property 'iptrans/routing\_table' was added.

The following properties in 'Information' (/api/tm/3.5/status/local\_tm/information) have been added:

Property 'information/uuid' was added.

The following properties in 'Pool' (/api/tm/3.5/config/active/pools) have been added:

- Property 'basic/node\_delete\_behavior' was added.
- Property 'basic/node\_drain\_to\_delete\_timeout' was added.

The following properties in 'Monitor' (/api/tm/3.5/config/active/monitors) have been added:

• Property 'basic/can\_edit\_ssl' was added.

- Property 'basic/can\_use\_ssl' was added.
- Property 'basic/editable\_keys' was added.

The following properties in 'Traffic IP Group' (/api/tm/3.5/config/active/traffic\_ip\_groups) have been added:

- Property 'basic/rhi\_bgp\_metric\_base' was added.
- Property 'basic/rhi\_bgp\_passive\_metric\_offset' was added.
- Property 'basic/rhi\_protocols' was added.

The following properties in 'Global Settings' (/api/tm/3.5/config/active/global\_settings) have been added:

- Property 'basic/license\_servers' was added.
- Property 'bgp/as\_number' was added.
- Property 'bgp/enabled' was added.
- Property 'ssl/ssl3\_diffie\_hellman\_client\_min\_key\_length' was added.

The following properties in 'Security Settings' (/api/tm/3.5/config/active/security) have been added:

- Property 'ssh\_intrusion/bantime' was added.
- Property 'ssh\_intrusion/blacklist' was added.
- Property 'ssh\_intrusion/enabled' was added.
- Property 'ssh\_intrusion/findtime' was added.
- Property 'ssh\_intrusion/maxretry' was added.
- Property 'ssh\_intrusion/whitelist' was added.

The following properties for 'Virtual Server' (/api/tm/3.5/config/active/virtual\_servers) have had flags change:

Property 'basic/glb\_services' has had the following flags removed: [SOAP\_IGNORE]

## **Changes in Version 3.4**

The following properties in 'Web cache' (/api/tm/3.4/status/local\_tm/statistics/cache/web\_cache) have been added:

- Property 'statistics/url\_store\_allocated' was added.
- Property 'statistics/url\_store\_free' was added.
- Property 'statistics/url\_store\_size' was added.
- Property 'statistics/url\_store\_total\_allocations' was added.
- Property 'statistics/url\_store\_total\_failures' was added.
- Property 'statistics/url\_store\_total\_frees' was added.

The following properties in 'Pool' (/api/tm/3.4/config/active/pools) have been added:

- Property 'auto\_scaling/addnode\_delaytime' was added.
- Property 'ssl/common\_name\_match' was added.
- Property 'ssl/elliptic\_curves' was added.

The following properties in 'GLB Service' (/api/tm/3.4/config/active/glb\_services) have been added:

• Property 'basic/peer\_health\_timeout' was added.

The following properties in 'Virtual Server' (/api/tm/3.4/config/active/virtual\_servers) have been added:

- Property 'dns/rrset\_order' was added.
- Property 'gzip/etag\_rewrite' was added.
- Property 'ssl/elliptic\_curves' was added.

The following properties in 'Globals' (/api/tm/3.4/status/local\_tm/statistics/globals) have been added:

- Property 'statistics/ssl\_cipher\_ecdh\_agreements' was added.
- Property 'statistics/ssl\_cipher\_ecdh\_generates' was added.

The following properties in 'Global Settings' (/api/tm/3.4/config/active/global\_settings) have been added:

Property 'admin/ssl\_elliptic\_curves' was added.

- Property 'auditlog/via\_syslog' was added.
- Property 'ssl/elliptic\_curves' was added.
- Property 'ssl\_hardware/azure\_api\_version' was added.
- Property 'ssl\_hardware/azure\_client\_id' was added.
- Property 'ssl\_hardware/azure\_client\_secret' was added.
- Property 'ssl\_hardware/azure\_connect\_timeout' was added.
- Property 'ssl\_hardware/azure\_idle\_timeout' was added.
- Property 'ssl\_hardware/azure\_vault\_url' was added.
- Property 'ssl\_hardware/azure\_verify\_rest\_api\_cert' was added.
- Property 'web\_cache/url\_store\_keep\_free' was added.
- Property 'web\_cache/url\_store\_max\_mallocs' was added.
- Property 'web\_cache/url\_store\_num\_bins' was added.

The following properties in 'Traffic Manager' (/api/tm/3.4/config/active/traffic\_managers) have been added:

• Property 'appliance/manageazureroutes' was added.

#### **Changes in Version 3.3**

The following resources were added:

- Resource 'DNS Zone File' (/api/tm/3.3/config/active/dns\_server/zone\_files)
- Resource 'DNS Zone' (/api/tm/3.3/config/active/dns\_server/zones)

The following properties in 'Global Settings' (/api/tm/3.3/config/active/global\_settings) have been added:

- Property 'admin/honor\_fallback\_scsv' was added.
- Property 'ssl/honor\_fallback\_scsv' was added.

The following properties in 'Globals' (/api/tm/3.3/status/local\_tm/statistics/globals) have been added:

Property 'statistics/ssl\_cipher\_aes\_gcm\_decrypts' was added.

Property 'statistics/ssl\_cipher\_aes\_gcm\_encrypts' was added.

The following properties in 'Traffic Manager' (/api/tm/3.3/config/active/traffic\_managers) have been added:

- Property 'autodiscover/product\_id' was added.
- Property 'basic/kmod\_policy' was added.
- Property 'basic/start\_sysd' was added.

The following properties in 'Virtual Server' (/api/tm/3.3/config/active/virtual\_servers) have been added:

- Property 'basic/ssl\_honor\_fallback\_scsv' was added.
- Property 'dns/verbose' was added.
- Property 'dns/zones' was added.

The following properties in 'GLB Service' (/api/tm/3.3/config/active/glb\_services) have been added:

- Property 'basic/autorecovery' was added.
- Property 'basic/disable\_on\_failure' was added.
- Property 'basic/last\_resort\_response' was added.

The following properties for 'Virtual Server' (/api/tm/3.3/config/active/virtual\_servers) have had flags change:

- Property 'dns/edns\_udpsize' has had the following flags removed: [ SOAP\_IGNORE ]
- Property 'dns/max\_udpsize' has had the following flags removed: [SOAP\_IGNORE]
- Property 'ssl/prefer\_sslv3' has had the following flags added: [SOAP\_IGNORE]

#### **Changes in Version 3.2**

The following properties in "Pool" (/api/tm/3.2/config/active/pools) have been added:

- "Property "ssl/signature\_algorithms" was added.
- "Property "ssl/ssl\_support\_tls1\_2" was added.

The following properties in "Virtual servers" (/api/tm/3.2/status/local\_tm/statistics/virtual\_servers/\*) have been added:

- "Property "statistics/max\_duration\_timed\_out" was added.
- "Property "statistics/processing\_timed\_out" was added.

The following properties in "Globals" (/api/tm/3.2/status/local\_tm/statistics/globals) have been added:

- "Property "statistics/ssl\_cipher\_dh\_agreements" was added.
- "Property "statistics/ssl\_cipher\_dh\_generates" was added.
- "Property "statistics/ssl\_cipher\_dsa\_signs" was added.
- "Property "statistics/ssl\_cipher\_dsa\_verifies" was added.
- "Property "statistics/ssl\_handshake\_t\_l\_sv12" was added.

The following properties in "Traffic Manager" (/api/tm/3.2/config/active/traffic\_managers) have been added:

- "Property "basic/adminMasterXMLIP" was added.
- "Property "basic/adminSlaveXMLIP" was added.
- "Property "basic/authenticationServerIP" was added.
- "Property "basic/updaterIP" was added.
- "Property "ec2/trafficips\_public\_enis" was added.

The following properties in "Global Settings" (/api/tm/3.2/config/active/global\_settings) have been added:

- "Property "admin/ssl\_signature\_algorithms" was added.
- "Property "admin/support\_tls12" was added.
- "Property "aptimizer/max\_concurrent\_jobs" was added.
- "Property "ec2/action\_timeout" was added.
- "Property "ssl/signature\_algorithms" was added.
- "Property "ssl/support\_tls1\_2" was added.

The following properties in "Virtual Server" (/api/tm/3.2/config/active/virtual\_servers) have been added:

"Property "dns/edns\_udpsize" was added.

- "Property "dns/max\_udpsize" was added.
- "Property "ssl/signature\_algorithms" was added.
- "Property "ssl/ssl\_support\_tls1\_2" was added.

The following properties in "Rules" (/api/tm/3.2/status/local\_tm/statistics/rules/\*) have been added:

"Property "statistics/execution\_time\_warnings" was added.

## **Changes in Version 3.1**

The following resources were added:

- Resource "User counters 32" (/api/tm/3.1/status/local\_tm/statistics/extras/user\_counters\_32)
- Resource "User counters 64" (/api/tm/3.1/status/local\_tm/statistics/extras/user\_counters\_64)

The following properties in "Global Settings" (/api/tm/3.1/config/active/global\_settings) have been added:

- Property "ec2/verify\_query\_server\_cert" was added.
- Property "fault\_tolerance/igmp\_interval" was added.
- Property "ssl/cache\_per\_virtualserver" was added.
- Property "ssl/ocsp\_max\_response\_size" was added.
- Property "trafficscript/execution\_time\_warning" was added.

The following properties in "Virtual Server" (/api/tm/3.1/config/active/virtual\_servers) have been added:

- Property "basic/close\_with\_rst" was added.
- Property "log/session\_persistence\_verbose" was added.

The following properties in "Pool" (/api/tm/3.1/config/active/pools) have been added:

Property "basic/node\_close\_with\_rst" was added.

The following properties in "Traffic Manager" (/api/tm/3.1/config/active/traffic\_managers) have been added:

- Property "basic/cloud\_platform" was added.
- Property "basic/disk\_serious" was added.

Property "basic/disk\_warn" was added

#### **Changes in Version 3.0**



The Traffic Manager REST representation of pool nodes has changed for this release. All nodes and related properties are now contained within a single table (nodes\_table). For more information, see the Pool configuration resource in the "Resource Model Reference" chapter of the *REST API Guide* for Stingray Traffic Manager release 9.6.

The following resources were added:

Resource 'NAT Configuration' (/api/tm/3.0/config/active/appliance/nat)

The following properties in 'Global Settings' (/api/tm/3.0/config/active/global\_settings) have been added:

- Property 'autoscaler/slm\_interval' was added.
- Property 'autoscaler/verbose' was added.
- Property 'fault\_tolerance/tipv6\_raise\_deprecated' was added.
- Property 'ssl/disable\_stitched\_cbc\_hmac' was added.
- Property 'ssl/ocsp\_stapling\_maximum\_refresh\_interval' was added.
- Property 'ssl/ocsp\_stapling\_time\_tolerance' was added.
- Property 'ssl/ocsp\_stapling\_verify\_response' was added.

The following properties in 'Pool' (/api/tm/3.0/config/active/pools) have been added:

- Property 'auto\_scaling/extraargs' was added.
- Property 'auto\_scaling/securitygroupids' was added.
- Property 'auto\_scaling/subnetids' was added.
- Property 'basic/nodes\_table' was added.
- Property 'ssl/ssl\_ciphers' was added.
- Property 'ssl/ssl\_support\_ssl2' was added.
- Property 'ssl/ssl\_support\_ssl3' was added.

- Property 'ssl/ssl\_support\_tls1' was added.
- Property 'ssl/ssl\_support\_tls1\_1' was added.

The following properties in 'Traffic Manager' (/api/tm/3.0/config/active/traffic\_managers) have been added:

• Property 'appliance/ipv4\_forwarding' was added.

The following properties in 'Virtual Server' (/api/tm/3.0/config/active/virtual\_servers) have been added:

- Property 'basic/completionrules' was added.
- Property 'connection/max\_transaction\_duration' was added.
- Property 'log/save\_all' was added.
- Property 'recent\_connections/enabled' was added.
- Property 'recent\_connections/save\_all' was added.
- Property 'ssl/ssl\_ciphers' was added.
- Property 'ssl/ssl\_support\_ssl2' was added.
- Property 'ssl/ssl\_support\_ssl3' was added.
- Property 'ssl/ssl\_support\_tls1' was added.
- Property 'ssl/ssl\_support\_tls1\_1' was added.

The following properties in 'Pool' (/api/tm/3.0/config/active/pools) have been removed:

- Property 'basic/disabled' was removed.
- Property 'basic/draining' was removed.
- Property 'basic/nodes' was removed.
- Property 'load\_balancing/node\_weighting' was removed.
- Property 'load\_balancing/priority\_values' was removed.