



MobileIron Monitor and RDB 2.0.0.1 Release Notes

August 7, 2019

Revised: October 16, 2019

For complete product documentation, see:
[MobileIron Monitor Product Documentation](#)

Copyright © 2009 - 2019 MobileIron, Inc. All Rights Reserved.

Any reproduction or redistribution of part or all of these materials is strictly prohibited. Information in this publication is subject to change without notice. MobileIron, Inc. does not warrant the use of this publication. For some phone images, a third-party database and image library, Copyright © 2007-2009 Aeleeeta's Art and Design Studio, is used. This database and image library cannot be distributed separate from the MobileIron product.

“MobileIron,” the MobileIron logos and other trade names, trademarks or service marks of MobileIron, Inc. appearing in this documentation are the property of MobileIron, Inc. This documentation contains additional trade names, trademarks and service marks of others, which are the property of their respective owners. We do not intend our use or display of other companies' trade names, trademarks or service marks to imply a relationship with, or endorsement or sponsorship of us by, these other companies.



Contents

- About MobileIron Monitor** 1
 - About these release notes 1
- Revision History** 1
- Resolved issues** 1
- Upgrade information for RDB** 1
 - Obtaining the release 2
 - Upgrading from supported versions to 2.0.0.1 2



About MobileIron Monitor

MobileIron Monitor organizes and displays monitoring data pushed from your MobileIron Sentry and Core instances, affording you a comprehensive view of the system status and alerts associated with those MobileIron Sentry and Core instances.

About these release notes

These release notes contain resolved and known issues, limitations, and upgrade information particular to this patch release. For new feature and other information about the major release, please see the [release notes for that release](#).

Revision History

Date	Description
October 16, 2019	Added the section Obtaining the release which contains a link to an article that has download links for the product.

Resolved issues

This section describes the following resolved issues fixed in the current release of MobileIron Monitor. For resolved issues found in previous releases, see the "Resolved issues" sections in the release notes for those releases, available in [MobileIron Monitor Product Documentation](#).

- **CMC-1562:** To enable mitigation of SACK Panic vulnerabilities in MobileIron Monitor and RDB, MobileIron has upgraded the RDB CentOS from 6.9 to 6.10.
- **CMC-1561:** MobileIron has released a patch to mitigate SACK Panic vulnerabilities in MobileIron Monitor and RDB. See Security Bulletin: SACK Panic (<https://help.mobileiron.com/s/article-detail-page?Id=kA12T000000fyuHSAQ>) for details.
- **CMC-1560:** This release corrects an ElastAlert rule that now correctly queries Logstash indexes, allowing alerts to be configured for MobileIron Core and Sentry.

Upgrade information for RDB

The [release notes for the major release](#) offer supplementary upgrade information, such as calculating disk space.



Supported upgrade paths:

- 1.9.1.0 → 2.0.0.1
- 1.9.1.0 → 2.0.0.0 → 2.0.0.1
- 2.0.0.0 → 2.0.0.1

NOTE: To upgrade from the supported versions above, follow the steps in [Upgrading from supported versions to 2.0.0.1](#)

Compatible upgrade paths:

- 1.8.0.0 → 2.0.0.0 → 2.0.0.1
- 1.8.0.0 → 1.9.1.0 → 2.0.0.0 → 2.0.0.1
- 1.8.0.0 → 2.0.0.1

Obtaining the release

See the section, "GET ACCESS TO THE NEW RELEASE" in the following article for information on obtaining the software: <https://help.mobileiron.com/s/article-detail-page?id=kA12T000000TOLQSA4>.

Upgrading from supported versions to 2.0.0.1

You cannot use the MobileIron System Manager user interface to perform the upgrade from the [supported](#) versions of MobileIron Monitor to version 2.0.0.1. You must use CLISH commands to upgrade from the [supported](#) versions of MobileIron Monitor to version 2.0.0.1. See the [MobileIron Core Command Line Interface \(CLI\) Reference Guide](#) for complete CLISH command information.

To upgrade from the supported versions of MobileIron Monitor to version 2.0.0.1:

1. Login into CLI.
2. Select **enable** → **enter password**.
3. Run the configure terminal command:
`configure terminal`
4. Run the following command to add the software repository:
`software repository <url> <username> <password>`
5. Run the following command to exit the terminal:
`end`
6. Run the following commands to check and update the software update:
`software checkupdate`
`software update`
7. Run the reload command:
`reload`

