



# HEAT Endpoint Management and Security Suite 8.5

## 8.0 to 8.5 Upgrade Guide





---

# Notices

---

## Version Information

HEAT Endpoint Management and Security Suite 8.0 to 8.5 Upgrade Guide - HEAT Endpoint Management and Security Suite Version 8.5 - Published: November 2016

Document Number: 02\_244\_8.5\_163131120

## Copyright Information

Lumension Security Inc.,  
8660 East Hartford Drive, Suite 300  
Scottsdale, AZ 85255  
Phone: +1 888.725.7828  
Fax: +1 480.970.6323  
E-mail: [info@lumension.com](mailto:info@lumension.com)

**Copyright© 1999-2016; Lumension Security, Inc.; all rights reserved. Covered by one or more of U.S. Patent Nos. 6,990,660, 7,278,158, 7,487,495, 7,823,147, 7,870,606, and/or 7,894,514; other patents pending.** This manual, as well as the software described in it, is furnished under license. No part of this manual may be reproduced, stored in a retrieval system, or transmitted in any form – electronic, mechanical, recording, or otherwise – except as permitted by such license.

**LIMITATION OF LIABILITY/DISCLAIMER OF WARRANTY:** LUMENSION SECURITY, INC. (LUMENSION) MAKES NO REPRESENTATIONS OR WARRANTIES WITH REGARD TO THE ACCURACY OR COMPLETENESS OF THE INFORMATION PROVIDED IN THIS MANUAL. LUMENSION RESERVES THE RIGHT TO MAKE CHANGES TO THE INFORMATION DESCRIBED IN THIS MANUAL AT ANY TIME WITHOUT NOTICE AND WITHOUT OBLIGATION TO NOTIFY ANY PERSON OF SUCH CHANGES. THE INFORMATION PROVIDED IN THIS MANUAL IS PROVIDED "AS IS" AND WITHOUT WARRANTY OF ANY KIND, INCLUDING WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE INFORMATION PROVIDED IN THIS MANUAL IS NOT GUARANTEED OR WARRANTED TO PRODUCE ANY PARTICULAR RESULT, AND THE ADVICE AND STRATEGIES CONTAINED MAY NOT BE SUITABLE FOR EVERY ORGANIZATION. NO WARRANTY MAY BE CREATED OR EXTENDED WITH RESPECT TO THIS MANUAL BY SALES REPRESENTATIVES OR WRITTEN SALES MATERIALS. LUMENSION SHALL NOT BE LIABLE TO ANY PERSON WHATSOEVER FOR ANY LOSS OF PROFIT OR DATA OR ANY OTHER DAMAGES ARISING FROM THE USE OF THIS MANUAL, INCLUDING BUT NOT LIMITED TO DIRECT, INDIRECT, SPECIAL, INCIDENTAL, CONSEQUENTIAL, OR OTHER DAMAGES.

## Trademark Information

Lumension<sup>®</sup>, Lumension<sup>®</sup> Endpoint Management and Security Suite, Lumension<sup>®</sup> Endpoint Management Platform, Lumension<sup>®</sup> Patch and Remediation, Lumension<sup>®</sup> Enterprise Reporting, Lumension<sup>®</sup> Security Configuration Management, Lumension<sup>®</sup> Content Wizard, Lumension<sup>®</sup> AntiVirus, Lumension<sup>®</sup> Wake on LAN, Lumension<sup>®</sup> Power Management, Lumension<sup>®</sup> Application Control, Lumension<sup>®</sup> Device Control, Lumension<sup>®</sup> Endpoint Security, Lumension<sup>®</sup> Intelligent Whitelisting, PatchLink<sup>®</sup>, PatchLink<sup>®</sup> Update<sup>™</sup>, their associated logos, and all other Lumension trademarks and trade names used here are the property of Lumension Security, Inc. or its affiliates in the U.S. and other countries.

RSA Secured<sup>®</sup> is a registered trademark of RSA Security Inc.

Apache is a trademark of the Apache Software Foundation.

In addition, any other companies' names, trade names, trademarks, and products mentioned in this document may be either registered trademarks or trademarks of their respective owners.

## Feedback

Your feedback lets us know if we are meeting your documentation needs. E-mail the HEAT Software Technical Publications department at [techpubs@heatsoftware.com](mailto:techpubs@heatsoftware.com) to tell us what you like best, what you like least, and to report any inaccuracies.

---

# Table of Contents

---

<b>Chapter 1: Upgrading to 8.5.....</b>	<b>7</b>
Upgrade Preparations.....	7
Upgradable Server Versions.....	11
Upgradable Agent Versions.....	11
<b>Chapter 2: Upgrading Your Server.....</b>	<b>13</b>
Upgrading EMSS.....	13
<b>Chapter 3: Upgrading Your Agents.....</b>	<b>15</b>
Upgrading Endpoints.....	15
<b>Appendix A: Troubleshooting Your Upgrade.....</b>	<b>17</b>
Top Upgrade Issues.....	17
Frequently Asked Questions.....	17
<b>Appendix B: Upgrade Checklists.....</b>	<b>19</b>
Checklist to Upgrade to 8.5.....	19



---

# Chapter 1

---

## Upgrading to 8.5

---

### In this chapter:

- Upgrade Preparations

This upgrade guide is a resource to guide you through the upgrade to HEAT Endpoint Management and Security Suite 8.5.

### Upgrade Preparations

---

Before upgrading your HEAT Endpoint Management and Security Suite server to version 8.5, you must prepare your environment.

---

**EMSS Version Requirements** Only HEMSS 8.0 and later can be updated to 8.5.

- [Upgradable Server Versions](#) on page 11
- [Upgradable Agent Versions](#) on page 11

---

**Operating System Requirements**

The server must be installed on one of the following operating systems to be eligible to upgrade:

- Microsoft Windows Server 2012 R2  
(Standard, Datacenter, and Foundation editions)
- Microsoft Windows Server 2012  
(Standard, Datacenter, and Foundation editions)
- Microsoft Windows Web Server 2008 R2
- Microsoft Windows Server 2008 R2 SP1  
(Standard and Enterprise editions)
- Microsoft Windows Server 2008 SP2  
(Web, Standard, and Enterprise editions)

---

**Microsoft SQL Server Requirements**

The EMSS upgrade requires that your database instance for EMSS is SQL Server 2008 SP2+ or a later SQL Server release.

---

---

<b>User Permissions</b>	EMSS upgrades to 8.5 are completed using HEAT Installation Manager, which uses the <i>serviceadmin</i> account to update the database. This means that the user completing the upgrade does not require administrative rights to complete the upgrade. However, this user does require access to Installation Manager.
<b>Installation Manager Access</b>	Users performing the upgrade require access to Installation Manager, so they must meet one of the following requirements: <ul data-bbox="501 383 1265 479" style="list-style-type: none"><li>• The user must be assigned the administrator role within EMSS.</li><li>• The user must be assigned a custom role with the Installation Manager access right.</li></ul> See <a href="https://support.heatsoftware.com/">HEAT Endpoint Management and Security Suite User Guide (https://support.heatsoftware.com/)</a> for more information about users and roles.
<b>Firewall Settings</b>	EMSS 8.5 requires access to the following Web sites: <ul data-bbox="501 656 1210 1112" style="list-style-type: none"><li>• <a href="https://cdn.securegss.net">https://cdn.securegss.net</a></li><li>• <a href="http://cache.patchlinksecure.net">http://cache.patchlinksecure.net</a></li><li>• <a href="http://cache.lumension.com">http://cache.lumension.com</a></li><li>• <a href="http://gssnews.lumension.com">http://gssnews.lumension.com</a></li><li>• <a href="https://leicapi-lemss.lumension.com">https://leicapi-lemss.lumension.com</a></li><li>• <a href="http://download.windowsupdate.com">http://download.windowsupdate.com</a></li><li>• <a href="http://www.download.windowsupdate.com">http://www.download.windowsupdate.com</a> (For Microsoft content)</li><li>• <a href="http://go.microsoft.com">http://go.microsoft.com</a> (For Microsoft content)</li><li>• <a href="http://ardownload.adobe.com">http://ardownload.adobe.com</a> (For Adobe content)</li><li>• <a href="http://swupdl.adobe.com">http://swupdl.adobe.com</a> (For Adobe content)</li><li>• <a href="http://armdl.adobe.com">http://armdl.adobe.com</a> (For Adobe content)</li><li>• <a href="http://download.adobe.com">http://download.adobe.com</a> (For Adobe content)</li></ul> <hr/> <b>Important:</b> <ul data-bbox="539 1194 1290 1512" style="list-style-type: none"><li>• Refer to <a href="https://support.heatsoftware.com/">HEAT KnowledgeBase Article 22967 (https://support.heatsoftware.com)</a> and <a href="https://support.heatsoftware.com/">HEAT KnowledgeBase Article 22795 (https://support.heatsoftware.com)</a> for additional URLs and IP Addresses which may be required depending upon your configuration and content subscriptions.</li><li>• The firewalls on your server may require modification to access these URLs. If your corporate policies do not allow you to make the necessary firewall modifications, please contact <a href="mailto:support@lumension.com">HEAT Support (support@lumension.com)</a> for a recommended configuration.</li></ul>

---



---

<b>Additional Prerequisites</b>	During upgrade, you are prompted to install software bundled in with the upgrade if they are not already installed on the server. You may be prompted to reboot your server.
<b>AntiVirus Products</b>	AntiVirus products can prevent the necessary installation processes from running correctly. To ensure a successful installation of EMSS 8.5 you must stop or disable any third-party AntiVirus products (such as McAfee, Trend-micro, Symantec, and so on) before upgrade. If you use HEAT AntiVirus as your AntiVirus solution, you do not have to disable it.
<b>Storage Folder Backup</b>	Although the storage folder can grow quite large, creation of a backup content storage folder is recommended for Patch and Remediation users. By default, the storage folder is %Installation Directory%\Lumension\EMSS\Content.

---

**Database Backup**

During upgrade, HEAT Installation Manager updates the existing EMSS databases. Therefore, creation of database backups before upgrade is recommended.

**Note:** Some of the databases listed may not be present on server. Their presence is conditional based on your server configuration and module licensing.

Table 1: Database Names

Database Name	Product
PLUS	HEAT Endpoint Management and Security Suite
PLUS_Reports	HEAT Enterprise Reporting Client
SCM	HEAT Security Configuration Management
STAT_Guardian	HEAT Endpoint Management and Security Suite
UPCCommon	HEAT Endpoint Management and Security Suite
UPCExtended	HEAT Endpoint Management and Security Suite
ERS	HEAT Enterprise Reporting
ERS_Staging	HEAT Enterprise Reporting
ReportServer <sup>1</sup>	Microsoft SQL Server Reporting Services
ReportServerTempDB <sup>1</sup>	Microsoft SQL Server Reporting Services
SafeGuard <sup>2</sup>	powered by Sophos <sup>®</sup>
<ol style="list-style-type: none"> <li>Subscription features available in Microsoft SQL Server Reporting Services can be implemented in HEAT Enterprise Reporting. By default, the database names are <code>ReportServer</code> and <code>ReportServerTempDB</code>.</li> <li>Data protection capabilities in is enhanced with a full disk encryption add-on from Sophos. The installation of results in a <code>Safeguard</code> database.</li> </ol> <p><b>Note:</b> Refer to <i>Creating a Database Backup</i> in the <a href="https://support.heatsoftware.com/">HEAT Endpoint Management and Security Suite User Guide (https://support.heatsoftware.com/)</a> for additional information.</p>	

## Upgradable Server Versions

You can upgrade the following versions of the HEAT Endpoint Management and Security Suite server to 8.5.

You can view the version you have installed by opening the Web console and selecting **Help > Technical Support** and scrolling to **Suite Version Information**.

Release	Server Suite Version
HEMSS 8.4	8.4.0.10
HEMSS 8.3	8.3.0.10
HEMSS 8.2	8.2.0.10
HEMSS 8.1	8.1.0.10
HEMSS 8.0	8.0.0.10

**Note:** Upgrading from any pre-8.0 server to 8.5 is a two-step process. You must first upgrade your server to 8.4, and then upgrade to 8.5.

## Upgradable Agent Versions

You can upgrade the following versions of the HEAT Endpoint Management and Security Suite Agent to 8.5.

You can view the agent version installed on each endpoint by opening the Web console and selecting **Manage > Endpoints**.

Release	Agent Version
HEMSS Agent 8.4	8.4.0.10
HEMSS Agent 8.3	8.3.0.10
HEMSS Agent 8.2	8.2.0.10
HEMSS Agent 8.1	8.1.0.10
HEMSS Agent 8.0	8.0.0.10

**Note:** Upgrading from any pre-8.0 agent to 8.5 is a two-step process. You must first upgrade your server to 8.4, and then upgrade to 8.5.



---

# Chapter 2

---

## Upgrading Your Server

---

### In this chapter:

- Upgrading EMSS

After preparing for the upgrade, you can begin upgrading your HEAT Endpoint Management and Security Suite server to version 8.5.

Upgrades from HEAT Endpoint Management and Security Suite 8.0+ to 8.5 are only supported using Installation Manager.

## Upgrading EMSS

---

You can use HEAT Installation Manager to download new or update existing components and install them automatically.

### Prerequisites:

- Your server is running an upgradable version. See [Upgradable Server Versions](#) on page 11.
- Complete each item in the [Upgrade Preparations](#) on page 7.

Upgrade your old version of to 8.5 using Installation Manager.

1. Within the HEMSS Web console, select **Tools > Launch Installation Manager**.

**Step Result:** Installation Manager opens.

2. If necessary, upgrade Silverlight by clicking **Install**.
3. If necessary, upgrade Installation Manager by clicking **Install**. Click **Close** when the upgrade finishes.
4. If necessary, click **Reboot Server**, and then log back into the Web console.
5. Select the latest **Suite Version** radio button.
6. [Optional] Select any new components you want to install.  
When updating the suite version, modules already installed are automatically selected for update and cannot be deselected.
7. Click **Install**.

8. If the **Prerequisites** dialog opens, resolve the requirements before continuing. Complete the substeps below.

If the **Database backup recommended** dialog opens, proceed to [Step 9](#).

a) Click **Install** to install the requirements.

---

**Tip:**

- Click **Retry** to re-access the system for requirements.
  - Click **Print** to print the requirements.
- 

b) If necessary, **Reboot Server** and then log back in to EMSS.

9. If you haven't already, create a database backup before clicking **Next**.

**Step Result:** The **Ready to Install** dialog opens.

10. Click the **terms and conditions** to review the user agreement.

11. Click **Install** to begin installation. If prompted, click **OK** to proceed.

Installation takes several minutes.

12. After installation completes, review the **Confirmation** page. Click **Finish** when you are done.

---

**Tip:**

- Click **View install log** to review the install log.
  - Clear the **Launch** checkbox to cancel relaunch of the Web console.
- 

**Result:** Your server and modules are upgraded to version 8.5.

---

**After Completing This Task:**

Begin upgrading you endpoints to EMSS Agent 8.5.

---

---

# Chapter 3

---

## Upgrading Your Agents

---

### In this chapter:

- Upgrading Endpoints

After upgrading the server to 8.5, you can upgrade your agents to version 8.5 using the Web console.

### Upgrading Endpoints

---

From the **Endpoints** page, you can upgrade your endpoints to the latest version of the HEAT Endpoint Management and Security Suite Agent. You can update all the endpoints at once, but, as a test, you should upgrade just a few endpoints.

Upgrade your agents using the **Manage Agent Versions** dialog, which can be opened from any tab on the **Endpoints** page.

1. From the **Navigation Menu**, select **Manage > Endpoints**.
2. Select the endpoints you want to upgrade.
3. Click **Agent Versions**.

**Step Result:** The **Manage Agent Versions** dialog opens.


4. Select the latest agent version from the **Select One** menu and click **Apply to All Agents**. Pre-8.0 agents will upgrade to 8.4 as they can't upgrade directly to 8.5. A warning message will display to inform you of such a situation.

#### Tip:

- You can also select an agent version for each endpoint by using the **Agent Version** column menu.
- The agent versions available for upgrading can be selected from the **Agents** tab on the **Options** page.

5. Click **OK**.

**Result:** Your endpoints begin upgrading.

- Endpoint upgrade progress displays on the **Manage > Endpoints** page.
- Endpoints in the process of upgrading display the  icon in the **Agent Version** column.
- When the icons stops displaying, and the agent version updates, the upgrade is complete.

---

**After Completing This Task:**

If you had pre-8.0 endpoints in your environment that could not upgrade directly to 8.5, as they required upgrade to 8.4 first, perform this endpoint upgrade procedure once more.

---





---

# Appendix

# A

---

## Troubleshooting Your Upgrade

---

### In this appendix:

- Top Upgrade Issues
- Frequently Asked Questions

The following topics will assist you in the unlikely event that you experience difficulty when upgrading to HEAT Endpoint Management and Security Suite 8.5.

### Top Upgrade Issues

---

The following list identifies the top reasons why you cannot complete upgrade.

1. You do not have adequate permission to perform the upgrade. Only users assigned the *Administrator* role (or the *Installation Manager* access right) can access Installation Manager.
2. Your system does not have the minimum required Windows components, or does not meet the minimum system requirements.  
Refer to the [HEAT Endpoint Management and Security Suite: Server Installation Guide \(https://support.heatsoftware.com\)](https://support.heatsoftware.com) for a complete list of both required and recommended system requirements.
3. Failure to stop or disable an AntiVirus product (such as McAfee, Trend-micro, Symantec, and so on) prior to running the upgrade.

**Note:** An AntiVirus product can prevent processes from running correctly during the installation. For best results, stop or disable all AntiVirus services prior to the upgrade. If you have an upgrade issue and you currently have an AntiVirus product running, HEAT Support will be unable to assist you until the AntiVirus product has been disabled.

### Frequently Asked Questions

---

When preparing for, or while performing an upgrade, users often ask the following questions.

1. Is there a cost for the upgrade?

No, as long as you are a current HEAT customer you can download and install the latest version without an additional charge.

2. I cannot remember my login and/or password to the [HEAT Self Service Portal \(https://support.heatsoftware.com\)](https://support.heatsoftware.com). What do I do?

Click the red **Lost your Password** link and follow the instructions. A new password will be sent to you. If you receive a message indicating that the email you entered is not recognized, try using a different email address or contact [HEAT Self Service Support \(https://support.heatsoftware.com\)](https://support.heatsoftware.com) for assistance.

3. If I upgrade my server now, do I have to immediately upgrade my agents?

No, it is not necessary for you to upgrade your agents at the same time that you upgrade your server. We do, however, encourage you to upgrade them to take advantage of the new EMSS Agents.

4. My upgrade appeared to go smoothly, however my replication appears to be taking a long time. How long should this first replication take?

After the upgrade to EMSS 8.5, it is not uncommon for the initial replication to take anywhere from 30 minutes to 2 hours to complete, depending upon your network speed and available bandwidth.

5. What should I do if I want to get a separate license to build and test my EMSS server before I upgrade or move my agents?

Contact your HEAT Account Manager for additional details. If necessary, refer to <https://heatsoftware.com/support/support-email-contacts/> for contact details.

6. Who do I contact if I have questions or would like assistance with the upgrade?

Please contact the [HEAT Customer Success Team \(EndPointSecurity.Support@HEATsoftware.com\)](mailto:EndPointSecurity.Support@HEATsoftware.com) with any questions or requests for assistance.

7. Who do I contact if I have problems with the upgrade or the upgrade fails?

Please contact the HEAT Support Team, toll free, at (888) 725-7828, option 2..

---

# Appendix

# B

---

## Upgrade Checklists

---

### In this appendix:

- Checklist to Upgrade to 8.5

The following checklists will assist you when upgrading to 8.5.

### Checklist to Upgrade to 8.5

---

The following checklist identifies the tasks necessary to upgrade to HEAT Endpoint Management and Security Suite (EMSS) 8.5. By upgrading to EMSS 8.5 you can take advantage of new features.

- Your firewall is configured to access required URLs.  
Refer to *Firewall Settings* under [Upgrade Preparations](#) on page 7 for details.
- You are logged into the Web console as a user with access to Installation Manager.

---

You have disabled any AntiVirus products running on your server before running Installation Manager. If you use HEAT AntiVirus as your AntiVirus, you can leave it running.

- Note:** An AntiVirus product can prevent the necessary installation processes from running correctly.
-

You have created a backup of the databases listed below so that your EMSS server can roll back if upgrade fails.

**Note:** Some databases may not be present on your system, as their presence is determined by your server configuration and licensed modules.

Table 2: Database Names

Database Name	Product
PLUS	HEAT Endpoint Management and Security Suite
PLUS_Reports	HEAT Enterprise Reporting Client
SCM	HEAT Security Configuration Management
STAT_Guardian	HEAT Endpoint Management and Security Suite
UPCCommon	HEAT Endpoint Management and Security Suite
UPCExtended	HEAT Endpoint Management and Security Suite
ERS	HEAT Enterprise Reporting
ERS_Staging	HEAT Enterprise Reporting
ReportServer <sup>(1)</sup>	Microsoft SQL Server Reporting Services
ReportServerTempDB <sup>(1)</sup>	Microsoft SQL Server Reporting Services
SafeGuard <sup>(2)</sup>	powered by Sophos®
<p>(1) Subscription features available in Microsoft SQL Server Reporting Services can be implemented in HEAT Enterprise Reporting. By default, the database names are <code>ReportServer</code> and <code>ReportServerTempDB</code>.</p> <p>(2) Data protection capabilities in is enhanced with a full disk encryption add-on from Sophos. The installation of results in a <code>Safeguard</code> database.</p>	

- You have used Installation Manager to upgrade the EMSS platform and components. Refer to [Upgrading EMSS](#) on page 13 for step-by-step instructions.
- You have upgraded your agents. Refer to [Upgrading Your Agents](#) on page 15 for additional details.